

Clp  
1.14

Generated by Doxygen 1.7.4

Wed Nov 9 2011 10:10:29

## Contents

|          |  |          |
|----------|--|----------|
| <b>1</b> | <b>Class Index</b>                               | <b>1</b> |
| 1.1      | Class Hierarchy . . . . .                        | 1        |
| <b>2</b> | <b>Class Index</b>                               | <b>4</b> |
| 2.1      | Class List . . . . .                             | 4        |
| <b>3</b> | <b>Class Documentation</b>                       | <b>7</b> |
| 3.1      | blockStruct Struct Reference . . . . .           | 7        |
| 3.1.1    | Detailed Description . . . . .                   | 7        |
| 3.2      | ClpNode::branchState Struct Reference . . . . .  | 8        |
| 3.2.1    | Detailed Description . . . . .                   | 8        |
| 3.3      | CbcOrClpParam Class Reference . . . . .          | 8        |
| 3.3.1    | Detailed Description . . . . .                   | 12       |
| 3.4      | ClpCholeskyBase Class Reference . . . . .        | 12       |
| 3.4.1    | Detailed Description . . . . .                   | 17       |
| 3.4.2    | Constructor & Destructor Documentation . . . . . | 17       |
| 3.4.3    | Member Function Documentation . . . . .          | 17       |
| 3.5      | ClpCholeskyDense Class Reference . . . . .       | 19       |
| 3.5.1    | Detailed Description . . . . .                   | 20       |
| 3.5.2    | Constructor & Destructor Documentation . . . . . | 21       |
| 3.5.3    | Member Function Documentation . . . . .          | 21       |
| 3.6      | ClpCholeskyDenseC Struct Reference . . . . .     | 21       |
| 3.6.1    | Detailed Description . . . . .                   | 22       |
| 3.7      | ClpCholeskyMumps Class Reference . . . . .       | 22       |
| 3.7.1    | Detailed Description . . . . .                   | 23       |
| 3.7.2    | Constructor & Destructor Documentation . . . . . | 24       |
| 3.7.3    | Member Function Documentation . . . . .          | 24       |
| 3.8      | ClpCholeskyTaucs Class Reference . . . . .       | 24       |
| 3.8.1    | Detailed Description . . . . .                   | 26       |
| 3.8.2    | Constructor & Destructor Documentation . . . . . | 26       |
| 3.8.3    | Member Function Documentation . . . . .          | 26       |
| 3.9      | ClpCholeskyUfl Class Reference . . . . .         | 27       |
| 3.9.1    | Detailed Description . . . . .                   | 28       |

|        |  |    |
|--------|--|----|
| 3.9.2  | Constructor & Destructor Documentation . . . . . | 29 |
| 3.9.3  | Member Function Documentation . . . . .          | 29 |
| 3.10   | ClpCholeskyWssmp Class Reference . . . . .       | 30 |
| 3.10.1 | Detailed Description . . . . .                   | 31 |
| 3.10.2 | Constructor & Destructor Documentation . . . . . | 31 |
| 3.10.3 | Member Function Documentation . . . . .          | 31 |
| 3.11   | ClpCholeskyWssmpKKT Class Reference . . . . .    | 32 |
| 3.11.1 | Detailed Description . . . . .                   | 34 |
| 3.11.2 | Constructor & Destructor Documentation . . . . . | 34 |
| 3.11.3 | Member Function Documentation . . . . .          | 34 |
| 3.12   | ClpConstraint Class Reference . . . . .          | 35 |
| 3.12.1 | Detailed Description . . . . .                   | 36 |
| 3.12.2 | Member Function Documentation . . . . .          | 37 |
| 3.13   | ClpConstraintLinear Class Reference . . . . .    | 37 |
| 3.13.1 | Detailed Description . . . . .                   | 39 |
| 3.13.2 | Member Function Documentation . . . . .          | 39 |
| 3.14   | ClpConstraintQuadratic Class Reference . . . . . | 40 |
| 3.14.1 | Detailed Description . . . . .                   | 42 |
| 3.14.2 | Member Function Documentation . . . . .          | 42 |
| 3.15   | ClpDataSave Class Reference . . . . .            | 43 |
| 3.15.1 | Detailed Description . . . . .                   | 43 |
| 3.16   | ClpDisasterHandler Class Reference . . . . .     | 44 |
| 3.16.1 | Detailed Description . . . . .                   | 46 |
| 3.16.2 | Constructor & Destructor Documentation . . . . . | 46 |
| 3.16.3 | Member Function Documentation . . . . .          | 46 |
| 3.17   | ClpDualRowDantzig Class Reference . . . . .      | 47 |
| 3.17.1 | Detailed Description . . . . .                   | 49 |
| 3.17.2 | Member Function Documentation . . . . .          | 49 |
| 3.18   | ClpDualRowPivot Class Reference . . . . .        | 49 |
| 3.18.1 | Detailed Description . . . . .                   | 53 |
| 3.18.2 | Member Function Documentation . . . . .          | 53 |
| 3.19   | ClpDualRowSteepest Class Reference . . . . .     | 53 |
| 3.19.1 | Detailed Description . . . . .                   | 56 |
| 3.19.2 | Constructor & Destructor Documentation . . . . . | 57 |

|        |   |    |
|--------|---|----|
| 3.19.3 | Member Function Documentation . . . . .           | 57 |
| 3.20   | ClpDummyMatrix Class Reference . . . . .          | 57 |
| 3.20.1 | Detailed Description . . . . .                    | 60 |
| 3.20.2 | Constructor & Destructor Documentation . . . . .  | 61 |
| 3.20.3 | Member Function Documentation . . . . .           | 61 |
| 3.21   | ClpDynamicExampleMatrix Class Reference . . . . . | 63 |
| 3.21.1 | Detailed Description . . . . .                    | 67 |
| 3.21.2 | Constructor & Destructor Documentation . . . . .  | 67 |
| 3.21.3 | Member Function Documentation . . . . .           | 67 |
| 3.21.4 | Member Data Documentation . . . . .               | 68 |
| 3.22   | ClpDynamicMatrix Class Reference . . . . .        | 68 |
| 3.22.1 | Detailed Description . . . . .                    | 74 |
| 3.22.2 | Constructor & Destructor Documentation . . . . .  | 75 |
| 3.22.3 | Member Function Documentation . . . . .           | 75 |
| 3.22.4 | Member Data Documentation . . . . .               | 76 |
| 3.23   | ClpEventHandler Class Reference . . . . .         | 77 |
| 3.23.1 | Detailed Description . . . . .                    | 78 |
| 3.23.2 | Member Enumeration Documentation . . . . .        | 79 |
| 3.23.3 | Constructor & Destructor Documentation . . . . .  | 79 |
| 3.23.4 | Member Function Documentation . . . . .           | 79 |
| 3.24   | ClpFactorization Class Reference . . . . .        | 79 |
| 3.24.1 | Detailed Description . . . . .                    | 84 |
| 3.24.2 | Constructor & Destructor Documentation . . . . .  | 84 |
| 3.24.3 | Member Function Documentation . . . . .           | 84 |
| 3.25   | ClpGubDynamicMatrix Class Reference . . . . .     | 85 |
| 3.25.1 | Detailed Description . . . . .                    | 89 |
| 3.25.2 | Constructor & Destructor Documentation . . . . .  | 89 |
| 3.25.3 | Member Function Documentation . . . . .           | 90 |
| 3.26   | ClpGubMatrix Class Reference . . . . .            | 90 |
| 3.26.1 | Detailed Description . . . . .                    | 96 |
| 3.26.2 | Constructor & Destructor Documentation . . . . .  | 96 |
| 3.26.3 | Member Function Documentation . . . . .           | 97 |
| 3.26.4 | Member Data Documentation . . . . .               | 98 |
| 3.27   | ClpHashValue Class Reference . . . . .            | 99 |

|   |     |
|---|-----|
| 3.27.1 Detailed Description . . . . .                       | 100 |
| 3.27.2 Constructor & Destructor Documentation . . . . .     | 100 |
| 3.28 ClpInterior Class Reference . . . . .                  | 101 |
| 3.28.1 Detailed Description . . . . .                       | 109 |
| 3.28.2 Constructor & Destructor Documentation . . . . .     | 109 |
| 3.28.3 Member Function Documentation . . . . .              | 110 |
| 3.28.4 Friends And Related Function Documentation . . . . . | 111 |
| 3.28.5 Member Data Documentation . . . . .                  | 111 |
| 3.29 ClpLinearObjective Class Reference . . . . .           | 111 |
| 3.29.1 Detailed Description . . . . .                       | 113 |
| 3.29.2 Constructor & Destructor Documentation . . . . .     | 113 |
| 3.29.3 Member Function Documentation . . . . .              | 113 |
| 3.30 ClpLsqqr Class Reference . . . . .                     | 114 |
| 3.30.1 Detailed Description . . . . .                       | 115 |
| 3.31 ClpMatrixBase Class Reference . . . . .                | 117 |
| 3.31.1 Detailed Description . . . . .                       | 123 |
| 3.31.2 Constructor & Destructor Documentation . . . . .     | 123 |
| 3.31.3 Member Function Documentation . . . . .              | 123 |
| 3.31.4 Member Data Documentation . . . . .                  | 129 |
| 3.32 ClpMessage Class Reference . . . . .                   | 130 |
| 3.32.1 Detailed Description . . . . .                       | 130 |
| 3.33 ClpModel Class Reference . . . . .                     | 130 |
| 3.33.1 Detailed Description . . . . .                       | 144 |
| 3.33.2 Constructor & Destructor Documentation . . . . .     | 144 |
| 3.33.3 Member Function Documentation . . . . .              | 144 |
| 3.33.4 Member Data Documentation . . . . .                  | 150 |
| 3.34 ClpNetworkBasis Class Reference . . . . .              | 151 |
| 3.34.1 Detailed Description . . . . .                       | 153 |
| 3.34.2 Member Function Documentation . . . . .              | 153 |
| 3.35 ClpNetworkMatrix Class Reference . . . . .             | 153 |
| 3.35.1 Detailed Description . . . . .                       | 157 |
| 3.35.2 Constructor & Destructor Documentation . . . . .     | 157 |
| 3.35.3 Member Function Documentation . . . . .              | 158 |
| 3.36 ClpNode Class Reference . . . . .                      | 162 |

|   |     |
|---|-----|
| 3.36.1 Detailed Description . . . . .                   | 165 |
| 3.36.2 Constructor & Destructor Documentation . . . . . | 165 |
| 3.37 ClpNodeStuff Class Reference . . . . .             | 166 |
| 3.37.1 Detailed Description . . . . .                   | 168 |
| 3.37.2 Constructor & Destructor Documentation . . . . . | 168 |
| 3.38 ClpNonLinearCost Class Reference . . . . .         | 169 |
| 3.38.1 Detailed Description . . . . .                   | 171 |
| 3.38.2 Constructor & Destructor Documentation . . . . . | 171 |
| 3.38.3 Member Function Documentation . . . . .          | 172 |
| 3.39 ClpObjective Class Reference . . . . .             | 172 |
| 3.39.1 Detailed Description . . . . .                   | 174 |
| 3.39.2 Member Function Documentation . . . . .          | 175 |
| 3.40 ClpPackedMatrix Class Reference . . . . .          | 176 |
| 3.40.1 Detailed Description . . . . .                   | 182 |
| 3.40.2 Constructor & Destructor Documentation . . . . . | 182 |
| 3.40.3 Member Function Documentation . . . . .          | 182 |
| 3.41 ClpPackedMatrix2 Class Reference . . . . .         | 187 |
| 3.41.1 Detailed Description . . . . .                   | 188 |
| 3.41.2 Constructor & Destructor Documentation . . . . . | 188 |
| 3.41.3 Member Function Documentation . . . . .          | 189 |
| 3.42 ClpPackedMatrix3 Class Reference . . . . .         | 189 |
| 3.42.1 Detailed Description . . . . .                   | 191 |
| 3.42.2 Constructor & Destructor Documentation . . . . . | 191 |
| 3.42.3 Member Function Documentation . . . . .          | 191 |
| 3.43 ClpPdco Class Reference . . . . .                  | 191 |
| 3.43.1 Detailed Description . . . . .                   | 193 |
| 3.43.2 Member Function Documentation . . . . .          | 193 |
| 3.44 ClpPdcoBase Class Reference . . . . .              | 194 |
| 3.44.1 Detailed Description . . . . .                   | 195 |
| 3.44.2 Constructor & Destructor Documentation . . . . . | 195 |
| 3.45 ClpPlusMinusOneMatrix Class Reference . . . . .    | 196 |
| 3.45.1 Detailed Description . . . . .                   | 200 |
| 3.45.2 Constructor & Destructor Documentation . . . . . | 200 |
| 3.45.3 Member Function Documentation . . . . .          | 200 |

|   |     |
|---|-----|
| 3.46 ClpPredictorCorrector Class Reference . . . . .        | 204 |
| 3.46.1 Detailed Description . . . . .                       | 206 |
| 3.46.2 Member Function Documentation . . . . .              | 207 |
| 3.47 ClpPresolve Class Reference . . . . .                  | 207 |
| 3.47.1 Detailed Description . . . . .                       | 210 |
| 3.47.2 Member Function Documentation . . . . .              | 210 |
| 3.48 ClpPrimalColumnDantzig Class Reference . . . . .       | 211 |
| 3.48.1 Detailed Description . . . . .                       | 213 |
| 3.48.2 Member Function Documentation . . . . .              | 213 |
| 3.49 ClpPrimalColumnPivot Class Reference . . . . .         | 213 |
| 3.49.1 Detailed Description . . . . .                       | 216 |
| 3.49.2 Member Function Documentation . . . . .              | 216 |
| 3.50 ClpPrimalColumnSteepest Class Reference . . . . .      | 217 |
| 3.50.1 Detailed Description . . . . .                       | 221 |
| 3.50.2 Constructor & Destructor Documentation . . . . .     | 221 |
| 3.50.3 Member Function Documentation . . . . .              | 222 |
| 3.51 ClpPrimalQuadraticDantzig Class Reference . . . . .    | 222 |
| 3.51.1 Detailed Description . . . . .                       | 224 |
| 3.51.2 Member Function Documentation . . . . .              | 224 |
| 3.52 ClpQuadraticObjective Class Reference . . . . .        | 224 |
| 3.52.1 Detailed Description . . . . .                       | 227 |
| 3.52.2 Constructor & Destructor Documentation . . . . .     | 227 |
| 3.52.3 Member Function Documentation . . . . .              | 227 |
| 3.53 ClpSimplex Class Reference . . . . .                   | 228 |
| 3.53.1 Detailed Description . . . . .                       | 247 |
| 3.53.2 Member Enumeration Documentation . . . . .           | 247 |
| 3.53.3 Constructor & Destructor Documentation . . . . .     | 247 |
| 3.53.4 Member Function Documentation . . . . .              | 248 |
| 3.53.5 Friends And Related Function Documentation . . . . . | 258 |
| 3.53.6 Member Data Documentation . . . . .                  | 259 |
| 3.54 ClpSimplexDual Class Reference . . . . .               | 260 |
| 3.54.1 Detailed Description . . . . .                       | 263 |
| 3.54.2 Member Function Documentation . . . . .              | 263 |
| 3.55 ClpSimplexNonlinear Class Reference . . . . .          | 267 |

|  |     |
|--|-----|
| 3.55.1 Detailed Description . . . . .                      | 270 |
| 3.55.2 Member Function Documentation . . . . .             | 270 |
| 3.56 ClpSimplexOther Class Reference . . . . .             | 271 |
| 3.56.1 Detailed Description . . . . .                      | 275 |
| 3.56.2 Member Function Documentation . . . . .             | 275 |
| 3.57 ClpSimplexPrimal Class Reference . . . . .            | 277 |
| 3.57.1 Detailed Description . . . . .                      | 280 |
| 3.57.2 Member Function Documentation . . . . .             | 280 |
| 3.58 ClpSimplexProgress Class Reference . . . . .          | 282 |
| 3.58.1 Detailed Description . . . . .                      | 285 |
| 3.59 ClpSolve Class Reference . . . . .                    | 285 |
| 3.59.1 Detailed Description . . . . .                      | 287 |
| 3.59.2 Member Function Documentation . . . . .             | 287 |
| 3.60 ClpTrustedData Struct Reference . . . . .             | 288 |
| 3.60.1 Detailed Description . . . . .                      | 288 |
| 3.61 ClpHashValue::CoinHashLink Struct Reference . . . . . | 288 |
| 3.61.1 Detailed Description . . . . .                      | 288 |
| 3.62 Idiot Class Reference . . . . .                       | 288 |
| 3.62.1 Detailed Description . . . . .                      | 290 |
| 3.62.2 Member Function Documentation . . . . .             | 290 |
| 3.63 IdiotResult Struct Reference . . . . .                | 291 |
| 3.63.1 Detailed Description . . . . .                      | 292 |
| 3.64 Info Struct Reference . . . . .                       | 292 |
| 3.64.1 Detailed Description . . . . .                      | 292 |
| 3.65 MyEventHandler Class Reference . . . . .              | 292 |
| 3.65.1 Detailed Description . . . . .                      | 293 |
| 3.65.2 Constructor & Destructor Documentation . . . . .    | 294 |
| 3.65.3 Member Function Documentation . . . . .             | 294 |
| 3.66 MyMessageHandler Class Reference . . . . .            | 294 |
| 3.66.1 Detailed Description . . . . .                      | 295 |
| 3.66.2 Constructor & Destructor Documentation . . . . .    | 296 |
| 3.67 myPdco Class Reference . . . . .                      | 296 |
| 3.67.1 Detailed Description . . . . .                      | 298 |
| 3.67.2 Constructor & Destructor Documentation . . . . .    | 298 |

|   |     |
|---|-----|
| 3.68 Options Struct Reference . . . . .                     | 298 |
| 3.68.1 Detailed Description . . . . .                       | 298 |
| 3.69 OsiClpDisasterHandler Class Reference . . . . .        | 299 |
| 3.69.1 Detailed Description . . . . .                       | 301 |
| 3.69.2 Constructor & Destructor Documentation . . . . .     | 301 |
| 3.69.3 Member Function Documentation . . . . .              | 301 |
| 3.70 OsiClpSolverInterface Class Reference . . . . .        | 301 |
| 3.70.1 Detailed Description . . . . .                       | 316 |
| 3.70.2 Member Function Documentation . . . . .              | 316 |
| 3.70.3 Friends And Related Function Documentation . . . . . | 328 |
| 3.70.4 Member Data Documentation . . . . .                  | 328 |
| 3.71 Outfo Struct Reference . . . . .                       | 330 |
| 3.71.1 Detailed Description . . . . .                       | 330 |

## 1 Class Index

### 1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

```

std::basic_fstream< char >
std::basic_fstream< wchar_t >
std::basic_ifstream< char >
std::basic_ifstream< wchar_t >
std::basic_ios< char >
std::basic_ios< wchar_t >
std::basic_iostream< char >
std::basic_iostream< wchar_t >
std::basic_istream< char >
std::basic_istream< wchar_t >
std::basic_istreamstream< char >
std::basic_istreamstream< wchar_t >
std::basic_ofstream< char >
std::basic_ofstream< wchar_t >
std::basic_ostream< char >
std::basic_ostream< wchar_t >
std::basic_ostreamstream< char >
std::basic_ostreamstream< wchar_t >
std::basic_string< char >
std::basic_string< wchar_t >
std::basic_stringstream< char >
std::basic_stringstream< wchar_t >

```

|                               |            |
|-------------------------------|------------|
| <b>blockStruct</b>            | <b>7</b>   |
| <b>ClpNode::branchState</b>   | <b>8</b>   |
| <b>CbcOrClpParam</b>          | <b>8</b>   |
| <b>ClpCholeskyBase</b>        | <b>12</b>  |
| <b>ClpCholeskyDense</b>       | <b>19</b>  |
| <b>ClpCholeskyMumps</b>       | <b>22</b>  |
| <b>ClpCholeskyTaucs</b>       | <b>24</b>  |
| <b>ClpCholeskyUfl</b>         | <b>27</b>  |
| <b>ClpCholeskyWssmp</b>       | <b>30</b>  |
| <b>ClpCholeskyWssmpKKT</b>    | <b>32</b>  |
| <b>ClpCholeskyDenseC</b>      | <b>21</b>  |
| <b>ClpConstraint</b>          | <b>35</b>  |
| <b>ClpConstraintLinear</b>    | <b>37</b>  |
| <b>ClpConstraintQuadratic</b> | <b>40</b>  |
| <b>ClpDataSave</b>            | <b>43</b>  |
| <b>ClpDisasterHandler</b>     | <b>44</b>  |
| <b>OsiClpDisasterHandler</b>  | <b>299</b> |
| <b>ClpDualRowPivot</b>        | <b>49</b>  |
| <b>ClpDualRowDantzig</b>      | <b>47</b>  |
| <b>ClpDualRowSteepest</b>     | <b>53</b>  |
| <b>ClpEventHandler</b>        | <b>77</b>  |
| <b>MyEventHandler</b>         | <b>292</b> |
| <b>ClpFactorization</b>       | <b>79</b>  |
| <b>ClpHashValue</b>           | <b>99</b>  |
| <b>ClpLsqr</b>                | <b>114</b> |
| <b>ClpMatrixBase</b>          | <b>117</b> |
| <b>ClpDummyMatrix</b>         | <b>57</b>  |

|                         |     |
|-------------------------|-----|
| ClpNetworkMatrix        | 153 |
| ClpPackedMatrix         | 176 |
| ClpDynamicMatrix        | 68  |
| ClpDynamicExampleMatrix | 63  |
| ClpGubMatrix            | 90  |
| ClpGubDynamicMatrix     | 85  |
| ClpPlusMinusOneMatrix   | 196 |
| ClpMessage              | 130 |
| ClpModel                | 130 |
| ClpInterior             | 101 |
| ClpPdco                 | 191 |
| ClpPredictorCorrector   | 204 |
| ClpSimplex              | 228 |
| ClpSimplexDual          | 260 |
| ClpSimplexOther         | 271 |
| ClpSimplexPrimal        | 277 |
| ClpSimplexNonlinear     | 267 |
| ClpNetworkBasis         | 151 |
| ClpNode                 | 162 |
| ClpNodeStuff            | 166 |
| ClpNonLinearCost        | 169 |
| ClpObjective            | 172 |
| ClpLinearObjective      | 111 |
| ClpQuadraticObjective   | 224 |
| ClpPackedMatrix2        | 187 |
| ClpPackedMatrix3        | 189 |
| ClpPdcoBase             | 194 |

|  |                     |
|--|---------------------|
| <a href="#">myPdco</a>                     | <a href="#">296</a> |
| <a href="#">ClpPresolve</a>                | <a href="#">207</a> |
| <a href="#">ClpPrimalColumnPivot</a>       | <a href="#">213</a> |
| <a href="#">ClpPrimalColumnDantzig</a>     | <a href="#">211</a> |
| <a href="#">ClpPrimalColumnSteepest</a>    | <a href="#">217</a> |
| <a href="#">ClpPrimalQuadraticDantzig</a>  | <a href="#">222</a> |
| <a href="#">ClpSimplexProgress</a>         | <a href="#">282</a> |
| <a href="#">ClpSolve</a>                   | <a href="#">285</a> |
| <a href="#">ClpTrustedData</a>             | <a href="#">288</a> |
| <a href="#">ClpHashValue::CoinHashLink</a> | <a href="#">288</a> |
| <a href="#">Idiot</a>                      | <a href="#">288</a> |
| <a href="#">IdiotResult</a>                | <a href="#">291</a> |
| <a href="#">Info</a>                       | <a href="#">292</a> |
| <a href="#">MyMessageHandler</a>           | <a href="#">294</a> |
| <a href="#">Options</a>                    | <a href="#">298</a> |
| <a href="#">OsiClpSolverInterface</a>      | <a href="#">301</a> |
| <a href="#">Outfo</a>                      | <a href="#">330</a> |

## 2 Class Index

### 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

|   |                    |
|---|--------------------|
| <a href="#">blockStruct</a>   | <a href="#">7</a>  |
| <a href="#">ClpNode::branchState</a>  | <a href="#">8</a>  |
| <a href="#">CbcOrClpParam</a> (Very simple class for setting parameters )                                 | <a href="#">8</a>  |
| <a href="#">ClpCholeskyBase</a> (Base class for Clp Cholesky factorization Will do better factorization ) | <a href="#">12</a> |
| <a href="#">ClpCholeskyDense</a>  | <a href="#">19</a> |

|  |     |
|--|-----|
| <a href="#">ClpCholeskyDenseC</a>  | 21  |
| <a href="#">ClpCholeskyMumps</a> (Mumps class for Clp Cholesky factorization )   | 22  |
| <a href="#">ClpCholeskyTaucs</a> (Taucs class for Clp Cholesky factorization )   | 24  |
| <a href="#">ClpCholeskyUfl</a> (Ufl class for Clp Cholesky factorization )   | 27  |
| <a href="#">ClpCholeskyWssmp</a> (Wssmp class for Clp Cholesky factorization )   | 30  |
| <a href="#">ClpCholeskyWssmpKKT</a> (WssmpKKT class for Clp Cholesky factorization )   | 32  |
| <a href="#">ClpConstraint</a> (Constraint Abstract Base Class )  | 35  |
| <a href="#">ClpConstraintLinear</a> (Linear Constraint Class )   | 37  |
| <a href="#">ClpConstraintQuadratic</a> (Quadratic Constraint Class )   | 40  |
| <a href="#">ClpDataSave</a> (This is a tiny class where data can be saved round calls )  | 43  |
| <a href="#">ClpDisasterHandler</a> (Base class for Clp disaster handling )   | 44  |
| <a href="#">ClpDualRowDantzig</a> (Dual Row Pivot Dantzig Algorithm Class )  | 47  |
| <a href="#">ClpDualRowPivot</a> (Dual Row Pivot Abstract Base Class )  | 49  |
| <a href="#">ClpDualRowSteepest</a> (Dual Row Pivot Steepest Edge Algorithm Class )   | 53  |
| <a href="#">ClpDummyMatrix</a> (This implements a dummy matrix as derived from <a href="#">ClpMatrixBase</a> )                       | 57  |
| <a href="#">ClpDynamicExampleMatrix</a> (This implements a dynamic matrix when we have a limit on the number of "interesting rows" ) | 63  |
| <a href="#">ClpDynamicMatrix</a> (This implements a dynamic matrix when we have a limit on the number of "interesting rows" )        | 68  |
| <a href="#">ClpEventHandler</a> (Base class for Clp event handling )   | 77  |
| <a href="#">ClpFactorization</a> (This just implements CoinFactorization when an <a href="#">ClpMatrixBase</a> object is passed )    | 79  |
| <a href="#">ClpGubDynamicMatrix</a> (This implements Gub rows plus a <a href="#">ClpPackedMatrix</a> )                               | 85  |
| <a href="#">ClpGubMatrix</a> (This implements Gub rows plus a <a href="#">ClpPackedMatrix</a> )                                      | 90  |
| <a href="#">ClpHashValue</a>   | 99  |
| <a href="#">ClpInterior</a> (This solves LPs using interior point methods )  | 101 |
| <a href="#">ClpLinearObjective</a> (Linear Objective Class )   | 111 |

|   |     |
|---|-----|
| <a href="#">ClpLsq</a> (This class implements LSQR )  | 114 |
| <a href="#">ClpMatrixBase</a> (Abstract base class for Clp Matrices )   | 117 |
| <a href="#">ClpMessage</a> (This deals with Clp messages (as against Osi messages etc) )                                      | 130 |
| <a href="#">ClpModel</a>  | 130 |
| <a href="#">ClpNetworkBasis</a> (This deals with Factorization and Updates for network structures )                           | 151 |
| <a href="#">ClpNetworkMatrix</a> (This implements a simple network matrix as derived from <a href="#">ClpMatrixBase</a> )     | 153 |
| <a href="#">ClpNode</a>   | 162 |
| <a href="#">ClpNodeStuff</a>  | 166 |
| <a href="#">ClpNonLinearCost</a>  | 169 |
| <a href="#">ClpObjective</a> (Objective Abstract Base Class )   | 172 |
| <a href="#">ClpPackedMatrix</a>   | 176 |
| <a href="#">ClpPackedMatrix2</a>  | 187 |
| <a href="#">ClpPackedMatrix3</a>  | 189 |
| <a href="#">ClpPdco</a> (This solves problems in Primal Dual Convex Optimization )  | 191 |
| <a href="#">ClpPdcoBase</a> (Abstract base class for tailoring everything for Pdco )  | 194 |
| <a href="#">ClpPlusMinusOneMatrix</a> (This implements a simple +- one matrix as derived from <a href="#">ClpMatrixBase</a> ) | 196 |
| <a href="#">ClpPredictorCorrector</a> (This solves LPs using the predictor-corrector method due to Mehrotra )                 | 204 |
| <a href="#">ClpPresolve</a> (This is the Clp interface to CoinPresolve )  | 207 |
| <a href="#">ClpPrimalColumnDantzig</a> (Primal Column Pivot Dantzig Algorithm Class )   | 211 |
| <a href="#">ClpPrimalColumnPivot</a> (Primal Column Pivot Abstract Base Class )   | 213 |
| <a href="#">ClpPrimalColumnSteepest</a> (Primal Column Pivot Steepest Edge Algorithm Class )                                  | 217 |
| <a href="#">ClpPrimalQuadraticDantzig</a> (Primal Column Pivot Dantzig Algorithm Class )                                      | 222 |
| <a href="#">ClpQuadraticObjective</a> (Quadratic Objective Class )  | 224 |

|   |     |
|---|-----|
| <a href="#">ClpSimplex</a> (This solves LPs using the simplex method )  | 228 |
| <a href="#">ClpSimplexDual</a> (This solves LPs using the dual simplex method )                                 | 260 |
| <a href="#">ClpSimplexNonlinear</a> (This solves non-linear LPs using the primal simplex method )               | 267 |
| <a href="#">ClpSimplexOther</a> (This is for Simplex stuff which is neither dual nor primal )                   | 271 |
| <a href="#">ClpSimplexPrimal</a> (This solves LPs using the primal simplex method )                             | 277 |
| <a href="#">ClpSimplexProgress</a> (For saving extra information to see if looping )                            | 282 |
| <a href="#">ClpSolve</a> (This is a very simple class to guide algorithms )                                     | 285 |
| <a href="#">ClpTrustedData</a> (For a structure to be used by trusted code )                                    | 288 |
| <a href="#">ClpHashValue::CoinHashLink</a> (Data )  | 288 |
| <a href="#">Idiot</a> (This class implements a very silly algorithm )   | 288 |
| <a href="#">IdiotResult</a> (For use internally )   | 291 |
| <a href="#">Info</a> (***** DATA to be moved into protected section of <a href="#">ClpInterior</a> )            | 292 |
| <a href="#">MyEventHandler</a> (This is so user can trap events and do useful stuff )                           | 292 |
| <a href="#">MyMessageHandler</a>  | 294 |
| <a href="#">myPdco</a> (This implements a simple network matrix as derived from <a href="#">ClpMatrixBase</a> ) | 296 |
| <a href="#">Options</a> (***** DATA to be moved into protected section of <a href="#">ClpInterior</a> )         | 298 |
| <a href="#">OsiClpDisasterHandler</a>   | 299 |
| <a href="#">OsiClpSolverInterface</a> (Clp Solver Interface )   | 301 |
| <a href="#">Outfo</a> (***** DATA to be moved into protected section of <a href="#">ClpInterior</a> )           | 330 |

## 3 Class Documentation

### 3.1 blockStruct Struct Reference

#### 3.1.1 Detailed Description

Definition at line 565 of file ClpPackedMatrix.hpp.

The documentation for this struct was generated from the following file:

- ClpPackedMatrix.hpp

## **3.2 ClpNode::branchState Struct Reference**

### **3.2.1 Detailed Description**

Definition at line 121 of file ClpNode.hpp.

The documentation for this struct was generated from the following file:


- ClpNode.hpp

## **3.3 CbcOrClpParam Class Reference**

Very simple class for setting parameters.

```
#include <CbcOrClpParam.hpp>
```

Collaboration diagram for CbcOrClpParam:



## Public Member Functions

### Constructor and destructor

- [CbcOrClpParam](#) ()  
*Constructors.*
- **CbcOrClpParam** (std::string name, std::string help, double lower, double upper, CbcOrClpParameterType type, int display=2)
- **CbcOrClpParam** (std::string name, std::string help, int lower, int upper, CbcOrClpParameterType type, int display=2)
- **CbcOrClpParam** (std::string name, std::string help, std::string firstValue, CbcOrClpParameterType type, int whereUsed=7, int display=2)
- **CbcOrClpParam** (std::string name, std::string help, CbcOrClpParameterType type, int whereUsed=7, int display=2)
- [CbcOrClpParam](#) (const [CbcOrClpParam](#) &)  
*Copy constructor.*

- [CbcOrClpParam](#) & [operator=](#) (const [CbcOrClpParam](#) &rhs)  
*Assignment operator. This copies the data.*
- [~CbcOrClpParam](#) ()  
*Destructor.*

## stuff

- void [append](#) (std::string keyWord)  
*Insert string (only valid for keywords)*
- void [addHelp](#) (std::string keyWord)  
*Adds one help line.*
- std::string [name](#) () const  
*Returns name.*
- std::string [shortHelp](#) () const  
*Returns short help.*
- int [setDoubleParameter](#) (CbcModel &model, double value)  
*Sets a double parameter (nonzero code if error)*
- const char \* [setDoubleParameterWithMessage](#) (CbcModel &model, double value, int &returnCode)  
*Sets double parameter and returns printable string and error code.*
- double [doubleParameter](#) (CbcModel &model) const  
*Gets a double parameter.*
- int [setIntParameter](#) (CbcModel &model, int value)  
*Sets a int parameter (nonzero code if error)*
- const char \* [setIntParameterWithMessage](#) (CbcModel &model, int value, int &returnCode)  
*Sets int parameter and returns printable string and error code.*
- int [intParameter](#) (CbcModel &model) const  
*Gets a int parameter.*
- int [setDoubleParameter](#) (ClpSimplex \*model, double value)  
*Sets a double parameter (nonzero code if error)*
- double [doubleParameter](#) (ClpSimplex \*model) const  
*Gets a double parameter.*
- const char \* [setDoubleParameterWithMessage](#) (ClpSimplex \*model, double value, int &returnCode)  
*Sets double parameter and returns printable string and error code.*
- int [setIntParameter](#) (ClpSimplex \*model, int value)  
*Sets a int parameter (nonzero code if error)*
- const char \* [setIntParameterWithMessage](#) (ClpSimplex \*model, int value, int &returnCode)  
*Sets int parameter and returns printable string and error code.*
- int [intParameter](#) (ClpSimplex \*model) const  
*Gets a int parameter.*
- int [setDoubleParameter](#) (OsiSolverInterface \*model, double value)

- Sets a double parameter (nonzero code if error)*
- const char \* [setDoubleParameterWithMessage](#) (OsiSolverInterface \*model, double value, int &returnCode)
- Sets double parameter and returns printable string and error code.*
- double [doubleParameter](#) (OsiSolverInterface \*model) const
- Gets a double parameter.*
- int [setIntParameter](#) (OsiSolverInterface \*model, int value)
- Sets a int parameter (nonzero code if error)*
- const char \* [setIntParameterWithMessage](#) (OsiSolverInterface \*model, int value, int &returnCode)
- Sets int parameter and returns printable string and error code.*
- int [intParameter](#) (OsiSolverInterface \*model) const
- Gets a int parameter.*
- int [checkDoubleParameter](#) (double value) const
- Checks a double parameter (nonzero code if error)*
- std::string [matchName](#) () const
- Returns name which could match.*
- int [lengthMatchName](#) () const
- Returns length of name for printing.*
- int [parameterOption](#) (std::string check) const
- Returns parameter option which matches (-1 if none)*
- void [printOptions](#) () const
- Prints parameter options.*
- std::string [currentOption](#) () const
- Returns current parameter option.*
- void [setCurrentOption](#) (int value, bool printIt=false)
- Sets current parameter option.*
- const char \* [setCurrentOptionWithMessage](#) (int value)
- Sets current parameter option and returns printable string.*
- void [setCurrentOption](#) (const std::string value)
- Sets current parameter option using string.*
- int [currentOptionAsInteger](#) () const
- Returns current parameter option position.*
- void [setIntValue](#) (int value)
- Sets int value.*
- int [intValue](#) () const
- void [setDoubleValue](#) (double value)
- Sets double value.*
- double [doubleValue](#) () const
- void [setStringValue](#) (std::string value)
- Sets string value.*
- std::string [stringValue](#) () const
- int [matches](#) (std::string input) const
- Returns 1 if matches minimum, 2 if matches less, 0 if not matched.*

- CbcOrClpParameterType [type](#) () const  
*type*
- int [displayThis](#) () const  
*whether to display*
- void [setLonghelp](#) (const std::string help)  
*Set Long help.*
- void [printLongHelp](#) () const  
*Print Long help.*
- void [printString](#) () const  
*Print action and string.*
- int [whereUsed](#) () const  
*7 if used everywhere, 1 - used by clp 2 - used by cbc 4 - used by ampl*

### 3.3.1 Detailed Description

Very simple class for setting parameters.

Definition at line 272 of file CbcOrClpParam.hpp.

The documentation for this class was generated from the following file:


- CbcOrClpParam.hpp

## 3.4 ClpCholeskyBase Class Reference


Base class for Clp Cholesky factorization Will do better factorization.

```
#include <ClpCholeskyBase.hpp>
```

Inheritance diagram for ClpCholeskyBase:



Collaboration diagram for ClpCholeskyBase:



## Public Member Functions

## Gets

- int `status` () const  
*status. Returns status*
- int `numberOfRowsDropped` () const  
*numberOfRowsDropped. Number of rows gone*
- void `resetRowsDropped` ()  
*reset numberOfRowsDropped and rowsDropped.*
- char \* `rowsDropped` () const  
*rowsDropped - which rows are gone*
- double `choleskyCondition` () const  
*choleskyCondition.*
- double `goDense` () const  
*goDense i.e. use dense factoriaztion if > this (default 0.7).*
- void `setGoDense` (double value)  
*goDense i.e. use dense factoriaztion if > this (default 0.7).*
- int `rank` () const  
*rank. Returns rank*
- int `numberOfRows` () const  
*Return number of rows.*
- CoinBigIndex `size` () const  
*Return size.*
- longDouble \* `sparseFactor` () const  
*Return sparseFactor.*
- longDouble \* `diagonal` () const  
*Return diagonal.*
- longDouble \* `workDouble` () const  
*Return workDouble.*
- bool `kkt` () const  
*If KKT on.*
- void `setKKT` (bool yesNo)  
*Set KKT.*
- void `setIntegerParameter` (int i, int value)  
*Set integer parameter.*
- int `getIntegerParameter` (int i)  
*get integer parameter*
- void `setDoubleParameter` (int i, double value)  
*Set double parameter.*
- double `getDoubleParameter` (int i)  
*get double parameter*

## Constructors, destructor

- `ClpCholeskyBase` (int denseThreshold=-1)  
*Constructor which has dense columns activated.*
- virtual `~ClpCholeskyBase` ()  
*Destructor (has to be public)*
- `ClpCholeskyBase` (const `ClpCholeskyBase` &)  
*Copy.*
- `ClpCholeskyBase` & `operator=` (const `ClpCholeskyBase` &)  
*Assignment.*

## Protected Member Functions

## Symbolic, factor and solve

- int [symbolic1](#) (const CoinBigIndex \*Astart, const int \*Arow)  
*Symbolic1 - works out size without clever stuff.*
- void [symbolic2](#) (const CoinBigIndex \*Astart, const int \*Arow)  
*Symbolic2 - Fills in indices Uses lower triangular so can do cliques etc.*
- void [factorizePart2](#) (int \*rowsDropped)  
*Factorize - filling in rowsDropped and returning number dropped in integerParam.*
- void [solve](#) (CoinWorkDouble \*region, int type)  
*solve - 1 just first half, 2 just second half - 3 both.*
- int [preOrder](#) (bool lowerTriangular, bool includeDiagonal, bool doKKT)  
*Forms ADAT - returns nonzero if not enough memory.*
- void [updateDense](#) (longDouble \*d, int \*first)  
*Updates dense part (broken out for profiling)*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- int [type\\_](#)  
*type (may be useful) if > 20 do KKT*
- bool [doKKT\\_](#)  
*Doing full KKT (only used if default symbolic and factorization)*
- double [goDense\\_](#)  
*Go dense at this fraction.*
- double [choleskyCondition\\_](#)  
*choleskyCondition.*
- [ClpInterior](#) \* [model\\_](#)  
*model.*
- int [numberTrials\\_](#)  
*numberTrials. Number of trials before rejection*
- int [numberRows\\_](#)  
*numberRows. Number of Rows in factorization*
- int [status\\_](#)  
*status. Status of factorization*
- char \* [rowsDropped\\_](#)  
*rowsDropped*
- int \* [permuteInverse\\_](#)  
*permute inverse.*
- int \* [permute\\_](#)  
*main permute.*
- int [numberRowsDropped\\_](#)  
*numberRowsDropped. Number of rows gone*
- longDouble \* [sparseFactor\\_](#)

- sparseFactor.*
- CoinBigIndex \* [choleskyStart\\_](#)  
*choleskyStart - element starts*
- int \* [choleskyRow\\_](#)  
*choleskyRow (can be shorter than sparsefactor)*
- CoinBigIndex \* [indexStart\\_](#)  
*Index starts.*
- longDouble \* [diagonal\\_](#)  
*Diagonal.*
- longDouble \* [workDouble\\_](#)  
*double work array*
- int \* [link\\_](#)  
*link array*
- CoinBigIndex \* [workInteger\\_](#)
- int \* [clique\\_](#)
- CoinBigIndex [sizeFactor\\_](#)  
*sizeFactor.*
- CoinBigIndex [sizeIndex\\_](#)  
*Size of index array.*
- int [firstDense\\_](#)  
*First dense row.*
- int [integerParameters\\_](#) [64]  
*integerParameters*
- double [doubleParameters\\_](#) [64]  
*doubleParameters;*
- ClpMatrixBase \* [rowCopy\\_](#)  
*Row copy of matrix.*
- char \* [whichDense\\_](#)  
*Dense indicators.*
- longDouble \* [denseColumn\\_](#)  
*Dense columns (updated)*
- ClpCholeskyDense \* [dense\\_](#)  
*Dense cholesky.*
- int [denseThreshold\\_](#)  
*Dense threshold (for taking out of Cholesky)*

Virtual methods that the derived classes may provide

- virtual int [order](#) (ClpInterior \*model)  
*Orders rows and saves pointer to matrix.and model.*
- virtual int [symbolic](#) ()  
*Does Symbolic factorization given permutation.*
- virtual int [factorize](#) (const CoinWorkDouble \*diagonal, int \*rowsDropped)  
*Factorize - filling in rowsDropped and returning number dropped.*
- virtual void [solve](#) (CoinWorkDouble \*region)  
*Uses factorization to solve.*
- virtual void [solveKKT](#) (CoinWorkDouble \*region1, CoinWorkDouble \*region2, const CoinWorkDouble \*diagonal, CoinWorkDouble diagonalScaleFactor)  
*Uses factorization to solve.*

## Other

## Clone

- virtual [ClpCholeskyBase](#) \* **clone** () const
- int **type** () const  
*Returns type.*
- void **setType** (int type)  
*Sets type.*
- void **setModel** ([ClpInterior](#) \*model)  
*model.*

## 3.4.1 Detailed Description

Base class for Clp Cholesky factorization Will do better factorization.

very crude ordering

Derived classes may be using more sophisticated methods

Definition at line 53 of file ClpCholeskyBase.hpp.

## 3.4.2 Constructor &amp; Destructor Documentation

3.4.2.1 [ClpCholeskyBase::ClpCholeskyBase](#) ( int *denseThreshold* = -1 )

Constructor which has dense columns activated.

Default is off.

## 3.4.3 Member Function Documentation

3.4.3.1 virtual int [ClpCholeskyBase::order](#) ( [ClpInterior](#) \* *model* ) [virtual]

Orders rows and saves pointer to matrix.and model.

returns non-zero if not enough memory. You can use preOrder to set up ADAT If using default symbolic etc then must set sizeFactor\_ to size of input matrix to order (and to symbolic). Also just permute\_ and permuteInverse\_ should be created

Reimplemented in [ClpCholeskyDense](#), [ClpCholeskyMumps](#), [ClpCholeskyTaucs](#), [ClpCholeskyUfl](#), [ClpCholeskyWssmp](#), and [ClpCholeskyWssmpKKT](#).

3.4.3.2 virtual int [ClpCholeskyBase::symbolic](#) ( ) [virtual]

Does Symbolic factorization given permutation.

This is called immediately after order. If user provides this then user must provide factorize and solve. Otherwise the default factorization is used returns non-zero if not enough memory

Reimplemented in [ClpCholeskyDense](#), [ClpCholeskyMumps](#), [ClpCholeskyTaucs](#), [ClpCholeskyUfl](#), [ClpCholeskyWssmp](#), and [ClpCholeskyWssmpKKT](#).

**3.4.3.3** `virtual int ClpCholeskyBase::factorize ( const CoinWorkDouble * diagonal, int * rowsDropped ) [virtual]`

Factorize - filling in rowsDropped and returning number dropped.

If return code negative then out of memory

Reimplemented in [ClpCholeskyDense](#).

**3.4.3.4** `virtual void ClpCholeskyBase::solve ( CoinWorkDouble * region ) [virtual]`

Uses factorization to solve.

Reimplemented in [ClpCholeskyDense](#).

**3.4.3.5** `virtual void ClpCholeskyBase::solveKKT ( CoinWorkDouble * region1, CoinWorkDouble * region2, const CoinWorkDouble * diagonal, CoinWorkDouble diagonalScaleFactor ) [virtual]`

Uses factorization to solve.

- given as if KKT. region1 is rows+columns, region2 is rows

**3.4.3.6** `int ClpCholeskyBase::symbolic1 ( const CoinBigIndex * Astart, const int * Arow ) [protected]`

Symbolic1 - works out size without clever stuff.

Uses upper triangular as much easier. Returns size

**3.4.3.7** `void ClpCholeskyBase::solve ( CoinWorkDouble * region, int type ) [protected]`


solve - 1 just first half, 2 just second half - 3 both.

If 1 and 2 then diagonal has sqrt of inverse otherwise inverse

The documentation for this class was generated from the following file:

- [ClpCholeskyBase.hpp](#)

Inheritance diagram for ClpCholeskyDense:



### Virtual methods that the derived classes provides

- virtual int **order** (CplInterior \*model)  
*Orders rows and saves pointer to matrix.and model.*
- virtual int **symbolic** ()

*Does Symbolic factorization given permutation.*

- virtual int [factorize](#) (const CoinWorkDouble \*diagonal, int \*rowsDropped)

*Factorize - filling in rowsDropped and returning number dropped.*

- virtual void [solve](#) (CoinWorkDouble \*region)

*Uses factorization to solve.*

#### Non virtual methods for ClpCholeskyDense

- int [reserveSpace](#) (const [ClpCholeskyBase](#) \*factor, int numberOfRows)

*Reserves space.*

- CoinBigIndex [space](#) (int numberOfRows) const

*Returns space needed.*

- void [factorizePart2](#) (int \*rowsDropped)

*part 2 of Factorize - filling in rowsDropped*

- void [factorizePart3](#) (int \*rowsDropped)

*part 2 of Factorize - filling in rowsDropped - blocked*

- void [solveF1](#) (longDouble \*a, int n, CoinWorkDouble \*region)

*Forward part of solve.*

- void [solveF2](#) (longDouble \*a, int n, CoinWorkDouble \*region, CoinWorkDouble \*region2)

- void [solveB1](#) (longDouble \*a, int n, CoinWorkDouble \*region)

*Backward part of solve.*

- void [solveB2](#) (longDouble \*a, int n, CoinWorkDouble \*region, CoinWorkDouble \*region2)

- int [bNumber](#) (const longDouble \*array, int &, int &)

- longDouble \* [aMatrix](#) () const

*A.*

- longDouble \* [diagonal](#) () const

*Diagonal.*

#### Constructors, destructor

- [ClpCholeskyDense](#) ()

*Default constructor.*

- virtual [~ClpCholeskyDense](#) ()

*Destructor.*

- [ClpCholeskyDense](#) (const [ClpCholeskyDense](#) &)

*Copy.*

- [ClpCholeskyDense](#) & [operator=](#) (const [ClpCholeskyDense](#) &)

*Assignment.*

- virtual [ClpCholeskyBase](#) \* [clone](#) () const

*Clone.*

#### 3.5.1 Detailed Description

Definition at line 14 of file ClpCholeskyDense.hpp.

## 3.5.2 Constructor &amp; Destructor Documentation

## 3.5.2.1 ClpCholeskyDense::ClpCholeskyDense ( )

Default constructor.

## 3.5.3 Member Function Documentation

3.5.3.1 virtual int ClpCholeskyDense::order ( ClpInterior \* *model* ) [virtual]

Orders rows and saves pointer to matrix.and model.

Returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

## 3.5.3.2 virtual int ClpCholeskyDense::symbolic ( ) [virtual]

Does Symbolic factorization given permutation.

This is called immediately after order. If user provides this then user must provide factorize and solve. Otherwise the default factorization is used returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

3.5.3.3 virtual int ClpCholeskyDense::factorize ( const CoinWorkDouble \* *diagonal*, int \* *rowsDropped* ) [virtual]

Factorize - filling in rowsDropped and returning number dropped.

If return code negative then out of memory

Reimplemented from [ClpCholeskyBase](#).

3.5.3.4 virtual void ClpCholeskyDense::solve ( CoinWorkDouble \* *region* ) [virtual]

Uses factorization to solve.

Reimplemented from [ClpCholeskyBase](#).

3.5.3.5 int ClpCholeskyDense::reserveSpace ( const ClpCholeskyBase \* *factor*, int *numberRows* )

Reserves space.

If factor not NULL then just uses passed space Returns non-zero if not enough memory

The documentation for this class was generated from the following file:

- ClpCholeskyDense.hpp

## 3.6 ClpCholeskyDenseC Struct Reference

### 3.6.1 Detailed Description

Definition at line 88 of file ClpCholeskyDense.hpp.

The documentation for this struct was generated from the following file:


- ClpCholeskyDense.hpp

## 3.7 ClpCholeskyMumps Class Reference


Mumps class for Clp Cholesky factorization.

```
#include <ClpCholeskyMumps.hpp>
```

Inheritance diagram for ClpCholeskyMumps:



Collaboration diagram for ClpCholeskyMumps:



## Public Member Functions

### Virtual methods that the derived classes provides

- virtual int **order** (CIPInterior \*model)  
*Orders rows and saves pointer to matrix and model.*
- virtual int **symbolic** ()  
*Does Symbolic factorization given permutation.*
- virtual int **factorize** (const double \*diagonal, int \*rowsDropped)  
*Factorize - filling in rowsDropped and returning number dropped.*
- virtual void **solve** (double \*region)  
*Uses factorization to solve.*

## Constructors, destructor

- `ClpCholeskyMumps` (int denseThreshold=-1)  
*Constructor which has dense columns activated.*
- `virtual ~ClpCholeskyMumps ()`  
*Destructor.*
- `virtual ClpCholeskyBase * clone () const`  
*Clone.*

### 3.7.1 Detailed Description

Mumps class for Clp Cholesky factorization.

Definition at line 21 of file ClpCholeskyMumps.hpp.

### 3.7.2 Constructor & Destructor Documentation

#### 3.7.2.1 ClpCholeskyMumps::ClpCholeskyMumps ( int *denseThreshold* = -1 )

Constructor which has dense columns activated.

Default is off.

### 3.7.3 Member Function Documentation

#### 3.7.3.1 virtual int ClpCholeskyMumps::order ( ClpInterior \* *model* ) [virtual]

Orders rows and saves pointer to matrix and model.

Returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

#### 3.7.3.2 virtual int ClpCholeskyMumps::symbolic ( ) [virtual]

Does Symbolic factorization given permutation.

This is called immediately after order. If user provides this then user must provide factorize and solve. Otherwise the default factorization is used returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

#### 3.7.3.3 virtual int ClpCholeskyMumps::factorize ( const double \* *diagonal*, int \* *rowsDropped* ) [virtual]

Factorize - filling in rowsDropped and returning number dropped.

If return code negative then out of memory

#### 3.7.3.4 virtual void ClpCholeskyMumps::solve ( double \* *region* ) [virtual]

Uses factorization to solve.

The documentation for this class was generated from the following file:


- ClpCholeskyMumps.hpp

## 3.8 ClpCholeskyTaucs Class Reference


Taucs class for Clp Cholesky factorization.

```
#include <ClpCholeskyTaucs.hpp>
```

Inheritance diagram for ClpCholeskyTaucs:



Collaboration diagram for ClpCholeskyTaucs:



## Public Member Functions

Virtual methods that the derived classes provides

- virtual int `order` (`ClpInterior *model`)  
Orders rows and saves pointer to matrix.and model.
- virtual int `symbolic` ()  
Dummy.
- virtual int `factorize` (const double \*diagonal, int \*rowsDropped)

*Factorize - filling in rowsDropped and returning number dropped.*

- virtual void [solve](#) (double \*region)

*Uses factorization to solve.*

#### Constructors, destructor

- [ClpCholeskyTaucs](#) ()

*Default constructor.*

- virtual [~ClpCholeskyTaucs](#) ()

*Destructor.*

- **ClpCholeskyTaucs** (const [ClpCholeskyTaucs](#) &)
- [ClpCholeskyTaucs](#) & **operator=** (const [ClpCholeskyTaucs](#) &)
- virtual [ClpCholeskyBase](#) \* **clone** () const

*Clone.*

### 3.8.1 Detailed Description

Taucs class for Clp Cholesky factorization.

If you wish to use Sivan Toledo's TAUCS code see

<http://www.tau.ac.il/~stoledo/taucs/>

for terms of use

The taucs.h file was modified to put

```
#ifndef __cplusplus extern "C"{ #endif after line 440 (#endif) and #ifdef __cplusplus }
#endif at end
```

I also modified LAPACK dpotf2.f (two places) to change the GO TO 30 on AJJ.Lt.0.0

to

```
IF( AJJ.LE.1.0e-20 ) THEN AJJ = 1.0e100; ELSE AJJ = SQRT( AJJ ) END IF
```

Definition at line 43 of file ClpCholeskyTaucs.hpp.

### 3.8.2 Constructor & Destructor Documentation

#### 3.8.2.1 ClpCholeskyTaucs::ClpCholeskyTaucs ( )

Default constructor.

### 3.8.3 Member Function Documentation

#### 3.8.3.1 virtual int ClpCholeskyTaucs::order ( ClpInterior \* model ) [virtual]

Orders rows and saves pointer to matrix.and model.

Returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

3.8.3.2 `virtual int ClpCholeskyTaucs::factorize ( const double * diagonal, int * rowsDropped )`  
[virtual]

Factorize - filling in rowsDropped and returning number dropped.

If return code negative then out of memory

3.8.3.3 `virtual void ClpCholeskyTaucs::solve ( double * region )` [virtual]

Uses factorization to solve.

The documentation for this class was generated from the following file:


- ClpCholeskyTaucs.hpp

### 3.9 ClpCholeskyUfl Class Reference


Ufl class for Clp Cholesky factorization.

```
#include <ClpCholeskyUfl.hpp>
```

Inheritance diagram for ClpCholeskyUfl:



Collaboration diagram for ClpCholeskyUfl:



## Public Member Functions

### Virtual methods that the derived classes provides

- virtual int **order** (CplInterior \*model)  
*Orders rows and saves pointer to matrix and model.*
- virtual int **symbolic** ()  
*Does Symbolic factorization given permutation using CHOLMOD (if available).*
- virtual int **factorize** (const double \*diagonal, int \*rowsDropped)  
*Factorize - filling in rowsDropped and returning number dropped using CHOLMOD (if available).*
- virtual void **solve** (double \*region)  
*Uses factorization to solve.*

## Constructors, destructor

- `ClpCholeskyUfl` (int denseThreshold=-1)  
*Constructor which has dense columns activated.*
- `virtual ~ClpCholeskyUfl ()`  
*Destructor.*
- `virtual ClpCholeskyBase * clone () const`  
*Clone.*

### 3.9.1 Detailed Description

Ufl class for Clp Cholesky factorization.

If you wish to use AMD code from University of Florida see

<http://www.cise.ufl.edu/research/sparse/amd>

for terms of use

If you wish to use CHOLMOD code from University of Florida see

<http://www.cise.ufl.edu/research/sparse/cholmod>

for terms of use

Definition at line 32 of file ClpCholeskyUfl.hpp.

### 3.9.2 Constructor & Destructor Documentation

#### 3.9.2.1 ClpCholeskyUfl::ClpCholeskyUfl ( int *denseThreshold* = -1 )

Constructor which has dense columns activated.

Default is off.

### 3.9.3 Member Function Documentation

#### 3.9.3.1 virtual int ClpCholeskyUfl::order ( ClpInterior \* *model* ) [virtual]

Orders rows and saves pointer to matrix.and model.

Returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

#### 3.9.3.2 virtual int ClpCholeskyUfl::symbolic ( ) [virtual]

Does Symbolic factorization given permutation using CHOLMOD (if available).

This is called immediately after order. If user provides this then user must provide factorize and solve. Otherwise the default factorization is used returns non-zero if not enough memory.

Reimplemented from [ClpCholeskyBase](#).

#### 3.9.3.3 virtual int ClpCholeskyUfl::factorize ( const double \* *diagonal*, int \* *rowsDropped* ) [virtual]

Factorize - filling in rowsDropped and returning number dropped using CHOLMOD (if available).

If return code negative then out of memory

#### 3.9.3.4 virtual void ClpCholeskyUfl::solve ( double \* *region* ) [virtual]



Uses factorization to solve.

Uses CHOLMOD (if available).

- ClpCholeskyUfl.hpp

Wssmp class for Clp Cholesky factorization.

Inheritance diagram for ClpCholeskyWssmp:



## Public Member Functions

Virtual methods that the derived classes provides

- virtual int [order](#) ([ClpInterior](#) \*model)  
*Orders rows and saves pointer to matrix.and model.*
- virtual int [symbolic](#) ()  
*Does Symbolic factorization given permutation.*
- virtual int [factorize](#) (const double \*diagonal, int \*rowsDropped)  
*Factorize - filling in rowsDropped and returning number dropped.*
- virtual void [solve](#) (double \*region)  
*Uses factorization to solve.*

## Constructors, destructor

- [ClpCholeskyWssmp](#) (int denseThreshold=-1)  
*Constructor which has dense columns activated.*
- virtual [~ClpCholeskyWssmp](#) ()  
*Destructor.*
- **ClpCholeskyWssmp** (const [ClpCholeskyWssmp](#) &)
- [ClpCholeskyWssmp](#) & **operator=** (const [ClpCholeskyWssmp](#) &)
- virtual [ClpCholeskyBase](#) \* [clone](#) () const  
*Clone.*

## 3.10.1 Detailed Description

Wssmp class for Clp Cholesky factorization.

Definition at line 17 of file ClpCholeskyWssmp.hpp.

## 3.10.2 Constructor &amp; Destructor Documentation

3.10.2.1 [ClpCholeskyWssmp::ClpCholeskyWssmp](#) ( int *denseThreshold* = -1 )

Constructor which has dense columns activated.

Default is off.

## 3.10.3 Member Function Documentation

3.10.3.1 virtual int [ClpCholeskyWssmp::order](#) ( [ClpInterior](#) \* *model* ) [virtual]

Orders rows and saves pointer to matrix.and model.

Returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

3.10.3.2 `virtual int ClpCholeskyWssmp::symbolic ( ) [virtual]`

Does Symbolic factorization given permutation.

This is called immediately after order. If user provides this then user must provide factorize and solve. Otherwise the default factorization is used returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

3.10.3.3 `virtual int ClpCholeskyWssmp::factorize ( const double * diagonal, int * rowsDropped ) [virtual]`

Factorize - filling in rowsDropped and returning number dropped.

If return code negative then out of memory

3.10.3.4 `virtual void ClpCholeskyWssmp::solve ( double * region ) [virtual]`

Uses factorization to solve.

The documentation for this class was generated from the following file:


- `ClpCholeskyWssmp.hpp`

## 3.11 ClpCholeskyWssmpKKT Class Reference


WssmpKKT class for Clp Cholesky factorization.

```
#include <ClpCholeskyWssmpKKT.hpp>
```

Inheritance diagram for ClpCholeskyWssmpKKT:



Collaboration diagram for ClpCholeskyWssmpKKT:



## Public Member Functions

### Virtual methods that the derived classes provides

- virtual int **order** (ClpInterior \*model)  
*Orders rows and saves pointer to matrix and model.*
- virtual int **symbolic** ()  
*Does Symbolic factorization given permutation.*
- virtual int **factorize** (const double \*diagonal, int \*rowsDropped)  
*Factorize - filling in rowsDropped and returning number dropped.*
- virtual void **solve** (double \*region)  
*Uses factorization to solve.*
- virtual void **solveKKT** (double \*region1, double \*region2, const double \*diagonal, double diagonalScaleFactor)  
*Uses factorization to solve.*

## Constructors, destructor

- **ClpCholeskyWssmpKKT** (int denseThreshold=-1)  
*Constructor which has dense columns activated.*
- virtual ~**ClpCholeskyWssmpKKT** ()  
*Destructor.*
- **ClpCholeskyWssmpKKT** (const **ClpCholeskyWssmpKKT** &)
- **ClpCholeskyWssmpKKT** & **operator=** (const **ClpCholeskyWssmpKKT** &)
- virtual **ClpCholeskyBase** \* **clone** () const  
*Clone.*

## 3.11.1 Detailed Description

WssmpKKT class for Clp Cholesky factorization.

Definition at line 17 of file ClpCholeskyWssmpKKT.hpp.

## 3.11.2 Constructor &amp; Destructor Documentation

3.11.2.1 ClpCholeskyWssmpKKT::ClpCholeskyWssmpKKT ( int *denseThreshold* = -1 )

Constructor which has dense columns activated.

Default is off.

## 3.11.3 Member Function Documentation

3.11.3.1 virtual int ClpCholeskyWssmpKKT::order ( ClpInterior \* *model* ) [virtual]

Orders rows and saves pointer to matrix.and model.

Returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

## 3.11.3.2 virtual int ClpCholeskyWssmpKKT::symbolic ( ) [virtual]

Does Symbolic factorization given permutation.

This is called immediately after order. If user provides this then user must provide factorize and solve. Otherwise the default factorization is used returns non-zero if not enough memory

Reimplemented from [ClpCholeskyBase](#).

3.11.3.3 virtual int ClpCholeskyWssmpKKT::factorize ( const double \* *diagonal*, int \* *rowsDropped* ) [virtual]

Factorize - filling in rowsDropped and returning number dropped.

If return code negative then out of memory

3.11.3.4 virtual void ClpCholeskyWssmpKKT::solve ( double \* *region* ) [virtual]

Uses factorization to solve.

3.11.3.5 virtual void ClpCholeskyWssmpKKT::solveKKT ( double \* *region1*, double \* *region2*, const double \* *diagonal*, double *diagonalScaleFactor* ) [virtual]

Uses factorization to solve.

- given as if KKT. region1 is rows+columns, region2 is rows

The documentation for this class was generated from the following file:


- ClpCholeskyWssmpKKT.hpp

### 3.12 ClpConstraint Class Reference

Constraint Abstract Base Class.

```
#include <ClpConstraint.hpp>
```

Inheritance diagram for ClpConstraint:



#### Public Member Functions

##### Stuff

- virtual int [gradient](#) (const [ClpSimplex](#) \*model, const double \*solution, double \*gradient, double &functionValue, double &offset, bool useScaling=false, bool refresh=true) const =0  
*Fills gradient.*
- virtual double [functionValue](#) (const [ClpSimplex](#) \*model, const double \*solution, bool useScaling=false, bool refresh=true) const  
*Constraint function value.*
- virtual void [resize](#) (int newNumberColumns)=0  
*Resize constraint.*
- virtual void [deleteSome](#) (int numberToDelete, const int \*which)=0  
*Delete columns in constraint.*
- virtual void [reallyScale](#) (const double \*columnScale)=0  
*Scale constraint.*
- virtual int [markNonlinear](#) (char \*which) const =0  
*Given a zeroed array sets nonlinear columns to 1.*
- virtual int [markNonzero](#) (char \*which) const =0  
*Given a zeroed array sets possible nonzero coefficients to 1.*

## Constructors and destructors

- [ClpConstraint](#) ()  
*Default Constructor.*
- [ClpConstraint](#) (const [ClpConstraint](#) &)  
*Copy constructor.*
- [ClpConstraint](#) & [operator=](#) (const [ClpConstraint](#) &rhs)  
*Assignment operator.*
- virtual [~ClpConstraint](#) ()  
*Destructor.*
- virtual [ClpConstraint](#) \* [clone](#) () const =0  
*Clone.*

## Other

- int [type](#) ()  
*Returns type, 0 linear, 1 nonlinear.*
- int [rowNumber](#) () const  
*Row number (-1 is objective)*
- virtual int [numberCoefficients](#) () const =0  
*Number of possible coefficients in gradient.*
- double [functionValue](#) () const  
*Stored constraint function value.*
- double [offset](#) () const  
*Constraint offset.*
- virtual void [newXValues](#) ()  
*Say we have new primal solution - so may need to recompute.*

## Protected Attributes

## Protected member data

- double \* [lastGradient\\_](#)  
*Gradient at last evaluation.*
- double [functionValue\\_](#)  
*Value of non-linear part of constraint.*
- double [offset\\_](#)  
*Value of offset for constraint.*
- int [type\\_](#)  
*Type of constraint - linear is 1.*
- int [rowNumber\\_](#)  
*Row number (-1 is objective)*

## 3.12.1 Detailed Description

Constraint Abstract Base Class.

Abstract Base Class for describing a constraint or objective function

Definition at line 19 of file [ClpConstraint.hpp](#).

## 3.12.2 Member Function Documentation

3.12.2.1 `virtual int ClpConstraint::gradient ( const ClpSimplex * model, const double * solution, double * gradient, double & functionValue, double & offset, bool useScaling = false, bool refresh = true ) const` [pure virtual]

Fills gradient.

If Linear then solution may be NULL, also returns true value of function and offset so we can use x not deltaX in constraint If refresh is false then uses last solution Uses model for scaling Returns non-zero if gradient undefined at current solution

Implemented in [ClpConstraintLinear](#), and [ClpConstraintQuadratic](#).

3.12.2.2 `virtual int ClpConstraint::markNonlinear ( char * which ) const` [pure virtual]

Given a zeroed array sets nonlinear columns to 1.

Returns number of nonlinear columns

Implemented in [ClpConstraintLinear](#), and [ClpConstraintQuadratic](#).

3.12.2.3 `virtual int ClpConstraint::markNonzero ( char * which ) const` [pure virtual]

Given a zeroed array sets possible nonzero coefficients to 1.

Returns number of nonzeros

Implemented in [ClpConstraintLinear](#), and [ClpConstraintQuadratic](#).

The documentation for this class was generated from the following file:


- [ClpConstraint.hpp](#)

## 3.13 ClpConstraintLinear Class Reference


Linear Constraint Class.

```
#include <ClpConstraintLinear.hpp>
```

Inheritance diagram for ClpConstraintLinear:



Collaboration diagram for ClpConstraintLinear:



#### Public Member Functions

##### Stuff

- virtual int [gradient](#) (const [ClpSimplex](#) \*model, const double \*solution, double \*gradient, double &functionValue, double &offset, bool useScaling=false, bool refresh=true) const  
*Fills gradient.*
- virtual void [resize](#) (int newNumberColumns)  
*Resize constraint.*
- virtual void [deleteSome](#) (int numberToDelete, const int \*which)  
*Delete columns in constraint.*
- virtual void [reallyScale](#) (const double \*columnScale)

*Scale constraint.*

- virtual int [markNonlinear](#) (char \*which) const  
*Given a zeroed array sets nonlinear columns to 1.*
- virtual int [markNonzero](#) (char \*which) const  
*Given a zeroed array sets possible nonzero coefficients to 1.*

#### Constructors and destructors

- [ClpConstraintLinear](#) ()  
*Default Constructor.*
- [ClpConstraintLinear](#) (int row, int numberCoefficients, int numberColumns, const int \*column, const double \*element)  
*Constructor from constraint.*
- [ClpConstraintLinear](#) (const [ClpConstraintLinear](#) &rhs)  
*Copy constructor .*
- [ClpConstraintLinear](#) & operator= (const [ClpConstraintLinear](#) &rhs)  
*Assignment operator.*
- virtual [~ClpConstraintLinear](#) ()  
*Destructor.*
- virtual [ClpConstraint](#) \* [clone](#) () const  
*Clone.*

#### Gets and sets

- virtual int [numberCoefficients](#) () const  
*Number of coefficients.*
- int [numberColumns](#) () const  
*Number of columns in linear constraint.*
- const int \* [column](#) () const  
*Columns.*
- const double \* [coefficient](#) () const  
*Coefficients.*

#### 3.13.1 Detailed Description

Linear Constraint Class.

Definition at line 17 of file ClpConstraintLinear.hpp.

#### 3.13.2 Member Function Documentation

- 3.13.2.1 virtual int [ClpConstraintLinear::gradient](#) ( const [ClpSimplex](#) \* *model*, const double \* *solution*, double \* *gradient*, double & *functionValue*, double & *offset*, bool *useScaling* = false, bool *refresh* = true ) const [virtual]

Fills gradient.

If Linear then solution may be NULL, also returns true value of function and offset so we can use x not deltaX in constraint If refresh is false then uses last solution Uses model for scaling Returns non-zero if gradient undefined at current solution

Implements [ClpConstraint](#).

3.13.2.2 `virtual int ClpConstraintLinear::markNonlinear ( char * which ) const` [virtual]

Given a zeroed array sets nonlinear columns to 1.

Returns number of nonlinear columns

Implements [ClpConstraint](#).

3.13.2.3 `virtual int ClpConstraintLinear::markNonzero ( char * which ) const` [virtual]

Given a zeroed array sets possible nonzero coefficients to 1.

Returns number of nonzeros

Implements [ClpConstraint](#).

The documentation for this class was generated from the following file:


- ClpConstraintLinear.hpp

## 3.14 ClpConstraintQuadratic Class Reference


Quadratic Constraint Class.

```
#include <ClpConstraintQuadratic.hpp>
```

Inheritance diagram for ClpConstraintQuadratic:



Collaboration diagram for ClpConstraintQuadratic:



#### Public Member Functions

##### Stuff

- virtual int [gradient](#) (const [ClpSimplex](#) \*model, const double \*solution, double \*gradient, double &functionValue, double &offset, bool useScaling=false, bool refresh=true) const  
*Fills gradient.*
- virtual void [resize](#) (int newNumberColumns)  
*Resize constraint.*
- virtual void [deleteSome](#) (int numberToDelete, const int \*which)  
*Delete columns in constraint.*
- virtual void [reallyScale](#) (const double \*columnScale)  
*Scale constraint.*
- virtual int [markNonlinear](#) (char \*which) const  
*Given a zeroed array sets nonquadratic columns to 1.*
- virtual int [markNonzero](#) (char \*which) const  
*Given a zeroed array sets possible nonzero coefficients to 1.*

##### Constructors and destructors

- [ClpConstraintQuadratic](#) ()  
*Default Constructor.*
- [ClpConstraintQuadratic](#) (int row, int numberQuadraticColumns, int numberColumns, const CoinBigIndex \*start, const int \*column, const double \*element)  
*Constructor from quadratic.*
- [ClpConstraintQuadratic](#) (const [ClpConstraintQuadratic](#) &rhs)  
*Copy constructor .*
- [ClpConstraintQuadratic](#) & [operator=](#) (const [ClpConstraintQuadratic](#) &rhs)  
*Assignment operator.*

- virtual [~ClpConstraintQuadratic](#) ()  
*Destructor.*
- virtual [ClpConstraint](#) \* [clone](#) () const  
*Clone.*

#### Gets and sets

- virtual int [numberCoefficients](#) () const  
*Number of coefficients.*
- int [numberColumns](#) () const  
*Number of columns in constraint.*
- CoinBigIndex \* [start](#) () const  
*Column starts.*
- const int \* [column](#) () const  
*Columns.*
- const double \* [coefficient](#) () const  
*Coefficients.*

#### 3.14.1 Detailed Description

Quadratic Constraint Class.

Definition at line 17 of file ClpConstraintQuadratic.hpp.

#### 3.14.2 Member Function Documentation

**3.14.2.1** virtual int ClpConstraintQuadratic::gradient ( const ClpSimplex \* *model*, const double \* *solution*, double \* *gradient*, double & *functionValue*, double & *offset*, bool *useScaling* = false, bool *refresh* = true ) const [virtual]

Fills gradient.

If Quadratic then solution may be NULL, also returns true value of function and offset so we can use x not deltaX in constraint If refresh is false then uses last solution Uses model for scaling Returns non-zero if gradient undefined at current solution

Implements [ClpConstraint](#).

**3.14.2.2** virtual int ClpConstraintQuadratic::markNonlinear ( char \* *which* ) const [virtual]

Given a zeroed array sets nonquadratic columns to 1.

Returns number of nonquadratic columns

Implements [ClpConstraint](#).

**3.14.2.3** virtual int ClpConstraintQuadratic::markNonzero ( char \* *which* ) const [virtual]

Given a zeroed array sets possible nonzero coefficients to 1.

Returns number of nonzeros

Implements [ClpConstraint](#).

The documentation for this class was generated from the following file:

- ClpConstraintQuadratic.hpp

### 3.15 ClpDataSave Class Reference

This is a tiny class where data can be saved round calls.

```
#include <ClpModel.hpp>
```

#### Public Member Functions

##### Constructors and destructor

- [ClpDataSave](#) ()  
*Default constructor.*
- [ClpDataSave](#) (const [ClpDataSave](#) &)  
*Copy constructor.*
- [ClpDataSave](#) & [operator=](#) (const [ClpDataSave](#) &rhs)  
*Assignment operator. This copies the data.*
- [~ClpDataSave](#) ()  
*Destructor.*

#### Public Attributes

data - with same names as in other classes

- double **dualBound\_**
- double **infeasibilityCost\_**
- double **pivotTolerance\_**
- double **zeroFactorizationTolerance\_**
- double **zeroSimplexTolerance\_**
- double **acceptablePivot\_**
- double **objectiveScale\_**
- int **sparseThreshold\_**
- int **perturbation\_**
- int **forceFactorization\_**
- int **scalingFlag\_**
- unsigned int **specialOptions\_**

#### 3.15.1 Detailed Description

This is a tiny class where data can be saved round calls.

Definition at line 1229 of file ClpModel.hpp.

The documentation for this class was generated from the following file:


- ClpModel.hpp

### 3.16 ClpDisasterHandler Class Reference


Base class for Clp disaster handling.

```
#include <ClpEventHandler.hpp>
```

Inheritance diagram for ClpDisasterHandler:



Collaboration diagram for ClpDisasterHandler:



## Public Member Functions

**Virtual methods that the derived classe should provide.**

- virtual void **intoSimplex** ()=0  
*Into simplex.*
- virtual bool **check** () const =0  
*Checks if disaster.*
- virtual void **saveInfo** ()=0  
*saves information for next attempt*
- virtual int **typeOfDisaster** ()  
*Type of disaster 0 can fix, 1 abort.*

**Constructors, destructor**

- [ClpDisasterHandler](#) ([ClpSimplex](#) \*model=NULL)  
*Default constructor.*
- virtual [~ClpDisasterHandler](#) ()  
*Destructor.*
- **ClpDisasterHandler** (const [ClpDisasterHandler](#) &)
- [ClpDisasterHandler](#) & **operator=** (const [ClpDisasterHandler](#) &)
- virtual [ClpDisasterHandler](#) \* [clone](#) () const =0  
*Clone.*

**Sets/gets**

- void [setSimplex](#) ([ClpSimplex](#) \*model)  
*set model.*
- [ClpSimplex](#) \* [simplex](#) () const  
*Get model.*

**Protected Attributes****Data members**

*The data members are protected to allow access for derived classes.*

- [ClpSimplex](#) \* [model\\_](#)  
*Pointer to simplex.*

**3.16.1 Detailed Description**

Base class for Clp disaster handling.

This is here to allow for disaster handling. By disaster I mean that Clp would otherwise give up

Definition at line 108 of file ClpEventHandler.hpp.

**3.16.2 Constructor & Destructor Documentation****3.16.2.1 ClpDisasterHandler::ClpDisasterHandler ( [ClpSimplex](#) \* *model* = NULL )**

Default constructor.

**3.16.3 Member Function Documentation****3.16.3.1 void ClpDisasterHandler::setSimplex ( [ClpSimplex](#) \* *model* )**

set model.

The documentation for this class was generated from the following file:


- ClpEventHandler.hpp

### 3.17 ClpDualRowDantzig Class Reference


Dual Row Pivot Dantzig Algorithm Class.

```
#include <ClpDualRowDantzig.hpp>
```

Inheritance diagram for ClpDualRowDantzig:



Collaboration diagram for ClpDualRowDantzig:



## Public Member Functions

## Algorithmic methods

- virtual int **pivotRow** ()  
*Returns pivot row, -1 if none.*
- virtual double **updateWeights** (CoinIndexedVector \*input, CoinIndexedVector \*spare, CoinIndexedVector \*spare2, CoinIndexedVector \*updatedColumn)  
*Updates weights and returns pivot alpha.*
- virtual void **updatePrimalSolution** (CoinIndexedVector \*input, double theta, double &changeInObjective)  
*Updates primal solution (and maybe list of candidates) Uses input vector which it deletes Computes change in objective function.*

## Constructors and destructors

- [ClpDualRowDantzig](#) ()  
*Default Constructor.*
- [ClpDualRowDantzig](#) (const [ClpDualRowDantzig](#) &)  
*Copy constructor.*
- [ClpDualRowDantzig](#) & [operator=](#) (const [ClpDualRowDantzig](#) &rhs)  
*Assignment operator.*
- virtual [~ClpDualRowDantzig](#) ()  
*Destructor.*
- virtual [ClpDualRowPivot](#) \* [clone](#) (bool copyData=true) const  
*Clone.*

## 3.17.1 Detailed Description

Dual Row Pivot Dantzig Algorithm Class.

This is simplest choice - choose largest infeasibility

Definition at line 19 of file [ClpDualRowDantzig.hpp](#).

## 3.17.2 Member Function Documentation

- 3.17.2.1 virtual double [ClpDualRowDantzig::updateWeights](#) ( [CoinIndexedVector](#) \* *input*, [CoinIndexedVector](#) \* *spare*, [CoinIndexedVector](#) \* *spare2*, [CoinIndexedVector](#) \* *updatedColumn* ) [virtual]

Updates weights and returns pivot alpha.

Also does FT update

Implements [ClpDualRowPivot](#).

The documentation for this class was generated from the following file:


- [ClpDualRowDantzig.hpp](#)

## 3.18 ClpDualRowPivot Class Reference


Dual Row Pivot Abstract Base Class.

```
#include <ClpDualRowPivot.hpp>
```

Inheritance diagram for ClpDualRowPivot:



Collaboration diagram for ClpDualRowPivot:



## Public Member Functions

## Algorithmic methods

- virtual int **pivotRow** ()=0  
*Returns pivot row, -1 if none.*
- virtual double **updateWeights** (CoinIndexedVector \*input, CoinIndexedVector \*spare, CoinIndexedVector \*spare2, CoinIndexedVector \*updatedColumn)=0  
*Updates weights and returns pivot alpha.*
- virtual void **updatePrimalSolution** (CoinIndexedVector \*input, double theta, double &changeInObjective)=0

*Updates primal solution (and maybe list of candidates) Uses input vector which it deletes Computes change in objective function Would be faster if we kept basic regions, but on other hand it means everything is always in sync.*

- virtual void [saveWeights](#) ([ClpSimplex](#) \*model, int mode)  
*Saves any weights round factorization as pivot rows may change Will be empty unless steepest edge (will save model) May also recompute infeasibility stuff 1) before factorization 2) after good factorization (if weights empty may initialize) 3) after something happened but no factorization (e.g.*
- virtual void [checkAccuracy](#) ()  
*checks accuracy and may re-initialize (may be empty)*
- virtual void [unrollWeights](#) ()  
*Gets rid of last update (may be empty)*
- virtual void [clearArrays](#) ()  
*Gets rid of all arrays (may be empty)*
- virtual bool [looksOptimal](#) () const  
*Returns true if would not find any row.*
- virtual void [maximumPivotsChanged](#) ()  
*Called when maximum pivots changes.*

#### Constructors and destructors

- [ClpDualRowPivot](#) ()  
*Default Constructor.*
- [ClpDualRowPivot](#) (const [ClpDualRowPivot](#) &)  
*Copy constructor.*
- [ClpDualRowPivot](#) & [operator=](#) (const [ClpDualRowPivot](#) &rhs)  
*Assignment operator.*
- virtual [~ClpDualRowPivot](#) ()  
*Destructor.*
- virtual [ClpDualRowPivot](#) \* [clone](#) (bool copyData=true) const =0  
*Clone.*

#### Other

- [ClpSimplex](#) \* [model](#) ()  
*Returns model.*
- void [setModel](#) ([ClpSimplex](#) \*newmodel)  
*Sets model (normally to NULL)*
- int [type](#) ()  
*Returns type (above 63 is extra information)*

#### Protected Attributes

##### Protected member data

- [ClpSimplex](#) \* [model\\_](#)  
*Pointer to model.*
- int [type\\_](#)  
*Type of row pivot algorithm.*

## 3.18.1 Detailed Description

Dual Row Pivot Abstract Base Class.

Abstract Base Class for describing an interface to an algorithm to choose row pivot in dual simplex algorithm. For some algorithms e.g. Dantzig choice then some functions may be null.

Definition at line 22 of file ClpDualRowPivot.hpp.

## 3.18.2 Member Function Documentation

**3.18.2.1** `virtual double ClpDualRowPivot::updateWeights ( CoinIndexedVector * input, CoinIndexedVector * spare, CoinIndexedVector * spare2, CoinIndexedVector * updatedColumn ) [pure virtual]`

Updates weights and returns pivot alpha.

Also does FT update

Implemented in [ClpDualRowDantzig](#), and [ClpDualRowSteepest](#).

**3.18.2.2** `virtual void ClpDualRowPivot::saveWeights ( ClpSimplex * model, int mode ) [virtual]`

Saves any weights round factorization as pivot rows may change Will be empty unless steepest edge (will save model) May also recompute infeasibility stuff 1) before factorization 2) after good factorization (if weights empty may initialize) 3) after something happened but no factorization (e.g.

check for infeasible) 4) as 2 but restore weights from previous snapshot 5) for strong branching - initialize , infeasibilities

Reimplemented in [ClpDualRowSteepest](#).

The documentation for this class was generated from the following file:


- ClpDualRowPivot.hpp

## 3.19 ClpDualRowSteepest Class Reference


Dual Row Pivot Steepest Edge Algorithm Class.

```
#include <ClpDualRowSteepest.hpp>
```

Inheritance diagram for ClpDualRowSteepest:



Collaboration diagram for ClpDualRowSteepest:



## Public Types

- enum Persistence
  - enums for persistence*

## Public Member Functions

## Algorithmic methods

- virtual int **pivotRow** ()  
Returns pivot row, -1 if none.
- virtual double **updateWeights** (CoinIndexedVector \*input, CoinIndexedVector \*spare, CoinIndexedVector \*spare2, CoinIndexedVector \*updatedColumn)

- Updates weights and returns pivot alpha.*

  - virtual void [updatePrimalSolution](#) (CoinIndexedVector \*input, double theta, double &changeInObjective)

*Updates primal solution (and maybe list of candidates) Uses input vector which it deletes Computes change in objective function.*
- virtual void [saveWeights](#) (ClpSimplex \*model, int mode)

*Saves any weights round factorization as pivot rows may change Save model May also recompute infeasibility stuff 1) before factorization 2) after good factorization (if weights empty may initialize) 3) after something happened but no factorization (e.g.*
- virtual void [unrollWeights](#) ()

*Gets rid of last update.*
- virtual void [clearArrays](#) ()

*Gets rid of all arrays.*
- virtual bool [looksOptimal](#) () const

*Returns true if would not find any row.*
- virtual void [maximumPivotsChanged](#) ()

*Called when maximum pivots changes.*

#### Constructors and destructors

- [ClpDualRowSteepest](#) (int mode=3)
- Default Constructor 0 is uninitialized, 1 full, 2 is partial uninitialized, 3 starts as 2 but may switch to 1.*
- [ClpDualRowSteepest](#) (const [ClpDualRowSteepest](#) &)
- Copy constructor.*
- [ClpDualRowSteepest](#) & [operator=](#) (const [ClpDualRowSteepest](#) &rhs)
- Assignment operator.*
- void [fill](#) (const [ClpDualRowSteepest](#) &rhs)
- Fill most values.*
- virtual [~ClpDualRowSteepest](#) ()
- Destructor.*
- virtual [ClpDualRowPivot](#) \* [clone](#) (bool copyData=true) const
- Clone.*

#### gets and sets

- int [mode](#) () const
- Mode.*
- void [setPersistence](#) ([Persistence](#) life)
- Set/ get persistence.*
- [Persistence](#) [persistence](#) () const

#### 3.19.1 Detailed Description

Dual Row Pivot Steepest Edge Algorithm Class.

See Forrest-Goldfarb paper for algorithm

Definition at line 21 of file ClpDualRowSteepest.hpp.

## 3.19.2 Constructor &amp; Destructor Documentation

3.19.2.1 ClpDualRowSteepest::ClpDualRowSteepest ( int *mode* = 3 )

Default Constructor 0 is uninitialized, 1 full, 2 is partial uninitialized, 3 starts as 2 but may switch to 1.

By partial is meant that the weights are updated as normal but only part of the infeasible basic variables are scanned. This can be faster on very easy problems.

## 3.19.3 Member Function Documentation

3.19.3.1 virtual double ClpDualRowSteepest::updateWeights ( CoinIndexedVector \* *input*, CoinIndexedVector \* *spare*, CoinIndexedVector \* *spare2*, CoinIndexedVector \* *updatedColumn* ) [virtual]

Updates weights and returns pivot alpha.

Also does FT update

Implements [ClpDualRowPivot](#).

3.19.3.2 virtual void ClpDualRowSteepest::saveWeights ( ClpSimplex \* *model*, int *mode* ) [virtual]

Saves any weights round factorization as pivot rows may change Save model May also recompute infeasibility stuff 1) before factorization 2) after good factorization (if weights empty may initialize) 3) after something happened but no factorization (e.g.

check for infeasible) 4) as 2 but restore weights from previous snapshot 5) for strong branching - initialize (uninitialized) , infeasibilities

Reimplemented from [ClpDualRowPivot](#).

The documentation for this class was generated from the following file:


- [ClpDualRowSteepest.hpp](#)

## 3.20 ClpDummyMatrix Class Reference


This implements a dummy matrix as derived from [ClpMatrixBase](#).

```
#include <ClpDummyMatrix.hpp>
```

Inheritance diagram for ClpDummyMatrix:



Collaboration diagram for ClpDummyMatrix:



## Public Member Functions

### Useful methods

- virtual CoinPackedMatrix \* [getPackedMatrix](#) () const  
*Return a complete CoinPackedMatrix.*
- virtual bool [isColOrdered](#) () const  
*Whether the packed matrix is column major ordered or not.*
- virtual CoinBigIndex [getNumElements](#) () const  
*Number of entries in the packed matrix.*
- virtual int [getNumCols](#) () const  
*Number of columns.*
- virtual int [getNumRows](#) () const

- virtual const double \* [getElements](#) () const  
*A vector containing the elements in the packed matrix.*
- virtual const int \* [getIndices](#) () const  
*A vector containing the minor indices of the elements in the packed matrix.*
- virtual const CoinBigIndex \* [getVectorStarts](#) () const
- virtual const int \* [getVectorLengths](#) () const  
*The lengths of the major-dimension vectors.*
- virtual void [deleteCols](#) (const int numDel, const int \*indDel)  
*Delete the columns whose indices are listed in indDel.*
- virtual void [deleteRows](#) (const int numDel, const int \*indDel)  
*Delete the rows whose indices are listed in indDel.*
- virtual [ClpMatrixBase](#) \* [reverseOrderedCopy](#) () const  
*Returns a new matrix in reverse order without gaps.*
- virtual CoinBigIndex [countBasis](#) (const int \*whichColumn, int &numberColumnBasic)  
*Returns number of elements in column part of basis.*
- virtual void [fillBasis](#) ([ClpSimplex](#) \*model, const int \*whichColumn, int &numberColumnBasic, int \*row, int \*start, int \*rowCount, int \*columnCount, CoinFactorizationDouble \*element)  
*Fills in column part of basis.*
- virtual void [unpack](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const  
*Unpacks a column into an CoinIndexedvector.*
- virtual void [unpackPacked](#) ([ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const  
*Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.*
- virtual void [add](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column, double multiplier) const  
*Adds multiple of a column into an CoinIndexedvector You can use quickAdd to add to vector.*
- virtual void [add](#) (const [ClpSimplex](#) \*model, double \*array, int column, double multiplier) const  
*Adds multiple of a column into an array.*
- virtual void [releasePackedMatrix](#) () const  
*Allow any parts of a created CoinMatrix to be deleted Allow any parts of a created CoinPackedMatrix to be deleted.*

#### Matrix times vector methods

- virtual void [times](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + A * scalar * x$  in y.*
- virtual void [times](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale) const  
*And for scaling.*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + x * scalar * A$  in y.*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale) const

*And for scaling.*

- virtual void [transposeTimes](#) (const [ClpSimplex](#) \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const

*Return  $x * scalar * A + y$  in  $z$ .*

- virtual void [subsetTransposeTimes](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*x, const CoinIndexedVector \*y, CoinIndexedVector \*z) const

*Return  $x * A$  in  $z$  but just for indices in  $y$ .*

#### Constructors, destructor

- [ClpDummyMatrix](#) ()

*Default constructor.*

- [ClpDummyMatrix](#) (int numberColumns, int numberRows, int numberElements)

*Constructor with data.*

- virtual [~ClpDummyMatrix](#) ()

*Destructor.*

#### Copy method

- [ClpDummyMatrix](#) (const [ClpDummyMatrix](#) &)

*The copy constructor.*

- [ClpDummyMatrix](#) (const CoinPackedMatrix &)

*The copy constructor from an CoinDummyMatrix.*

- [ClpDummyMatrix](#) & **operator=** (const [ClpDummyMatrix](#) &)

- virtual [ClpMatrixBase](#) \* [clone](#) () const

*Clone.*

#### Protected Attributes

##### Data members

*The data members are protected to allow access for derived classes.*

- int [numberRows\\_](#)

*Number of rows.*

- int [numberColumns\\_](#)

*Number of columns.*

- int [numberElements\\_](#)

*Number of elements.*

#### 3.20.1 Detailed Description

This implements a dummy matrix as derived from [ClpMatrixBase](#).

This is so you can do [ClpPdco](#) but may come in useful elsewhere. It just has dimensions but no data

Definition at line 20 of file [ClpDummyMatrix.hpp](#).

### 3.20.2 Constructor & Destructor Documentation

#### 3.20.2.1 ClpDummyMatrix::ClpDummyMatrix ( )

Default constructor.

#### 3.20.2.2 ClpDummyMatrix::ClpDummyMatrix ( const ClpDummyMatrix & )

The copy constructor.

#### 3.20.2.3 ClpDummyMatrix::ClpDummyMatrix ( const CoinPackedMatrix & )

The copy constructor from an CoinDummyMatrix.

### 3.20.3 Member Function Documentation

#### 3.20.3.1 virtual bool ClpDummyMatrix::isColOrdered ( ) const [inline, virtual]

Whether the packed matrix is column major ordered or not.

Implements [ClpMatrixBase](#).

Definition at line 28 of file ClpDummyMatrix.hpp.

#### 3.20.3.2 virtual CoinBigIndex ClpDummyMatrix::getNumElements ( ) const [inline, virtual]

Number of entries in the packed matrix.

Implements [ClpMatrixBase](#).

Definition at line 32 of file ClpDummyMatrix.hpp.

#### 3.20.3.3 virtual int ClpDummyMatrix::getNumCols ( ) const [inline, virtual]

Number of columns.

Implements [ClpMatrixBase](#).

Definition at line 36 of file ClpDummyMatrix.hpp.

#### 3.20.3.4 virtual int ClpDummyMatrix::getNumRows ( ) const [inline, virtual]

Number of rows.

Implements [ClpMatrixBase](#).

Definition at line 40 of file ClpDummyMatrix.hpp.

#### 3.20.3.5 virtual const double\* ClpDummyMatrix::getElements ( ) const [virtual]

A vector containing the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together

with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

**3.20.3.6** `virtual const int* ClpDummyMatrix::getIndices ( ) const [virtual]`

A vector containing the minor indices of the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

**3.20.3.7** `virtual const int* ClpDummyMatrix::getVectorLengths ( ) const [virtual]`

The lengths of the major-dimension vectors.

Implements [ClpMatrixBase](#).

**3.20.3.8** `virtual void ClpDummyMatrix::deleteCols ( const int numDel, const int * indDel ) [virtual]`

Delete the columns whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.20.3.9** `virtual void ClpDummyMatrix::deleteRows ( const int numDel, const int * indDel ) [virtual]`

Delete the rows whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.20.3.10** `virtual void ClpDummyMatrix::unpackPacked ( ClpSimplex * model, CoinIndexedVector * rowArray, int column ) const [virtual]`

Unpacks a column into an `CoinIndexedvector` in packed format. Note that `model` is NOT const.

Bounds and objective could be modified if doing column generation (just for this variable)

Implements [ClpMatrixBase](#).

**3.20.3.11** `virtual void ClpDummyMatrix::times ( double scalar, const double * x, double * y ) const [virtual]`

Return  $y + A * scalar * x$  in `y`.

#### Precondition

`x` must be of size `numColumns()`  
`y` must be of size `numRows()`

Implements [ClpMatrixBase](#).

3.20.3.12 `virtual void ClpDummyMatrix::transposeTimes ( double scalar, const double * x, double * y ) const` [virtual]

Return  $y + x * scalar * A$  in  $y$ .

#### Precondition

$x$  must be of size `numRows()`  
 $y$  must be of size `numColumns()`

Implements [ClpMatrixBase](#).

3.20.3.13 `virtual void ClpDummyMatrix::transposeTimes ( const ClpSimplex * model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z ) const` [virtual]

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode

Implements [ClpMatrixBase](#).

3.20.3.14 `virtual void ClpDummyMatrix::subsetTransposeTimes ( const ClpSimplex * model, const CoinIndexedVector * x, const CoinIndexedVector * y, CoinIndexedVector * z ) const` [virtual]

Return  $x * A$  in  $z$  but just for indices in  $y$ .

Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#)

Implements [ClpMatrixBase](#).

The documentation for this class was generated from the following file:


- `ClpDummyMatrix.hpp`

## 3.21 ClpDynamicExampleMatrix Class Reference


This implements a dynamic matrix when we have a limit on the number of "interesting rows".

```
#include <ClpDynamicExampleMatrix.hpp>
```

Inheritance diagram for ClpDynamicExampleMatrix:



Collaboration diagram for ClpDynamicExampleMatrix:



## Public Member Functions

## Main functions provided

- virtual void [partialPricing](#) ([ClpSimplex](#) \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Partial pricing.*
- virtual void [createVariable](#) ([ClpSimplex](#) \*model, int &bestSequence)  
*Creates a variable.*
- virtual void [packDown](#) (const int \*in, int numberToPack)  
*If addColumn forces compression then this allows descendant to know what to do.*

## Constructors, destructor

- [ClpDynamicExampleMatrix](#) ()  
*Default constructor.*
- [ClpDynamicExampleMatrix](#) ([ClpSimplex](#) \*model, int numberSets, int numberColumns, const int \*starts, const double \*lower, const double \*upper, const int \*startColumn, const int \*row, const double \*element, const double \*cost, const double \*columnLower=NULL, const double \*columnUpper=NULL, const unsigned char \*status=NULL, const unsigned char \*dynamicStatus=NULL, int numberIds=0, const int \*ids=NULL)  
*This is the real constructor.*
- [ClpDynamicExampleMatrix](#) ([ClpSimplex](#) \*model, int numberSets, int numberColumns, int \*starts, const double \*lower, const double \*upper, int \*startColumn, int \*row, double \*element, double \*cost, double \*columnLower=NULL, double \*columnUpper=NULL, const unsigned char \*status=NULL, const unsigned char \*dynamicStatus=NULL, int numberIds=0, const int \*ids=NULL)  
*This constructor just takes over ownership (except for lower, upper)*
- virtual [~ClpDynamicExampleMatrix](#) ()  
*Destructor.*

## Copy method

- [ClpDynamicExampleMatrix](#) (const [ClpDynamicExampleMatrix](#) &)  
*The copy constructor.*
- [ClpDynamicExampleMatrix](#) & **operator=** (const [ClpDynamicExampleMatrix](#) &)
- virtual [ClpMatrixBase](#) \* [clone](#) () const  
*Clone.*

## gets and sets

- CoinBigIndex \* [startColumnGen](#) () const  
*Starts of each column.*
- int \* [rowGen](#) () const  
*rows*
- double \* [elementGen](#) () const  
*elements*
- double \* [costGen](#) () const

- costs*
- int \* [fullStartGen](#) () const
- full starts*
- int \* [idGen](#) () const
- ids in next level matrix*
- double \* [columnLowerGen](#) () const
- Optional lower bounds on columns.*
- double \* [columnUpperGen](#) () const
- Optional upper bounds on columns.*
- int [numberColumns](#) () const
- size*
- void **setDynamicStatusGen** (int sequence, [DynamicStatus](#) status)
- [DynamicStatus](#) **getDynamicStatusGen** (int sequence) const
- bool [flaggedGen](#) (int i) const
- Whether flagged.*
- void **setFlaggedGen** (int i)
- void **unsetFlagged** (int i)

#### Protected Attributes

##### Data members

*The data members are protected to allow access for derived classes.*

- int [numberColumns\\_](#)
- size*
- CoinBigIndex \* [startColumnGen\\_](#)
- Starts of each column.*
- int \* [rowGen\\_](#)
- rows*
- double \* [elementGen\\_](#)
- elements*
- double \* [costGen\\_](#)
- costs*
- int \* [fullStartGen\\_](#)
- start of each set*
- unsigned char \* [dynamicStatusGen\\_](#)
- for status and which bound*
- int \* [idGen\\_](#)
- identifier for each variable up one level (startColumn\_, etc).*
- double \* [columnLowerGen\\_](#)
- Optional lower bounds on columns.*
- double \* [columnUpperGen\\_](#)
- Optional upper bounds on columns.*

## 3.21.1 Detailed Description

This implements a dynamic matrix when we have a limit on the number of "interesting rows".

This version inherits from [ClpDynamicMatrix](#) and knows that the real matrix is gub. This acts just like [ClpDynamicMatrix](#) but generates columns. This "generates" columns by choosing from stored set. It is meant as a starting point as to how you could use shortest path to generate columns.

So it has its own copy of all data needed. It populates ClpDynamicMatrix with enough to allow for gub keys and active variables. In turn [ClpDynamicMatrix](#) populates a CoinPackedMatrix with active columns and rows.

As there is one copy here and one in ClpDynamicmatrix these names end in Gen\_

It is obviously more efficient to just use [ClpDynamicMatrix](#) but the idea is to show how much code a user would have to write.

This does not work very well with bounds

Definition at line 33 of file ClpDynamicExampleMatrix.hpp.

## 3.21.2 Constructor &amp; Destructor Documentation

## 3.21.2.1 ClpDynamicExampleMatrix::ClpDynamicExampleMatrix ( )

Default constructor.

**3.21.2.2 ClpDynamicExampleMatrix::ClpDynamicExampleMatrix ( ClpSimplex \* model, int numberSets, int numberColumns, const int \* starts, const double \* lower, const double \* upper, const int \* startColumn, const int \* row, const double \* element, const double \* cost, const double \* columnLower = NULL, const double \* columnUpper = NULL, const unsigned char \* status = NULL, const unsigned char \* dynamicStatus = NULL, int numberIds = 0, const int \* ids = NULL )**

This is the real constructor.

It assumes factorization frequency will not be changed. This resizes model !!!! The contents of original matrix in model will be taken over and original matrix will be sanitized so can be deleted (to avoid a very small memory leak)

**3.21.2.3 ClpDynamicExampleMatrix::ClpDynamicExampleMatrix ( const ClpDynamicExampleMatrix & )**

The copy constructor.

## 3.21.3 Member Function Documentation

3.21.3.1 `virtual void ClpDynamicExampleMatrix::createVariable ( ClpSimplex * model, int & bestSequence )` [virtual]

Creates a variable.

This is called after partial pricing and will modify matrix. Will update bestSequence.

Reimplemented from [ClpDynamicMatrix](#).

3.21.3.2 `virtual void ClpDynamicExampleMatrix::packDown ( const int * in, int numberToPack )` [virtual]

If addColumn forces compression then this allows descendant to know what to do.

If  $\geq$  then entry stayed in, if -1 then entry went out to lower bound of zero. Entries at upper bound (really nonzero) never go out (at present).

Reimplemented from [ClpDynamicMatrix](#).

#### 3.21.4 Member Data Documentation

3.21.4.1 `int* ClpDynamicExampleMatrix::idGen_` [protected]

identifier for each variable up one level (startColumn\_, etc).

This is of length maximumGubColumns\_. For this version it is just sequence number at this level

Definition at line 177 of file ClpDynamicExampleMatrix.hpp.

The documentation for this class was generated from the following file:


- ClpDynamicExampleMatrix.hpp

## 3.22 ClpDynamicMatrix Class Reference


This implements a dynamic matrix when we have a limit on the number of "interesting rows".

```
#include <ClpDynamicMatrix.hpp>
```

Inheritance diagram for ClpDynamicMatrix:



Collaboration diagram for ClpDynamicMatrix:



## Public Types

- enum [DynamicStatus](#)  
*enums for status of various sorts*

## Public Member Functions

## Main functions provided

- virtual void [partialPricing](#) ([ClpSimplex](#) \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Partial pricing.*
- virtual int [updatePivot](#) ([ClpSimplex](#) \*model, double oldInValue, double oldOutValue)  
*update information for a pivot (and effective rhs)*
- virtual double \* [rhsOffset](#) ([ClpSimplex](#) \*model, bool forceRefresh=false, bool check=false)  
*Returns effective RHS offset if it is being used.*
- virtual void [times](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + A * scalar * x$  in y.*
- void [modifyOffset](#) (int sequence, double amount)  
*Modifies rhs offset.*
- double [keyValue](#) (int iSet) const  
*Gets key value when none in small.*
- virtual void [dualExpanded](#) ([ClpSimplex](#) \*model, CoinIndexedVector \*array, double \*other, int mode)  
*mode=0 - Set up before "updateTranspose" and "transposeTimes" for duals using extended updates array (and may use other if dual values pass) mode=1 - Update dual solution after "transposeTimes" using extended rows.*
- virtual int [generalExpanded](#) ([ClpSimplex](#) \*model, int mode, int &number)  
*mode=0 - Create list of non-key basics in pivotVariable\_ using number as number-Basic in and out mode=1 - Set all key variables as basic mode=2 - return number extra rows needed, number gives maximum number basic mode=3 - before replaceColumn mode=4 - return 1 if can do primal, 2 if dual, 3 if both mode=5 - save any status stuff (when in good state) mode=6 - restore status stuff mode=7 - flag given variable (normally sequenceIn) mode=8 - unflag all variables mode=9 - synchronize costs mode=10 - return 1 if there may be changing bounds on variable (column generation) mode=11 - make sure set is clean (used when a variable rejected - but not flagged) mode=12 - after factorize but before permute stuff mode=13 - at end of simplex to delete stuff*
- virtual int [refresh](#) ([ClpSimplex](#) \*model)  
*Purely for column generation and similar ideas.*
- virtual void [createVariable](#) ([ClpSimplex](#) \*model, int &bestSequence)  
*Creates a variable.*
- virtual double [reducedCost](#) ([ClpSimplex](#) \*model, int sequence) const  
*Returns reduced cost of a variable.*
- void [gubCrash](#) ()  
*Does gub crash.*
- void [writeMps](#) (const char \*name)

- Writes out model (without names)*
- void [initialProblem](#) ()
  - Populates initial matrix from dynamic status.*
- int [addColumn](#) (int numberEntries, const int \*row, const double \*element, double cost, double lower, double upper, int iSet, [DynamicStatus](#) status)
  - Adds in a column to gub structure (called from descendant) and returns sequence.*
- virtual void [packDown](#) (const int \*, int)
  - If addColumn forces compression then this allows descendant to know what to do.*
- double [columnLower](#) (int sequence) const
  - Gets lower bound (to simplify coding)*
- double [columnUpper](#) (int sequence) const
  - Gets upper bound (to simplify coding)*

#### Constructors, destructor

- [ClpDynamicMatrix](#) ()
  - Default constructor.*
- [ClpDynamicMatrix](#) ([ClpSimplex](#) \*model, int numberSets, int numberColumns, const int \*starts, const double \*lower, const double \*upper, const [CoinBigIndex](#) \*startColumn, const int \*row, const double \*element, const double \*cost, const double \*columnLower=NULL, const double \*columnUpper=NULL, const unsigned char \*status=NULL, const unsigned char \*dynamicStatus=NULL)
  - This is the real constructor.*
- virtual [~ClpDynamicMatrix](#) ()
  - Destructor.*

#### Copy method

- [ClpDynamicMatrix](#) (const [ClpDynamicMatrix](#) &)
  - The copy constructor.*
- [ClpDynamicMatrix](#) (const [CoinPackedMatrix](#) &)
  - The copy constructor from an [CoinPackedMatrix](#).*
- [ClpDynamicMatrix](#) & **operator=** (const [ClpDynamicMatrix](#) &)
- virtual [ClpMatrixBase](#) \* [clone](#) () const
  - Clone.*

#### gets and sets

- [ClpSimplex::Status](#) [getStatus](#) (int sequence) const
  - Status of row slacks.*
- void **setStatus** (int sequence, [ClpSimplex::Status](#) status)
- bool [flaggedSlack](#) (int i) const
  - Whether flagged slack.*
- void **setFlaggedSlack** (int i)
- void **unsetFlaggedSlack** (int i)
- int [numberSets](#) () const
  - Number of sets (dynamic rows)*
- int [numberGubEntries](#) () const
  - Number of possible gub variables.*
- int \* [startSets](#) () const

- Sets.*
  - bool **flagged** (int i) const
  - Whether flagged.*
  - void **setFlagged** (int i)
  - void **unsetFlagged** (int i)
  - void **setDynamicStatus** (int sequence, **DynamicStatus** status)
  - **DynamicStatus** **getDynamicStatus** (int sequence) const
  - double **objectiveOffset** () const
  - Saved value of objective offset.*
  - CoinBigIndex \* **startColumn** () const
  - Starts of each column.*
  - int \* **row** () const
  - rows*
  - double \* **element** () const
  - elements*
  - double \* **cost** () const
  - costs*
  - int \* **id** () const
  - ids of active columns (just index here)*
  - double \* **columnLower** () const
  - Optional lower bounds on columns.*
  - double \* **columnUpper** () const
  - Optional upper bounds on columns.*
  - double \* **lowerSet** () const
  - Lower bounds on sets.*
  - double \* **upperSet** () const
  - Upper bounds on sets.*
  - int **numberGubColumns** () const
  - size*
  - int **firstAvailable** () const
  - first free*
  - int **firstDynamic** () const
  - first dynamic*
  - int **lastDynamic** () const
  - number of columns in dynamic model*
  - int **numberStaticRows** () const
  - number of rows in original model*
  - int **numberElements** () const
  - size of working matrix (max)*
  - int \* **keyVariable** () const
  - void **switchOffCheck** ()
  - Switches off dj checking each factorization (for BIG models)*
  - unsigned char \* **gubRowStatus** () const
  - Status region for gub slacks.*
  - unsigned char \* **dynamicStatus** () const
  - Status region for gub variables.*
  - int **whichSet** (int sequence) const
  - Returns which set a variable is in.*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- double [sumDualInfeasibilities\\_](#)  
*Sum of dual infeasibilities.*
- double [sumPrimalInfeasibilities\\_](#)  
*Sum of primal infeasibilities.*
- double [sumOfRelaxedDualInfeasibilities\\_](#)  
*Sum of Dual infeasibilities using tolerance based on error in duals.*
- double [sumOfRelaxedPrimalInfeasibilities\\_](#)  
*Sum of Primal infeasibilities using tolerance based on error in primals.*
- double [savedBestGubDual\\_](#)  
*Saved best dual on gub row in pricing.*
- int [savedBestSet\\_](#)  
*Saved best set in pricing.*
- int \* [backToPivotRow\\_](#)  
*Backward pointer to pivot row !!!*
- int \* [keyVariable\\_](#)  
*Key variable of set (only accurate if none in small problem)*
- int \* [toIndex\\_](#)  
*Backward pointer to extra row.*
- int \* [fromIndex\\_](#)
- int [numberSets\\_](#)  
*Number of sets (dynamic rows)*
- int [numberActiveSets\\_](#)  
*Number of active sets.*
- double [objectiveOffset\\_](#)  
*Saved value of objective offset.*
- double \* [lowerSet\\_](#)  
*Lower bounds on sets.*
- double \* [upperSet\\_](#)  
*Upper bounds on sets.*
- unsigned char \* [status\\_](#)  
*Status of slack on set.*
- [ClpSimplex](#) \* [model\\_](#)  
*Pointer back to model.*
- int [firstAvailable\\_](#)  
*first free*
- int [firstAvailableBefore\\_](#)  
*first free when iteration started*
- int [firstDynamic\\_](#)  
*first dynamic*
- int [lastDynamic\\_](#)  
*number of columns in dynamic model*
- int [numberStaticRows\\_](#)

- number of rows in original model*
- int [numberElements\\_](#)
- size of working matrix (max)*
- int [numberDualInfeasibilities\\_](#)
- Number of dual infeasibilities.*
- int [numberPrimalInfeasibilities\\_](#)
- Number of primal infeasibilities.*
- int [noCheck\\_](#)
- If pricing will declare victory (i.e.*
- double [infeasibilityWeight\\_](#)
- Infeasibility weight when last full pass done.*
- int [numberGubColumns\\_](#)
- size*
- int [maximumGubColumns\\_](#)
- current maximum number of columns (then compress)*
- int [maximumElements\\_](#)
- current maximum number of elements (then compress)*
- int \* [startSet\\_](#)
- Start of each set.*
- int \* [next\\_](#)
- next in chain*
- CoinBigIndex \* [startColumn\\_](#)
- Starts of each column.*
- int \* [row\\_](#)
- rows*
- double \* [element\\_](#)
- elements*
- double \* [cost\\_](#)
- costs*
- int \* [id\\_](#)
- ids of active columns (just index here)*
- unsigned char \* [dynamicStatus\\_](#)
- for status and which bound*
- double \* [columnLower\\_](#)
- Optional lower bounds on columns.*
- double \* [columnUpper\\_](#)
- Optional upper bounds on columns.*

### 3.22.1 Detailed Description

This implements a dynamic matrix when we have a limit on the number of "interesting rows".

This version inherits from [ClpPackedMatrix](#) and knows that the real matrix is gub. A later version could use shortest path to generate columns.

Definition at line 20 of file [ClpDynamicMatrix.hpp](#).

## 3.22.2 Constructor &amp; Destructor Documentation

## 3.22.2.1 ClpDynamicMatrix::ClpDynamicMatrix ( )

Default constructor.

3.22.2.2 **ClpDynamicMatrix::ClpDynamicMatrix ( ClpSimplex \* *model*, int *numberSets*, int *numberColumns*, const int \* *starts*, const double \* *lower*, const double \* *upper*, const CoinBigIndex \* *startColumn*, const int \* *row*, const double \* *element*, const double \* *cost*, const double \* *columnLower* = NULL, const double \* *columnUpper* = NULL, const unsigned char \* *status* = NULL, const unsigned char \* *dynamicStatus* = NULL )**

This is the real constructor.

It assumes factorization frequency will not be changed. This resizes model !!!! The contents of original matrix in model will be taken over and original matrix will be sanitized so can be deleted (to avoid a very small memory leak)

## 3.22.2.3 ClpDynamicMatrix::ClpDynamicMatrix ( const ClpDynamicMatrix &amp; )

The copy constructor.

## 3.22.2.4 ClpDynamicMatrix::ClpDynamicMatrix ( const CoinPackedMatrix &amp; )

The copy constructor from an CoinPackedMatrix.

## 3.22.3 Member Function Documentation

3.22.3.1 **virtual double\* ClpDynamicMatrix::rhsOffset ( ClpSimplex \* *model*, bool *forceRefresh* = false, bool *check* = false ) [virtual]**

Returns effective RHS offset if it is being used.

This is used for long problems or big dynamic or anywhere where going through full columns is expensive. This may re-compute

Reimplemented from [ClpMatrixBase](#).

3.22.3.2 **virtual void ClpDynamicMatrix::times ( double *scalar*, const double \* *x*, double \* *y* ) const [virtual]**

Return  $y + A * scalar * x$  in  $y$ .

**Precondition**

$x$  must be of size `numColumns()`  
 $y$  must be of size `numRows()`

Reimplemented from [ClpPackedMatrix](#).

**3.22.3.3** `virtual void ClpDynamicMatrix::dualExpanded ( ClpSimplex * model,  
CoinIndexedVector * array, double * other, int mode ) [virtual]`

mode=0 - Set up before "updateTranspose" and "transposeTimes" for duals using extended updates array (and may use other if dual values pass) mode=1 - Update dual solution after "transposeTimes" using extended rows.

mode=2 - Compute all djs and compute key dual infeasibilities mode=3 - Report on key dual infeasibilities mode=4 - Modify before updateTranspose in partial pricing

Reimplemented from [ClpMatrixBase](#).

**3.22.3.4** `virtual int ClpDynamicMatrix::refresh ( ClpSimplex * model ) [virtual]`

Purely for column generation and similar ideas.

Allows matrix and any bounds or costs to be updated (sensibly). Returns non-zero if any changes.

Reimplemented from [ClpPackedMatrix](#).

**3.22.3.5** `virtual void ClpDynamicMatrix::createVariable ( ClpSimplex * model, int &  
bestSequence ) [virtual]`

Creates a variable.

This is called after partial pricing and will modify matrix. Will update bestSequence.

Reimplemented from [ClpMatrixBase](#).

Reimplemented in [ClpDynamicExampleMatrix](#).

**3.22.3.6** `virtual void ClpDynamicMatrix::packDown ( const int *, int ) [inline,  
virtual]`

If addColumn forces compression then this allows descendant to know what to do.

If  $\geq 0$  then entry stayed in, if -1 then entry went out to lower bound of zero. Entries at upper bound (really nonzero) never go out (at present).

Reimplemented in [ClpDynamicExampleMatrix](#).

Definition at line 109 of file ClpDynamicMatrix.hpp.

## 3.22.4 Member Data Documentation

**3.22.4.1** `int ClpDynamicMatrix::noCheck_ [protected]`

If pricing will declare victory (i.e.

no check every factorization). -1 - always check 0 - don't check 1 - in don't check mode but looks optimal

Definition at line 349 of file ClpDynamicMatrix.hpp.

The documentation for this class was generated from the following file:


- ClpDynamicMatrix.hpp

### 3.23 ClpEventHandler Class Reference


Base class for Clp event handling.

```
#include <ClpEventHandler.hpp>
```

Inheritance diagram for ClpEventHandler:



Collaboration diagram for ClpEventHandler:



#### Public Types

- enum [Event](#)  
*enums for what sort of event.*

## Public Member Functions

Virtual method that the derived classes should provide.

*The base class instance does nothing and as `event()` is only useful method it would not be very useful NOT providing one!*

- virtual int `event` (`Event` whichEvent)  
*This can do whatever it likes.*

## Constructors, destructor

- `ClpEventHandler` (`ClpSimplex` \*model=NULL)  
*Default constructor.*
- virtual `~ClpEventHandler` ()  
*Destructor.*
- **`ClpEventHandler`** (const `ClpEventHandler` &)
- `ClpEventHandler` & **`operator=`** (const `ClpEventHandler` &)
- virtual `ClpEventHandler` \* `clone` () const  
*Clone.*

## Sets/gets

- void `setSimplex` (`ClpSimplex` \*model)  
*set model.*
- `ClpSimplex` \* `simplex` () const  
*Get model.*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- `ClpSimplex` \* `model_`  
*Pointer to simplex.*

## 3.23.1 Detailed Description

Base class for Clp event handling.

This is just here to allow for event handling. By event I mean a Clp event e.g. end of values pass.

One use would be to let a user handle a system event e.g. Control-C. This could be done by deriving a class `MyEventHandler` which knows about such events. If one occurs `MyEventHandler::event()` could clear event status and return 3 (stopped).

Clp would then return to user code.

As it is called every iteration this should be fine grained enough.

User can derive and construct from `CbcModel` - not pretty

Definition at line 27 of file `ClpEventHandler.hpp`.

### 3.23.2 Member Enumeration Documentation

#### 3.23.2.1 enum ClpEventHandler::Event

enums for what sort of event.

These will also be returned in [ClpModel::secondaryStatus\(\)](#) as int

Definition at line 34 of file ClpEventHandler.hpp.

### 3.23.3 Constructor & Destructor Documentation

#### 3.23.3.1 ClpEventHandler::ClpEventHandler ( ClpSimplex \* *model* = NULL )

Default constructor.

### 3.23.4 Member Function Documentation

#### 3.23.4.1 virtual int ClpEventHandler::event ( Event *whichEvent* ) [virtual]

This can do whatever it likes.

If return code -1 then carries on if 0 sets [ClpModel::status\(\)](#) to 5 (stopped by event) and will return to user. At present if <-1 carries on and if >0 acts as if 0 - this may change. For [ClpSolve](#) 2 -> too big return status of -2 and -> too small 3

Reimplemented in [MyEventHandler](#).

#### 3.23.4.2 void ClpEventHandler::setSimplex ( ClpSimplex \* *model* )

set model.

The documentation for this class was generated from the following file:


- ClpEventHandler.hpp

## 3.24 ClpFactorization Class Reference

This just implements CoinFactorization when an [ClpMatrixBase](#) object is passed.

```
#include <ClpFactorization.hpp>
```

Collaboration diagram for ClpFactorization:



## Public Member Functions

### factorization

- `int factorize (ClpSimplex *model, int solveType, bool valuesPass)`  
When part of LP - given by basic variables.

### Constructors, destructor

- `ClpFactorization ()`  
Default constructor.
- `~ClpFactorization ()`  
Destructor.

## Copy method

- [ClpFactorization](#) (const [CoinFactorization](#) &)  
*The copy constructor from an [CoinFactorization](#).*
- [ClpFactorization](#) (const [ClpFactorization](#) &, int denselfSmaller=0)  
*The copy constructor.*
- [ClpFactorization](#) (const [CoinOtherFactorization](#) &)  
*The copy constructor from an [CoinOtherFactorization](#).*
- [ClpFactorization](#) & **operator=** (const [ClpFactorization](#) &)

## rank one updates which do exist

- int [replaceColumn](#) (const [ClpSimplex](#) \*model, [CoinIndexedVector](#) \*regionSparse, [CoinIndexedVector](#) \*tableauColumn, int pivotRow, double pivotCheck, bool checkBeforeModifying=false, double acceptablePivot=1.0e-8)  
*Replaces one Column to basis, returns 0=OK, 1=Probably OK, 2=singular, 3=no room If checkBeforeModifying is true will do all accuracy checks before modifying factorization.*

## various uses of factorization (return code number elements)

## which user may want to know about

- int [updateColumnFT](#) ([CoinIndexedVector](#) \*regionSparse, [CoinIndexedVector](#) \*regionSparse2)  
*Updates one column (FTRAN) from region2 Tries to do FT update number returned is negative if no room region1 starts as zero and is zero at end.*
- int [updateColumn](#) ([CoinIndexedVector](#) \*regionSparse, [CoinIndexedVector](#) \*regionSparse2, bool noPermute=false) const  
*Updates one column (FTRAN) from region2 region1 starts as zero and is zero at end.*
- int [updateTwoColumnsFT](#) ([CoinIndexedVector](#) \*regionSparse1, [CoinIndexedVector](#) \*regionSparse2, [CoinIndexedVector](#) \*regionSparse3, bool noPermuteRegion3=false)  
*Updates one column (FTRAN) from region2 Tries to do FT update number returned is negative if no room.*
- int [updateColumnForDebug](#) ([CoinIndexedVector](#) \*regionSparse, [CoinIndexedVector](#) \*regionSparse2, bool noPermute=false) const  
*For debug (no statistics update)*
- int [updateColumnTranspose](#) ([CoinIndexedVector](#) \*regionSparse, [CoinIndexedVector](#) \*regionSparse2) const  
*Updates one column (BTRAN) from region2 region1 starts as zero and is zero at end.*

Lifted from [CoinFactorization](#)

- int [numberElements](#) () const  
*Total number of elements in factorization.*
- int \* [permute](#) () const  
*Returns address of permute region.*
- int \* [pivotColumn](#) () const

- Returns address of pivotColumn region (also used for permuting)*

  - int `maximumPivots` () const  
*Maximum number of pivots between factorizations.*
  - void `maximumPivots` (int value)  
*Set maximum number of pivots between factorizations.*
  - int `pivots` () const  
*Returns number of pivots since factorization.*
  - double `areaFactor` () const  
*Whether larger areas needed.*
  - void `areaFactor` (double value)  
*Set whether larger areas needed.*
  - double `zeroTolerance` () const  
*Zero tolerance.*
  - void `zeroTolerance` (double value)  
*Set zero tolerance.*
  - void `saferTolerances` (double zeroTolerance, double pivotTolerance)  
*Set tolerances to safer of existing and given.*
  - int `sparseThreshold` () const  
*get sparse threshold*
  - void `sparseThreshold` (int value)  
*Set sparse threshold.*
  - int `status` () const  
*Returns status.*
  - void `setStatus` (int value)  
*Sets status.*
  - int `numberDense` () const  
*Returns number of dense rows.*
  - CoinBigIndex `numberElementsU` () const  
*Returns number in U area.*
  - CoinBigIndex `numberElementsL` () const  
*Returns number in L area.*
  - CoinBigIndex `numberElementsR` () const  
*Returns number in R area.*
  - bool `timeToRefactorize` () const
  - int `messageLevel` () const  
*Level of detail of messages.*
  - void `messageLevel` (int value)  
*Set level of detail of messages.*
  - void `clearArrays` ()  
*Get rid of all memory.*
  - int `numberRows` () const  
*Number of Rows after factorization.*
  - int `denseThreshold` () const  
*Gets dense threshold.*
  - void `setDenseThreshold` (int value)  
*Sets dense threshold.*
  - double `pivotTolerance` () const

- Pivot tolerance.*
- void [pivotTolerance](#) (double value)
- Set pivot tolerance.*
- void [relaxAccuracyCheck](#) (double value)
- Allows change of pivot accuracy check 1.0 == none > 1.0 relaxed.*
- int [persistenceFlag](#) () const
- Array persistence flag If 0 then as now (delete/new) 1 then only do arrays if bigger needed 2 as 1 but give a bit extra if bigger needed.*
- void [setPersistenceFlag](#) (int value)
- void [almostDestructor](#) ()
- Delete all stuff (leaves as after CoinFactorization())*
- double [adjustedAreaFactor](#) () const
- Returns areaFactor but adjusted for dense.*
- void [setBiasLU](#) (int value)
- void [setForrestTomlin](#) (bool value)
- true if Forrest Tomlin update, false if PFI*
- void [setDefaultValues](#) ()
- Sets default values.*
- void [forceOtherFactorization](#) (int which)
- If nonzero force use of 1,dense 2,small 3,osl.*
- int [goOslThreshold](#) () const
- Get switch to osl if number rows <= this.*
- void [setGoOslThreshold](#) (int value)
- Set switch to osl if number rows <= this.*
- int [goDenseThreshold](#) () const
- Get switch to dense if number rows <= this.*
- void [setGoDenseThreshold](#) (int value)
- Set switch to dense if number rows <= this.*
- int [goSmallThreshold](#) () const
- Get switch to small if number rows <= this.*
- void [setGoSmallThreshold](#) (int value)
- Set switch to small if number rows <= this.*
- void [goDenseOrSmall](#) (int numberOfRows)
- Go over to dense or small code if small enough.*
- void [setFactorization](#) ([ClpFactorization](#) &factorization)
- Sets factorization.*
- int [isDenseOrSmall](#) () const
- Return 1 if dense code.*

#### other stuff

- void [goSparse](#) ()
- makes a row copy of L for speed and to allow very sparse problems*
- void [cleanUp](#) ()
- Cleans up i.e. gets rid of network basis.*
- bool [needToReorder](#) () const
- Says whether to redo pivot order.*
- bool [networkBasis](#) () const
- Says if a network basis.*
- void [getWeights](#) (int \*weights) const
- Fills weighted row list.*

## 3.24.1 Detailed Description

This just implements CoinFactorization when an [ClpMatrixBase](#) object is passed.

If a network then has a dummy CoinFactorization and a genuine [ClpNetworkBasis](#) object

Definition at line 32 of file ClpFactorization.hpp.

## 3.24.2 Constructor &amp; Destructor Documentation

## 3.24.2.1 ClpFactorization::ClpFactorization ( )

Default constructor.

## 3.24.2.2 ClpFactorization::ClpFactorization ( const CoinFactorization &amp; )

The copy constructor from an CoinFactorization.

3.24.2.3 ClpFactorization::ClpFactorization ( const ClpFactorization & , int *denselfSmaller* = 0 )

The copy constructor.

## 3.24.2.4 ClpFactorization::ClpFactorization ( const CoinOtherFactorization &amp; )

The copy constructor from an CoinOtherFactorization.

## 3.24.3 Member Function Documentation

3.24.3.1 int ClpFactorization::factorize ( ClpSimplex \* *model*, int *solveType*, bool *valuesPass* )

When part of LP - given by basic variables.

Actually does factorization. Arrays passed in have non negative value to say basic. If status is okay, basic variables have pivot row - this is only needed if *increasingRows\_* > 1. Allows scaling If status is singular, then basic variables have pivot row and ones thrown out have -1 returns 0 -okay, -1 singular, -2 too many in basis, -99 memory

3.24.3.2 int ClpFactorization::replaceColumn ( const ClpSimplex \* *model*, CoinIndexedVector \* *regionSparse*, CoinIndexedVector \* *tableauColumn*, int *pivotRow*, double *pivotCheck*, bool *checkBeforeModifying* = false, double *acceptablePivot* = 1.0e-8 )

Replaces one Column to basis, returns 0=OK, 1=Probably OK, 2=singular, 3=no room If *checkBeforeModifying* is true will do all accuracy checks before modifying factorization.

Whether to set this depends on speed considerations. You could just do this on first iteration after factorization and thereafter re-factorize partial update already in U

3.24.3.3 `int ClpFactorization::updateTwoColumnsFT ( CoinIndexedVector * regionSparse1,  
CoinIndexedVector * regionSparse2, CoinIndexedVector * regionSparse3, bool  
noPermuteRegion3 = false )`

Updates one column (FTRAN) from region2 Tries to do FT update number returned is negative if no room.

Also updates region3 region1 starts as zero and is zero at end

The documentation for this class was generated from the following file:


- ClpFactorization.hpp

### 3.25 ClpGubDynamicMatrix Class Reference


This implements Gub rows plus a [ClpPackedMatrix](#).

```
#include <ClpGubDynamicMatrix.hpp>
```

Inheritance diagram for ClpGubDynamicMatrix:



Collaboration diagram for ClpGubDynamicMatrix:



## Public Member Functions

### Main functions provided

- virtual void **partialPricing** (**ClpSimplex** \*model, double start, double end, int &bestSequence, int &numberWanted)
  - Partial pricing.*
- virtual int **synchronize** (**ClpSimplex** \*model, int mode)
  - This is local to Gub to allow synchronization: mode=0 when status of basis is good mode=1 when variable is flagged mode=2 when all variables unflagged (returns number flagged) mode=3 just reset costs (primal) mode=4 correct number of dual infeasibilities mode=5 return 4 if time to re-factorize mode=8 - make sure set is clean mode=9 - adjust lower, upper on set by incoming.*
- virtual void **useEffectiveRhs** (**ClpSimplex** \*model, bool cheapest=true)
  - Sets up an effective RHS and does gub crash if needed.*
- virtual int **updatePivot** (**ClpSimplex** \*model, double oldInValue, double oldOutValue)
  - update information for a pivot (and effective rhs)*
- void **insertNonBasic** (int sequence, int iSet)
  - Add a new variable to a set.*
- virtual double \* **rhsOffset** (**ClpSimplex** \*model, bool forceRefresh=false, bool check=false)
  - Returns effective RHS offset if it is being used.*
- virtual void **times** (double scalar, const double \*x, double \*y) const
  - Return  $y + A * scalar * x$  in  $y$ .*
- virtual int **checkFeasible** (**ClpSimplex** \*model, double &sum) const
  - Just for debug Returns sum and number of primal infeasibilities.*
- void **cleanData** (**ClpSimplex** \*model)
  - Cleans data after setWarmStart.*

**Constructors, destructor**

- [ClpGubDynamicMatrix](#) ()  
*Default constructor.*
- virtual [~ClpGubDynamicMatrix](#) ()  
*Destructor.*

**Copy method**

- [ClpGubDynamicMatrix](#) (const [ClpGubDynamicMatrix](#) &)  
*The copy constructor.*
- [ClpGubDynamicMatrix](#) ([ClpSimplex](#) \*model, int numberSets, int numberColumns, const int \*starts, const double \*lower, const double \*upper, const int \*startColumn, const int \*row, const double \*element, const double \*cost, const double \*lowerColumn=NULL, const double \*upperColumn=NULL, const unsigned char \*status=NULL)  
*This is the real constructor.*
- [ClpGubDynamicMatrix](#) & **operator=** (const [ClpGubDynamicMatrix](#) &)
- virtual [ClpMatrixBase](#) \* [clone](#) () const  
*Clone.*

**Protected Attributes****Data members**

*The data members are protected to allow access for derived classes.*

- double [objectiveOffset\\_](#)  
*Saved value of objective offset.*
- CoinBigIndex \* [startColumn\\_](#)  
*Starts of each column.*
- int \* [row\\_](#)  
*rows*
- double \* [element\\_](#)  
*elements*
- double \* [cost\\_](#)  
*costs*
- int \* [fullStart\\_](#)  
*full starts*
- int \* [id\\_](#)  
*ids of active columns (just index here)*
- unsigned char \* [dynamicStatus\\_](#)  
*for status and which bound*
- double \* [lowerColumn\\_](#)  
*Optional lower bounds on columns.*
- double \* [upperColumn\\_](#)  
*Optional upper bounds on columns.*
- double \* [lowerSet\\_](#)  
*Optional true lower bounds on sets.*
- double \* [upperSet\\_](#)

*Optional true upper bounds on sets.*

- int [numberGubColumns\\_](#)  
*size*
- int [firstAvailable\\_](#)  
*first free*
- int [savedFirstAvailable\\_](#)  
*saved first free*
- int [firstDynamic\\_](#)  
*first dynamic*
- int [lastDynamic\\_](#)  
*number of columns in dynamic model*
- int [numberElements\\_](#)  
*size of working matrix (max)*

#### gets and sets

- enum [DynamicStatus](#)  
*enums for status of various sorts*
- bool [flagged](#) (int i) const  
*Whether flagged.*
- void [setFlagged](#) (int i)  
*To flag a variable.*
- void [unsetFlagged](#) (int i)
- void [setDynamicStatus](#) (int sequence, [DynamicStatus](#) status)
- [DynamicStatus](#) [getDynamicStatus](#) (int sequence) const
- double [objectiveOffset](#) () const  
*Saved value of objective offset.*
- CoinBigIndex \* [startColumn](#) () const  
*Starts of each column.*
- int \* [row](#) () const  
*rows*
- double \* [element](#) () const  
*elements*
- double \* [cost](#) () const  
*costs*
- int \* [fullStart](#) () const  
*full starts*
- int \* [id](#) () const  
*ids of active columns (just index here)*
- double \* [lowerColumn](#) () const  
*Optional lower bounds on columns.*
- double \* [upperColumn](#) () const  
*Optional upper bounds on columns.*
- double \* [lowerSet](#) () const

- Optional true lower bounds on sets.*
  - double \* [upperSet](#) () const
- Optional true upper bounds on sets.*
  - int [numberGubColumns](#) () const
- size*
  - int [firstAvailable](#) () const
- first free*
  - void [setFirstAvailable](#) (int value)
- set first free*
  - int [firstDynamic](#) () const
- first dynamic*
  - int [lastDynamic](#) () const
- number of columns in dynamic model*
  - int [numberElements](#) () const
- size of working matrix (max)*
  - unsigned char \* [gubRowStatus](#) () const
- Status region for gub slacks.*
  - unsigned char \* [dynamicStatus](#) () const
- Status region for gub variables.*
  - int [whichSet](#) (int sequence) const
- Returns which set a variable is in.*

### 3.25.1 Detailed Description

This implements Gub rows plus a [ClpPackedMatrix](#).

This a dynamic version which stores the gub part and dynamically creates matrix. All bounds are assumed to be zero and infinity

This is just a simple example for real column generation

Definition at line 20 of file ClpGubDynamicMatrix.hpp.

### 3.25.2 Constructor & Destructor Documentation

#### 3.25.2.1 ClpGubDynamicMatrix::ClpGubDynamicMatrix ( )

Default constructor.

#### 3.25.2.2 ClpGubDynamicMatrix::ClpGubDynamicMatrix ( const ClpGubDynamicMatrix & )

The copy constructor.

**3.25.2.3** `ClpGubDynamicMatrix::ClpGubDynamicMatrix ( ClpSimplex * model, int numberSets, int numberColumns, const int * starts, const double * lower, const double * upper, const int * startColumn, const int * row, const double * element, const double * cost, const double * lowerColumn = NULL, const double * upperColumn = NULL, const unsigned char * status = NULL )`

This is the real constructor.

It assumes factorization frequency will not be changed. This resizes model !!!!

### 3.25.3 Member Function Documentation

**3.25.3.1** `virtual double* ClpGubDynamicMatrix::rhsOffset ( ClpSimplex * model, bool forceRefresh = false, bool check = false ) [virtual]`

Returns effective RHS offset if it is being used.

This is used for long problems or big gub or anywhere where going through full columns is expensive. This may re-compute

Reimplemented from [ClpGubMatrix](#).

**3.25.3.2** `virtual void ClpGubDynamicMatrix::times ( double scalar, const double * x, double * y ) const [virtual]`

Return  $y + A * scalar * x$  in  $y$ .

#### Precondition

$x$  must be of size `numColumns()`  
 $y$  must be of size `numRows()`

Reimplemented from [ClpPackedMatrix](#).

**3.25.3.3** `virtual int ClpGubDynamicMatrix::checkFeasible ( ClpSimplex * model, double & sum ) const [virtual]`

Just for debug Returns sum and number of primal infeasibilities.

Recomputes keys

Reimplemented from [ClpMatrixBase](#).

The documentation for this class was generated from the following file:


- [ClpGubDynamicMatrix.hpp](#)

## 3.26 ClpGubMatrix Class Reference


This implements Gub rows plus a [ClpPackedMatrix](#).

```
#include <ClpGubMatrix.hpp>
```

Inheritance diagram for ClpGubMatrix:



Collaboration diagram for ClpGubMatrix:



## Public Member Functions

## Main functions provided

- virtual [ClpMatrixBase](#) \* [reverseOrderedCopy](#) () const  
*Returns a new matrix in reverse order without gaps (GUB wants NULL)*
- virtual [CoinBigIndex](#) [countBasis](#) (const int \*whichColumn, int &numberColumnBasic)  
*Returns number of elements in column part of basis.*
- virtual void [fillBasis](#) ([ClpSimplex](#) \*model, const int \*whichColumn, int &numberColumnBasic, int \*row, int \*start, int \*rowCount, int \*columnCount, [CoinFactorizationDouble](#) \*element)  
*Fills in column part of basis.*
- virtual void [unpack](#) (const [ClpSimplex](#) \*model, [CoinIndexedVector](#) \*rowArray, int column) const  
*Unpacks a column into an [CoinIndexedvector](#).*
- virtual void [unpackPacked](#) ([ClpSimplex](#) \*model, [CoinIndexedVector](#) \*rowArray, int column) const  
*Unpacks a column into an [CoinIndexedvector](#) in packed format Note that model is NOT const.*
- virtual void [add](#) (const [ClpSimplex](#) \*model, [CoinIndexedVector](#) \*rowArray, int column, double multiplier) const  
*Adds multiple of a column into an [CoinIndexedvector](#) You can use [quickAdd](#) to add to vector.*
- virtual void [add](#) (const [ClpSimplex](#) \*model, double \*array, int column, double multiplier) const  
*Adds multiple of a column into an array.*
- virtual void [partialPricing](#) ([ClpSimplex](#) \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Partial pricing.*
- virtual int [hiddenRows](#) () const  
*Returns number of hidden rows e.g. gub.*

## Matrix times vector methods

- virtual void [transposeTimes](#) (const [ClpSimplex](#) \*model, double scalar, const [CoinIndexedVector](#) \*x, [CoinIndexedVector](#) \*y, [CoinIndexedVector](#) \*z) const  
*Return  $x * scalar * A + y$  in  $z$ .*
- virtual void [transposeTimesByRow](#) (const [ClpSimplex](#) \*model, double scalar, const [CoinIndexedVector](#) \*x, [CoinIndexedVector](#) \*y, [CoinIndexedVector](#) \*z) const  
*Return  $x * scalar * A + y$  in  $z$ .*
- virtual void [subsetTransposeTimes](#) (const [ClpSimplex](#) \*model, const [CoinIndexedVector](#) \*x, const [CoinIndexedVector](#) \*y, [CoinIndexedVector](#) \*z) const  
*Return  $x * A$  in  $z$  but just for indices in  $y$ .*
- virtual int [extendUpdated](#) ([ClpSimplex](#) \*model, [CoinIndexedVector](#) \*update, int mode)  
*expands an updated column to allow for extra rows which the main solver does not know about and returns number added if mode 0.*
- virtual void [primalExpanded](#) ([ClpSimplex](#) \*model, int mode)

- mode=0 - Set up before "update" and "times" for primal solution using extended rows*  
*mode=1 - Cleanup primal solution after "times" using extended rows.*
- virtual void [dualExpanded](#) ([ClpSimplex](#) \*model, [CoinIndexedVector](#) \*array, double \*other, int mode)
  - mode=0 - Set up before "updateTranspose" and "transposeTimes" for duals using extended updates array (and may use other if dual values pass)*  
*mode=1 - Update dual solution after "transposeTimes" using extended rows.*
- virtual int [generalExpanded](#) ([ClpSimplex](#) \*model, int mode, int &number)
  - mode=0 - Create list of non-key basics in pivotVariable\_ using number as number-Basic in and out*  
*mode=1 - Set all key variables as basic*  
*mode=2 - return number extra rows needed, number gives maximum number basic*  
*mode=3 - before replaceColumn*  
*mode=4 - return 1 if can do primal, 2 if dual, 3 if both*  
*mode=5 - save any status stuff (when in good state)*  
*mode=6 - restore status stuff*  
*mode=7 - flag given variable (normally sequenceIn)*  
*mode=8 - unflag all variables*  
*mode=9 - synchronize costs*  
*mode=10 - return 1 if there may be changing bounds on variable (column generation)*  
*mode=11 - make sure set is clean (used when a variable rejected - but not flagged)*  
*mode=12 - after factorize but before permute stuff*  
*mode=13 - at end of simplex to delete stuff*
- virtual int [updatePivot](#) ([ClpSimplex](#) \*model, double oldInValue, double oldOutValue)
  - update information for a pivot (and effective rhs)*
- virtual void [useEffectiveRhs](#) ([ClpSimplex](#) \*model, bool cheapest=true)
  - Sets up an effective RHS and does gub crash if needed.*
- virtual double \* [rhsOffset](#) ([ClpSimplex](#) \*model, bool forceRefresh=false, bool check=false)
  - Returns effective RHS offset if it is being used.*
- virtual int [synchronize](#) ([ClpSimplex](#) \*model, int mode)
  - This is local to Gub to allow synchronization: mode=0 when status of basis is good*  
*mode=1 when variable is flagged*  
*mode=2 when all variables unflagged (returns number flagged)*  
*mode=3 just reset costs (primal)*  
*mode=4 correct number of dual infeasibilities*  
*mode=5 return 4 if time to re-factorize*  
*mode=6 - return 1 if there may be changing bounds on variable (column generation)*  
*mode=7 - do extra restores for column generation*  
*mode=8 - make sure set is clean*  
*mode=9 - adjust lower, upper on set by incoming.*
- virtual void [correctSequence](#) (const [ClpSimplex](#) \*model, int &sequenceIn, int &sequenceOut)
  - Correct sequence in and out to give true value.*

#### Constructors, destructor

- [ClpGubMatrix](#) ()
  - Default constructor.*
- virtual [~ClpGubMatrix](#) ()
  - Destructor.*

#### Copy method

- [ClpGubMatrix](#) (const [ClpGubMatrix](#) &)
  - The copy constructor.*
- [ClpGubMatrix](#) (const [CoinPackedMatrix](#) &)
  - The copy constructor from an [CoinPackedMatrix](#).*

- [ClpGubMatrix](#) (const [ClpGubMatrix](#) &wholeModel, int numberOfRows, const int \*whichRows, int numberOfColumns, const int \*whichColumns)  
*Subset constructor (without gaps).*
- **ClpGubMatrix** (const CoinPackedMatrix &wholeModel, int numberOfRows, const int \*whichRows, int numberOfColumns, const int \*whichColumns)
- [ClpGubMatrix](#) (CoinPackedMatrix \*matrix)  
*This takes over ownership (for space reasons)*
- [ClpGubMatrix](#) ([ClpPackedMatrix](#) \*matrix, int numberSets, const int \*start, const int \*end, const double \*lower, const double \*upper, const unsigned char \*status=NULL)  
*This takes over ownership (for space reasons) and is the real constructor.*
- [ClpGubMatrix](#) & **operator=** (const [ClpGubMatrix](#) &)
- virtual [ClpMatrixBase](#) \* **clone** () const  
*Clone.*
- virtual [ClpMatrixBase](#) \* **subsetClone** (int numberOfRows, const int \*whichRows, int numberOfColumns, const int \*whichColumns) const  
*Subset clone (without gaps).*
- void **redoSet** ([ClpSimplex](#) \*model, int newKey, int oldKey, int iSet)  
*redoes next\_ for a set.*

#### gets and sets

- [ClpSimplex::Status](#) **getStatus** (int sequence) const  
*Status.*
- void **setStatus** (int sequence, [ClpSimplex::Status](#) status)
- void **setFlagged** (int sequence)  
*To flag a variable.*
- void **clearFlagged** (int sequence)
- bool **flagged** (int sequence) const
- void **setAbove** (int sequence)  
*To say key is above ub.*
- void **setFeasible** (int sequence)  
*To say key is feasible.*
- void **setBelow** (int sequence)  
*To say key is below lb.*
- double **weight** (int sequence) const
- int \* **start** () const  
*Starts.*
- int \* **end** () const  
*End.*
- double \* **lower** () const  
*Lower bounds on sets.*
- double \* **upper** () const  
*Upper bounds on sets.*
- int \* **keyVariable** () const  
*Key variable of set.*
- int \* **backward** () const  
*Backward pointer to set number.*
- int **numberSets** () const  
*Number of sets (gub rows)*
- void **switchOffCheck** ()  
*Switches off dj checking each factorization (for BIG models)*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- double [sumDualInfeasibilities\\_](#)  
*Sum of dual infeasibilities.*
- double [sumPrimalInfeasibilities\\_](#)  
*Sum of primal infeasibilities.*
- double [sumOfRelaxedDualInfeasibilities\\_](#)  
*Sum of Dual infeasibilities using tolerance based on error in duals.*
- double [sumOfRelaxedPrimalInfeasibilities\\_](#)  
*Sum of Primal infeasibilities using tolerance based on error in primals.*
- double [infeasibilityWeight\\_](#)  
*Infeasibility weight when last full pass done.*
- int \* [start\\_](#)  
*Starts.*
- int \* [end\\_](#)  
*End.*
- double \* [lower\\_](#)  
*Lower bounds on sets.*
- double \* [upper\\_](#)  
*Upper bounds on sets.*
- unsigned char \* [status\\_](#)  
*Status of slacks.*
- unsigned char \* [saveStatus\\_](#)  
*Saved status of slacks.*
- int \* [savedKeyVariable\\_](#)  
*Saved key variables.*
- int \* [backward\\_](#)  
*Backward pointer to set number.*
- int \* [backToPivotRow\\_](#)  
*Backward pointer to pivot row !!!*
- double \* [changeCost\\_](#)  
*Change in costs for keys.*
- int \* [keyVariable\\_](#)  
*Key variable of set.*
- int \* [next\\_](#)  
*Next basic variable in set - starts at key and end with -(set+1).*
- int \* [toIndex\\_](#)  
*Backward pointer to index in CoinIndexedVector.*
- int \* [fromIndex\\_](#)
- [ClpSimplex](#) \* [model\\_](#)  
*Pointer back to model.*
- int [numberDualInfeasibilities\\_](#)  
*Number of dual infeasibilities.*
- int [numberPrimalInfeasibilities\\_](#)

- `int noCheck_`  
*Number of primal infeasibilities.*
- `int numberSets_`  
*If pricing will declare victory (i.e. Number of sets (gub rows))*
- `int saveNumber_`  
*Number in vector without gub extension.*
- `int possiblePivotKey_`  
*Pivot row of possible next key.*
- `int gubSlackIn_`  
*Gub slack in (set number or -1)*
- `int firstGub_`  
*First gub variables (same as start\_[0] at present)*
- `int lastGub_`  
*last gub variable (same as end\_[numberSets\_-1] at present)*
- `int gubType_`  
*type of gub - 0 not contiguous, 1 contiguous add 8 bit to say no ubs on individual variables*

### 3.26.1 Detailed Description

This implements Gub rows plus a [ClpPackedMatrix](#).

There will be a version using [ClpPlusMinusOne](#) matrix but there is no point doing one with [ClpNetworkMatrix](#) (although an embedded network is attractive).

Definition at line 22 of file [ClpGubMatrix.hpp](#).

### 3.26.2 Constructor & Destructor Documentation

#### 3.26.2.1 `ClpGubMatrix::ClpGubMatrix ( )`

Default constructor.

#### 3.26.2.2 `ClpGubMatrix::ClpGubMatrix ( const ClpGubMatrix & )`

The copy constructor.

#### 3.26.2.3 `ClpGubMatrix::ClpGubMatrix ( const CoinPackedMatrix & )`

The copy constructor from an [CoinPackedMatrix](#).

#### 3.26.2.4 `ClpGubMatrix::ClpGubMatrix ( const ClpGubMatrix & wholeModel, int numberOfRows, const int * whichRows, int numberColumns, const int * whichColumns )`

Subset constructor (without gaps).

Duplicates are allowed and order is as given

## 3.26.3 Member Function Documentation

**3.26.3.1** `virtual void ClpGubMatrix::unpackPacked ( ClpSimplex * model, CoinIndexedVector * rowArray, int column ) const [virtual]`

Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.

Bounds and objective could be modified if doing column generation (just for this variable)

Reimplemented from [ClpPackedMatrix](#).

**3.26.3.2** `virtual void ClpGubMatrix::transposeTimes ( const ClpSimplex * model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z ) const [virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#)

Reimplemented from [ClpPackedMatrix](#).

**3.26.3.3** `virtual void ClpGubMatrix::transposeTimesByRow ( const ClpSimplex * model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z ) const [virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#). This version uses row copy

Reimplemented from [ClpPackedMatrix](#).

**3.26.3.4** `virtual void ClpGubMatrix::subsetTransposeTimes ( const ClpSimplex * model, const CoinIndexedVector * x, const CoinIndexedVector * y, CoinIndexedVector * z ) const [virtual]`

Return  $x * A$  in  $z$  but just for indices in  $y$ .

Note -  $z$  always packed mode

Reimplemented from [ClpPackedMatrix](#).

**3.26.3.5** `virtual int ClpGubMatrix::extendUpdated ( ClpSimplex * model, CoinIndexedVector * update, int mode ) [virtual]`

expands an updated column to allow for extra rows which the main solver does not know about and returns number added if mode 0.

If mode 1 deletes extra entries

This active in Gub

Reimplemented from [ClpMatrixBase](#).

**3.26.3.6** `virtual void ClpGubMatrix::primalExpanded ( ClpSimplex * model, int mode )`  
`[virtual]`

mode=0 - Set up before "update" and "times" for primal solution using extended rows

mode=1 - Cleanup primal solution after "times" using extended rows.

mode=2 - Check (or report on) primal infeasibilities

Reimplemented from [ClpMatrixBase](#).

**3.26.3.7** `virtual void ClpGubMatrix::dualExpanded ( ClpSimplex * model, CoinIndexedVector * array, double * other, int mode )` `[virtual]`

mode=0 - Set up before "updateTranspose" and "transposeTimes" for duals using extended updates array (and may use other if dual values pass) mode=1 - Update dual solution after "transposeTimes" using extended rows.

mode=2 - Compute all djs and compute key dual infeasibilities mode=3 - Report on key dual infeasibilities mode=4 - Modify before updateTranspose in partial pricing

Reimplemented from [ClpMatrixBase](#).

**3.26.3.8** `virtual double* ClpGubMatrix::rhsOffset ( ClpSimplex * model, bool forceRefresh = false, bool check = false )` `[virtual]`

Returns effective RHS offset if it is being used.

This is used for long problems or big gub or anywhere where going through full columns is expensive. This may re-compute

Reimplemented from [ClpMatrixBase](#).

Reimplemented in [ClpGubDynamicMatrix](#).

**3.26.3.9** `virtual ClpMatrixBase* ClpGubMatrix::subsetClone ( int numberOfRows, const int * whichRows, int numberColumns, const int * whichColumns ) const` `[virtual]`

Subset clone (without gaps).

Duplicates are allowed and order is as given

Reimplemented from [ClpPackedMatrix](#).

**3.26.3.10** `void ClpGubMatrix::redoSet ( ClpSimplex * model, int newKey, int oldKey, int iSet )`

redoes next\_ for a set.

#### 3.26.4 Member Data Documentation

**3.26.4.1** `int* ClpGubMatrix::next_` `[mutable, protected]`

Next basic variable in set - starts at key and end with -(set+1).

Now changes to -(nonbasic+1). next\_ has extra space for 2\* longest set

Definition at line 323 of file ClpGubMatrix.hpp.

#### 3.26.4.2 int ClpGubMatrix::noCheck\_ [protected]

If pricing will declare victory (i.e.

no check every factorization). -1 - always check 0 - don't check 1 - in don't check mode but looks optimal


Definition at line 339 of file ClpGubMatrix.hpp.

The documentation for this class was generated from the following file:

- ClpGubMatrix.hpp

## 3.27 ClpHashValue Class Reference

Collaboration diagram for ClpHashValue:



### Classes

- struct [CoinHashLink](#)  
*Data.*

### Public Member Functions

#### Useful methods

- int [index](#) (double value) const  
*Return index or -1 if not found.*
- int [addValue](#) (double value)  
*Add value to list and return index.*

- int [numberEntries](#) () const  
*Number of different entries.*

#### Constructors, destructor

- [ClpHashValue](#) ()  
*Default constructor.*
- [ClpHashValue](#) ([ClpSimplex](#) \*model)  
*Useful constructor.*
- virtual [~ClpHashValue](#) ()  
*Destructor.*

#### Copy method

- [ClpHashValue](#) (const [ClpHashValue](#) &)  
*The copy constructor.*
- [ClpHashValue](#) & [operator=](#) (const [ClpHashValue](#) &)  
=

#### Protected Attributes

##### Data members

*The data members are protected to allow access for derived classes.*

- [CoinHashLink](#) \* [hash\\_](#)  
*Hash table.*
- int [numberHash\\_](#)  
*Number of entries in hash table.*
- int [maxHash\\_](#)  
*Maximum number of entries in hash table i.e. size.*
- int [lastUsed\\_](#)  
*Last used space.*

#### 3.27.1 Detailed Description

Definition at line 288 of file [ClpNode.hpp](#).

#### 3.27.2 Constructor & Destructor Documentation

##### 3.27.2.1 [ClpHashValue::ClpHashValue](#) ( )

Default constructor.

##### 3.27.2.2 [ClpHashValue::ClpHashValue](#) ( [ClpSimplex](#) \* *model* )

Useful constructor.

### 3.27.2.3 ClpHashValue::ClpHashValue ( const ClpHashValue & )

The copy constructor.

The documentation for this class was generated from the following file:


- ClpNode.hpp

## 3.28 ClpInterior Class Reference


This solves LPs using interior point methods.

```
#include <ClpInterior.hpp>
```

Inheritance diagram for ClpInterior:



Collaboration diagram for ClpInterior:



## Public Member Functions

### Constructors and destructor and copy

- [ClpInterior](#) ()  
Default constructor.
- [ClpInterior](#) (const [ClpInterior](#) &)  
Copy constructor.
- [ClpInterior](#) (const [ClpModel](#) &)  
Copy constructor from model.
- [ClpInterior](#) (const [ClpModel](#) \*wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns, bool dropNames=true, bool dropIntegers=true)  
Subproblem constructor.
- [ClpInterior](#) & operator= (const [ClpInterior](#) &rhs)  
Assignment operator. This copies the data.
- ~[ClpInterior](#) ()  
Destructor.
- void [loadProblem](#) (const [ClpMatrixBase](#) &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)  
Loads a problem (the constraints on the rows are given by lower and upper bounds).
- void [loadProblem](#) (const [CoinPackedMatrix](#) &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)
- void [loadProblem](#) (const int numcols, const int numRows, const [CoinBigIndex](#) \*start, const int \*index, const double \*value, const double \*collb, const double

\*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)

*Just like the other [loadProblem\(\)](#) method except that the matrix is given in a standard column major ordered format (without gaps).*

- void [loadProblem](#) (const int numcols, const int numRows, const CoinBigIndex \*start, const int \*index, const double \*value, const int \*length, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)

*This one is for after presolve to save memory.*

- int [readMps](#) (const char \*filename, bool keepNames=false, bool ignoreErrors=false)

*Read an mps file from the given filename.*

- void [borrowModel](#) ([ClpModel](#) &otherModel)

*Borrow model.*

- void [returnModel](#) ([ClpModel](#) &otherModel)

*Return model - updates any scalars.*

#### Functions most useful to user

- int [pdco](#) ()  
*Pdco algorithm - see [ClpPdco.hpp](#) for method.*
- int [pdco](#) ([ClpPdcoBase](#) \*stuff, [Options](#) &options, [Info](#) &info, [Outfo](#) &outfo)
- int [primalDual](#) ()  
*Primal-Dual Predictor-Corrector barrier.*

#### most useful gets and sets

- bool [primalFeasible](#) () const  
*If problem is primal feasible.*
- bool [dualFeasible](#) () const  
*If problem is dual feasible.*
- int [algorithm](#) () const  
*Current (or last) algorithm.*
- void [setAlgorithm](#) (int value)  
*Set algorithm.*
- CoinWorkDouble [sumDualInfeasibilities](#) () const  
*Sum of dual infeasibilities.*
- CoinWorkDouble [sumPrimalInfeasibilities](#) () const  
*Sum of primal infeasibilities.*
- CoinWorkDouble [dualObjective](#) () const  
*dualObjective.*
- CoinWorkDouble [primalObjective](#) () const  
*primalObjective.*
- CoinWorkDouble [diagonalNorm](#) () const  
*diagonalNorm*
- CoinWorkDouble [linearPerturbation](#) () const  
*linearPerturbation*
- void [setLinearPerturbation](#) (CoinWorkDouble value)
- CoinWorkDouble [projectionTolerance](#) () const

- projectionTolerance*
- void **setProjectionTolerance** (CoinWorkDouble value)
- CoinWorkDouble [diagonalPerturbation](#) () const
- diagonalPerturbation*
- void **setDiagonalPerturbation** (CoinWorkDouble value)
- CoinWorkDouble [gamma](#) () const
- gamma*
- void **setGamma** (CoinWorkDouble value)
- CoinWorkDouble [delta](#) () const
- delta*
- void **setDelta** (CoinWorkDouble value)
- CoinWorkDouble [complementarityGap](#) () const
- ComplementarityGap.*
- CoinWorkDouble [largestPrimalError](#) () const
- Largest error on Ax-b.*
- CoinWorkDouble [largestDualError](#) () const
- Largest error on basic duals.*
- int [maximumBarrierIterations](#) () const
- Maximum iterations.*
- void **setMaximumBarrierIterations** (int value)
- void **setCholesky** (ClpCholeskyBase \*cholesky)
- Set cholesky (and delete present one)*
- int [numberFixed](#) () const
- Return number fixed to see if worth presolving.*
- void [fixFixed](#) (bool reallyFix=true)
- fix variables interior says should be.*
- CoinWorkDouble \* [primalR](#) () const
- Primal erturbation vector.*
- CoinWorkDouble \* [dualR](#) () const
- Dual erturbation vector.*

#### public methods

- CoinWorkDouble [rawObjectiveValue](#) () const
- Raw objective value (so always minimize)*
- int [isColumn](#) (int sequence) const
- Returns 1 if sequence indicates column.*
- int [sequenceWithin](#) (int sequence) const
- Returns sequence number within section.*
- void [checkSolution](#) ()
- Checks solution.*
- CoinWorkDouble [quadraticDjs](#) (CoinWorkDouble \*djRegion, const CoinWorkDouble \*solution, CoinWorkDouble scaleFactor)
- Modifies djs to allow for quadratic.*
- void [setFixed](#) (int sequence)
- To say a variable is fixed.*
- void **clearFixed** (int sequence)
- bool **fixed** (int sequence) const
- void [setFlagged](#) (int sequence)

*To flag a variable.*

- void **clearFlagged** (int sequence)
- bool **flagged** (int sequence) const
- void **setFixedOrFree** (int sequence)

*To say a variable is fixed OR free.*

- void **clearFixedOrFree** (int sequence)
- bool **fixedOrFree** (int sequence) const
- void **setLowerBound** (int sequence)

*To say a variable has lower bound.*

- void **clearLowerBound** (int sequence)
- bool **lowerBound** (int sequence) const
- void **setUpperBound** (int sequence)

*To say a variable has upper bound.*

- void **clearUpperBound** (int sequence)
- bool **upperBound** (int sequence) const
- void **setFakeLower** (int sequence)

*To say a variable has fake lower bound.*

- void **clearFakeLower** (int sequence)
- bool **fakeLower** (int sequence) const
- void **setFakeUpper** (int sequence)

*To say a variable has fake upper bound.*

- void **clearFakeUpper** (int sequence)
- bool **fakeUpper** (int sequence) const

#### Protected Member Functions

##### protected methods

- void **gutsOfDelete** ()  
*Does most of deletion.*
- void **gutsOfCopy** (const ClpInterior &rhs)  
*Does most of copying.*
- bool **createWorkingData** ()  
*Returns true if data looks okay, false if not.*
- void **deleteWorkingData** ()
- bool **sanityCheck** ()  
*Sanity check on input rim data.*
- int **housekeeping** ()  
*This does housekeeping.*

#### Friends

- void **ClpInteriorUnitTest** (const std::string &mpsDir, const std::string &netlibDir)  
*A function that tests the methods in the ClpInterior class.*

data. Many arrays have a row part and a column part.

There is a single array with both - columns then rows and then normally two arrays pointing to rows and columns.

The single array is the owner of memory

- CoinWorkDouble [largestPrimalError\\_](#)  
*Largest error on  $Ax=b$ .*
- CoinWorkDouble [largestDualError\\_](#)  
*Largest error on basic duals.*
- CoinWorkDouble [sumDualInfeasibilities\\_](#)  
*Sum of dual infeasibilities.*
- CoinWorkDouble [sumPrimalInfeasibilities\\_](#)  
*Sum of primal infeasibilities.*
- CoinWorkDouble [worstComplementarity\\_](#)  
*Worst complementarity.*
- CoinWorkDouble \* [lower\\_](#)  
*Working copy of lower bounds (Owner of arrays below)*
- CoinWorkDouble \* [rowLowerWork\\_](#)  
*Row lower bounds - working copy.*
- CoinWorkDouble \* [columnLowerWork\\_](#)  
*Column lower bounds - working copy.*
- CoinWorkDouble \* [upper\\_](#)  
*Working copy of upper bounds (Owner of arrays below)*
- CoinWorkDouble \* [rowUpperWork\\_](#)  
*Row upper bounds - working copy.*
- CoinWorkDouble \* [columnUpperWork\\_](#)  
*Column upper bounds - working copy.*
- CoinWorkDouble \* [cost\\_](#)  
*Working copy of objective.*
- ClpLsq \* [lsqrObject\\_](#)  
*Pointer to Lsq object.*
- ClpPdcoBase \* [pdcoStuff\\_](#)  
*Pointer to stuff.*
- CoinWorkDouble [mu\\_](#)  
*Below here is standard barrier stuff mu.*
- CoinWorkDouble [objectiveNorm\\_](#)  
*objectiveNorm.*
- CoinWorkDouble [rhsNorm\\_](#)  
*rhsNorm.*
- CoinWorkDouble [solutionNorm\\_](#)  
*solutionNorm.*
- CoinWorkDouble [dualObjective\\_](#)

- dualObjective.*
- CoinWorkDouble [primalObjective\\_](#)  
*primalObjective.*
- CoinWorkDouble [diagonalNorm\\_](#)  
*diagonalNorm.*
- CoinWorkDouble [stepLength\\_](#)  
*stepLength*
- CoinWorkDouble [linearPerturbation\\_](#)  
*linearPerturbation*
- CoinWorkDouble [diagonalPerturbation\\_](#)  
*diagonalPerturbation*
- CoinWorkDouble **gamma\_**
- CoinWorkDouble **delta\_**
- CoinWorkDouble [targetGap\\_](#)  
*targetGap*
- CoinWorkDouble [projectionTolerance\\_](#)  
*projectionTolerance*
- CoinWorkDouble [maximumRHSError\\_](#)  
*maximumRHSError. maximum Ax*
- CoinWorkDouble [maximumBoundInfeasibility\\_](#)  
*maximumBoundInfeasibility.*
- CoinWorkDouble [maximumDualError\\_](#)  
*maximumDualError.*
- CoinWorkDouble [diagonalScaleFactor\\_](#)  
*diagonalScaleFactor.*
- CoinWorkDouble [scaleFactor\\_](#)  
*scaleFactor. For scaling objective*
- CoinWorkDouble [actualPrimalStep\\_](#)  
*actualPrimalStep*
- CoinWorkDouble [actualDualStep\\_](#)  
*actualDualStep*
- CoinWorkDouble [smallestInfeasibility\\_](#)  
*smallestInfeasibility*
- CoinWorkDouble **historyInfeasibility\_** [LENGTH\_HISTORY]
- CoinWorkDouble [complementarityGap\\_](#)  
*complementarityGap.*
- CoinWorkDouble [baseObjectiveNorm\\_](#)  
*baseObjectiveNorm*
- CoinWorkDouble [worstDirectionAccuracy\\_](#)  
*worstDirectionAccuracy*
- CoinWorkDouble [maximumRHSChange\\_](#)  
*maximumRHSChange*
- CoinWorkDouble \* [errorRegion\\_](#)

- errorRegion. i.e. Ax*
- CoinWorkDouble \* [rhsFixRegion\\_](#)  
*rhsFixRegion.*
- CoinWorkDouble \* [upperSlack\\_](#)  
*upperSlack*
- CoinWorkDouble \* [lowerSlack\\_](#)  
*lowerSlack*
- CoinWorkDouble \* [diagonal\\_](#)  
*diagonal*
- CoinWorkDouble \* [solution\\_](#)  
*solution*
- CoinWorkDouble \* [workArray\\_](#)  
*work array*
- CoinWorkDouble \* [deltaX\\_](#)  
*delta X*
- CoinWorkDouble \* [deltaY\\_](#)  
*delta Y*
- CoinWorkDouble \* [deltaZ\\_](#)  
*deltaZ.*
- CoinWorkDouble \* [deltaW\\_](#)  
*deltaW.*
- CoinWorkDouble \* [deltaSU\\_](#)  
*deltaS.*
- CoinWorkDouble \* **deltaSL\_**
- CoinWorkDouble \* [primalR\\_](#)  
*Primal regularization array.*
- CoinWorkDouble \* [dualR\\_](#)  
*Dual regularization array.*
- CoinWorkDouble \* [rhsB\\_](#)  
*rhs B*
- CoinWorkDouble \* [rhsU\\_](#)  
*rhsU.*
- CoinWorkDouble \* [rhsL\\_](#)  
*rhsL.*
- CoinWorkDouble \* [rhsZ\\_](#)  
*rhsZ.*
- CoinWorkDouble \* [rhsW\\_](#)  
*rhsW.*
- CoinWorkDouble \* [rhsC\\_](#)  
*rhs C*
- CoinWorkDouble \* [zVec\\_](#)  
*zVec*
- CoinWorkDouble \* [wVec\\_](#)

- wVec*
- [ClpCholeskyBase](#) \* [cholesky\\_](#)  
*cholesky.*
- int [numberComplementarityPairs\\_](#)  
*numberComplementarityPairs i.e. ones with lower and/or upper bounds (not fixed)*
- int [numberComplementarityItems\\_](#)  
*numberComplementarityItems\_ i.e. number of active bounds*
- int [maximumBarrierIterations\\_](#)  
*Maximum iterations.*
- bool [gonePrimalFeasible\\_](#)  
*gonePrimalFeasible.*
- bool [goneDualFeasible\\_](#)  
*goneDualFeasible.*
- int [algorithm\\_](#)  
*Which algorithm being used.*
- CoinWorkDouble **xsize\_**
- CoinWorkDouble **ysize\_**
- CoinWorkDouble \* [rhs\\_](#)  
*Rhs.*
- CoinWorkDouble \* **x\_**
- CoinWorkDouble \* **y\_**
- CoinWorkDouble \* **dj\_**

### 3.28.1 Detailed Description

This solves LPs using interior point methods.

It inherits from [ClpModel](#) and all its arrays are created at algorithm time.

Definition at line 72 of file ClpInterior.hpp.

### 3.28.2 Constructor & Destructor Documentation

**3.28.2.1** `ClpInterior::ClpInterior ( const ClpModel * wholeModel, int numberRows, const int * whichRows, int numberColumns, const int * whichColumns, bool dropNames = true, bool dropIntegers = true )`

Subproblem constructor.

A subset of whole model is created from the row and column lists given. The new order is given by list order and duplicates are allowed. Name and integer information can be dropped

## 3.28.3 Member Function Documentation

**3.28.3.1** `void ClpInterior::loadProblem ( const ClpMatrixBase & matrix, const double * collb, const double * colub, const double * obj, const double * rowlb, const double * rowub, const double * rowObjective = NULL )`

Loads a problem (the constraints on the rows are given by lower and upper bounds).

If a pointer is 0 then the following values are the default:

- *colub*: all columns have upper bound infinity
- *collb*: all columns have lower bound 0
- *rowub*: all rows have upper bound infinity
- *rowlb*: all rows have lower bound -infinity
- *obj*: all variables have 0 objective coefficient

Reimplemented from [ClpModel](#).

**3.28.3.2** `void ClpInterior::loadProblem ( const int numcols, const int numrows, const CoinBigIndex * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const double * rowlb, const double * rowub, const double * rowObjective = NULL )`

Just like the other [loadProblem\(\)](#) method except that the matrix is given in a standard column major ordered format (without gaps).

Reimplemented from [ClpModel](#).

**3.28.3.3** `void ClpInterior::borrowModel ( ClpModel & otherModel )`

Borrow model.

This is so we dont have to copy large amounts of data around. It assumes a derived class wants to overwrite an empty model with a real one - while it does an algorithm. This is same as [ClpModel](#) one.

Reimplemented from [ClpModel](#).

**3.28.3.4** `void ClpInterior::fixFixed ( bool reallyFix = true )`

fix variables interior says should be.

If *reallyFix* false then just set values to exact bounds

**3.28.3.5** `CoinWorkDouble ClpInterior::quadraticDjs ( CoinWorkDouble * djRegion, const CoinWorkDouble * solution, CoinWorkDouble scaleFactor )`

Modifies djs to allow for quadratic.

returns quadratic offset

#### 3.28.4 Friends And Related Function Documentation

**3.28.4.1** `void ClpInteriorUnitTest ( const std::string & mpsDir, const std::string & netlibDir )`  
[friend]

A function that tests the methods in the [ClpInterior](#) class.

The only reason for it not to be a member method is that this way it doesn't have to be compiled into the library. And that's a gain, because the library should be compiled with optimization on, but this method should be compiled with debugging.

It also does some testing of [ClpFactorization](#) class

#### 3.28.5 Member Data Documentation

**3.28.5.1** `CoinWorkDouble ClpInterior::mu_` [protected]

Below here is standard barrier stuff mu.

Definition at line 441 of file ClpInterior.hpp.

The documentation for this class was generated from the following file:


- ClpInterior.hpp

### 3.29 ClpLinearObjective Class Reference


Linear Objective Class.

```
#include <ClpLinearObjective.hpp>
```

Inheritance diagram for ClpLinearObjective:



Collaboration diagram for ClpLinearObjective:



#### Public Member Functions

##### Stuff

- virtual double \* [gradient](#) (const [ClpSimplex](#) \*model, const double \*solution, double &offset, bool refresh, int includeLinear=2)  
*Returns objective coefficients.*
- virtual double [reducedGradient](#) ([ClpSimplex](#) \*model, double \*region, bool useFeasibleCosts)  
*Returns reduced gradient. Returns an offset (to be added to current one).*
- virtual double [stepLength](#) ([ClpSimplex](#) \*model, const double \*solution, const double \*change, double maximumTheta, double &currentObj, double &predictedObj, double &thetaObj)  
*Returns step length which gives minimum of objective for solution + theta \* change vector up to maximum theta.*
- virtual double [objectiveValue](#) (const [ClpSimplex](#) \*model, const double \*solution) const  
*Return objective value (without any [ClpModel](#) offset) (model may be NULL)*
- virtual void [resize](#) (int newNumberColumns)  
*Resize objective.*
- virtual void [deleteSome](#) (int numberToDelete, const int \*which)  
*Delete columns in objective.*
- virtual void [reallyScale](#) (const double \*columnScale)  
*Scale objective.*

##### Constructors and destructors

- [ClpLinearObjective](#) ()  
*Default Constructor.*
- [ClpLinearObjective](#) (const double \*objective, int numberColumns)  
*Constructor from objective.*

- [ClpLinearObjective](#) (const [ClpLinearObjective](#) &)  
*Copy constructor.*
- [ClpLinearObjective](#) (const [ClpLinearObjective](#) &rhs, int numberColumns, const int \*whichColumns)  
*Subset constructor.*
- [ClpLinearObjective](#) & operator= (const [ClpLinearObjective](#) &rhs)  
*Assignment operator.*
- virtual [~ClpLinearObjective](#) ()  
*Destructor.*
- virtual [ClpObjective](#) \* clone () const  
*Clone.*
- virtual [ClpObjective](#) \* subsetClone (int numberColumns, const int \*whichColumns) const  
*Subset clone.*

### 3.29.1 Detailed Description

Linear Objective Class.

Definition at line 17 of file ClpLinearObjective.hpp.

### 3.29.2 Constructor & Destructor Documentation

#### 3.29.2.1 [ClpLinearObjective::ClpLinearObjective](#) ( const [ClpLinearObjective](#) & rhs, int numberColumns, const int \* whichColumns )

Subset constructor.

Duplicates are allowed and order is as given.

### 3.29.3 Member Function Documentation

#### 3.29.3.1 virtual double\* [ClpLinearObjective::gradient](#) ( const [ClpSimplex](#) \* model, const double \* solution, double & offset, bool refresh, int includeLinear = 2 ) [virtual]

Returns objective coefficients.

Offset is always set to 0.0. All other parameters unused.

Implements [ClpObjective](#).

#### 3.29.3.2 virtual double [ClpLinearObjective::stepLength](#) ( [ClpSimplex](#) \* model, const double \* solution, const double \* change, double maximumTheta, double & currentObj, double & predictedObj, double & thetaObj ) [virtual]

Returns step length which gives minimum of objective for solution + theta \* change vector up to maximum theta.

arrays are numberColumns+numberRows Also sets current objective, predicted and at maximumTheta

```
3.29.3.3 virtual ClpObjective* ClpLinearObjective::subsetClone ( int numberColumns, const
int * whichColumns ) const [virtual]
```

Duplicates are allowed and order is as given.


The documentation for this class was generated from the following file:

- ClpLinearObjective.hpp

This class implements LSQR.

Collaboration diagram for ClpLsqr:

Collaboration diagram for ClpLsqr:



## Constructors and destructors

- `ClpLsqr ()`  
*Default constructor.*
- `ClpLsqr (ClpInterior *model)`

Constructor for use with Pdco model (note modified for pdco!!!!)

- [ClpLsqr](#) (const [ClpLsqr](#) &)

Copy constructor.

- [ClpLsqr](#) & [operator=](#) (const [ClpLsqr](#) &rhs)

Assignment operator. This copies the data.

- [~ClpLsqr](#) ()

Destructor.

#### Methods

- bool [setParam](#) (char \*parmName, int parmValue)

Set an int parameter.

- void [do\\_lsqr](#) (CoinDenseVector< double > &b, double damp, double atol, double btol, double conlim, int itnlim, bool show, [Info](#) info, CoinDenseVector< double > &x, int \*istop, int \*itn, [Outfo](#) \*outfo, bool precon, CoinDenseVector< double > &Pr)

Call the Lsqr algorithm.

- void [matVecMult](#) (int, CoinDenseVector< double > \*, CoinDenseVector< double > \*)

Matrix-vector multiply - implemented by user.

- void [matVecMult](#) (int, CoinDenseVector< double > &, CoinDenseVector< double > &)
- void [borrowDiag1](#) (double \*array)

diag1 - we just borrow as it is part of a CoinDenseVector<double>

#### Public Attributes

##### Public member data

- int [nrows\\_](#)

Row dimension of matrix.

- int [ncols\\_](#)

Column dimension of matrix.

- [ClpInterior](#) \* [model\\_](#)

Pointer to Model object for this instance.

- double \* [diag1\\_](#)

Diagonal array 1.

- double [diag2\\_](#)

Constant diagonal 2.

#### 3.30.1 Detailed Description

This class implements LSQR.

```
LSQR solves  $Ax = b$  or  $\min ||b - Ax||_2$  if damp = 0,
or  $\min ||(b) - (A)x||$  otherwise.
|| (0) (damp I) ||2
A is an m by n matrix defined by user provided routines
```

matVecMult(mode, y, x)  
 which performs the matrix-vector operations where y and x  
 are references or pointers to CoinDenseVector objects.  
 If mode = 1, matVecMult must return  $y = Ax$  without altering x.  
 If mode = 2, matVecMult must return  $y = A'x$  without altering x.

-----  
 LSQR uses an iterative (conjugate-gradient-like) method.

For further information, see

1. C. C. Paige and M. A. Saunders (1982a).  
 LSQR: An algorithm for sparse linear equations and sparse least squares,  
 ACM TOMS 8(1), 43-71.
2. C. C. Paige and M. A. Saunders (1982b).  
 Algorithm 583. LSQR: Sparse linear equations and least squares problems,  
 ACM TOMS 8(2), 195-209.
3. M. A. Saunders (1995). Solution of sparse rectangular systems using  
 LSQR and CRAIG, BIT 35, 588-604.

Input parameters:

atol, btol are stopping tolerances. If both are 1.0e-9 (say),  
 the final residual norm should be accurate to about 9 digits.  
 (The final x will usually have fewer correct digits,  
 depending on cond(A) and the size of damp.)  
 conlim is also a stopping tolerance. lsqr terminates if an estimate  
 of cond(A) exceeds conlim. For compatible systems  $Ax = b$ ,  
 conlim could be as large as 1.0e+12 (say). For least-squares  
 problems, conlim should be less than 1.0e+8.  
 Maximum precision can be obtained by setting  
 atol = btol = conlim = zero, but the number of iterations  
 may then be excessive.  
 itnlim is an explicit limit on iterations (for safety).  
 show = 1 gives an iteration log,  
 show = 0 suppresses output.  
 info is a structure special to pdco.m, used to test if  
 was small enough, and continuing if necessary with smaller atol.

Output parameters:

x is the final solution.  
 \*istop gives the reason for termination.  
 \*istop = 1 means x is an approximate solution to  $Ax = b$ .  
 = 2 means x approximately solves the least-squares problem.  
 rnorm = norm(r) if damp = 0, where  $r = b - Ax$ ,  
 =  $\sqrt{\text{norm}(r)^2 + \text{damp}^2 * \text{norm}(x)^2}$  otherwise.  
 xnorm = norm(x).  
 var estimates  $\text{diag}(\text{inv}(A'A))$ . Omitted in this special version.  
 outfo is a structure special to pdco.m, returning information  
 about whether atol had to be reduced.

Other potential output parameters:

anorm, acond, arnorm, xnorm

Definition at line 76 of file ClpLsqqr.hpp.

The documentation for this class was generated from the following file:


- ClpLsqqr.hpp

### 3.31 ClpMatrixBase Class Reference

Abstract base class for Clp Matrices.

```
#include <ClpMatrixBase.hpp>
```

Inheritance diagram for ClpMatrixBase:



#### Public Member Functions

Virtual methods that the derived classes must provide

- virtual CoinPackedMatrix \* [getPackedMatrix](#) () const =0  
*Return a complete CoinPackedMatrix.*
- virtual bool [isColOrdered](#) () const =0  
*Whether the packed matrix is column major ordered or not.*
- virtual CoinBigIndex [getNumElements](#) () const =0  
*Number of entries in the packed matrix.*
- virtual int [getNumCols](#) () const =0  
*Number of columns.*
- virtual int [getNumRows](#) () const =0  
*Number of rows.*
- virtual const double \* [getElements](#) () const =0  
*A vector containing the elements in the packed matrix.*
- virtual const int \* [getIndices](#) () const =0  
*A vector containing the minor indices of the elements in the packed matrix.*
- virtual const CoinBigIndex \* [getVectorStarts](#) () const =0
- virtual const int \* [getVectorLengths](#) () const =0  
*The lengths of the major-dimension vectors.*
- virtual int [getVectorLength](#) (int index) const

- The length of a single major-dimension vector.*

  - virtual void [deleteCols](#) (const int numDel, const int \*indDel)=0

*Delete the columns whose indices are listed in `indDel`.*

  - virtual void [deleteRows](#) (const int numDel, const int \*indDel)=0

*Delete the rows whose indices are listed in `indDel`.*

  - virtual void [appendCols](#) (int number, const CoinPackedVectorBase \*const \*columns)
- Append Columns.*

  - virtual void [appendRows](#) (int number, const CoinPackedVectorBase \*const \*rows)

*Append Rows.*

  - virtual void [modifyCoefficient](#) (int row, int column, double newElement, bool keepZero=false)

*Modify one element of packed matrix.*

  - virtual int [appendMatrix](#) (int number, int type, const CoinBigIndex \*starts, const int \*index, const double \*element, int numberOther=-1)

*Append a set of rows/columns to the end of the matrix.*

  - virtual [ClpMatrixBase](#) \* [reverseOrderedCopy](#) () const

*Returns a new matrix in reverse order without gaps Is allowed to return NULL if doesn't want to have row copy.*

  - virtual CoinBigIndex [countBasis](#) (const int \*whichColumn, int &numberColumnBasic)=0

*Returns number of elements in column part of basis.*

  - virtual void [fillBasis](#) ([ClpSimplex](#) \*model, const int \*whichColumn, int &numberColumnBasic, int \*row, int \*start, int \*rowCount, int \*columnCount, CoinFactorizationDouble \*element)=0

*Fills in column part of basis.*

  - virtual int [scale](#) ([ClpModel](#) \*, const [ClpSimplex](#) \*model) const

*Creates scales for column copy (rowCopy in model may be modified) default does not allow scaling returns non-zero if no scaling done.*

  - virtual void [scaleRowCopy](#) ([ClpModel](#) \*) const

*Scales rowCopy if column copy scaled Only called if scales already exist.*

  - virtual bool [canGetRowCopy](#) () const

*Returns true if can create row copy.*

  - virtual [ClpMatrixBase](#) \* [scaledColumnCopy](#) ([ClpModel](#) \*) const

*Really really scales column copy Only called if scales already exist.*

  - virtual bool [allElementsInRange](#) ([ClpModel](#) \*, double, double, int=15)

*Checks if all elements are in valid range.*

  - virtual void [setDimensions](#) (int numRows, int numcols)

*Set the dimensions of the matrix.*

  - virtual void [rangeOfElements](#) (double &smallestNegative, double &largestNegative, double &smallestPositive, double &largestPositive)

*Returns largest and smallest elements of both signs.*

  - virtual void [unpack](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const =0

*Unpacks a column into an CoinIndexedvector.*

  - virtual void [unpackPacked](#) ([ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const =0

*Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.*

- virtual int **refresh** (ClpSimplex \*)  
*Purely for column generation and similar ideas.*
- virtual void **reallyScale** (const double \*rowScale, const double \*columnScale)
- virtual CoinBigIndex \* **dubiousWeights** (const ClpSimplex \*model, int \*inputWeights) const  
*Given positive integer weights for each row fills in sum of weights for each column (and slack).*
- virtual void **add** (const ClpSimplex \*model, CoinIndexedVector \*rowArray, int column, double multiplier) const =0  
*Adds multiple of a column into an CoinIndexedvector You can use quickAdd to add to vector.*
- virtual void **add** (const ClpSimplex \*model, double \*array, int column, double multiplier) const =0  
*Adds multiple of a column into an array.*
- virtual void **releasePackedMatrix** () const =0  
*Allow any parts of a created CoinPackedMatrix to be deleted.*
- virtual bool **canDoPartialPricing** () const  
*Says whether it can do partial pricing.*
- virtual int **hiddenRows** () const  
*Returns number of hidden rows e.g. gub.*
- virtual void **partialPricing** (ClpSimplex \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Partial pricing.*
- virtual int **extendUpdated** (ClpSimplex \*model, CoinIndexedVector \*update, int mode)  
*expands an updated column to allow for extra rows which the main solver does not know about and returns number added.*
- virtual void **primalExpanded** (ClpSimplex \*model, int mode)  
*utility primal function for dealing with dynamic constraints mode=0 - Set up before "update" and "times" for primal solution using extended rows mode=1 - Cleanup primal solution after "times" using extended rows.*
- virtual void **dualExpanded** (ClpSimplex \*model, CoinIndexedVector \*array, double \*other, int mode)  
*utility dual function for dealing with dynamic constraints mode=0 - Set up before "updateTranspose" and "transposeTimes" for duals using extended updates array (and may use other if dual values pass) mode=1 - Update dual solution after "transposeTimes" using extended rows.*
- virtual int **generalExpanded** (ClpSimplex \*model, int mode, int &number)  
*general utility function for dealing with dynamic constraints mode=0 - Create list of non-key basics in pivotVariable\_ using number as numberBasic in and out mode=1 - Set all key variables as basic mode=2 - return number extra rows needed, number gives maximum number basic mode=3 - before replaceColumn mode=4 - return 1 if can do primal, 2 if dual, 3 if both mode=5 - save any status stuff (when in good state) mode=6 - restore status stuff mode=7 - flag given variable (normally sequenceIn) mode=8 - unflag all variables mode=9 - synchronize costs and bounds mode=10 - return 1 if there may be changing bounds on variable (column generation) mode=11 - make sure set is clean (used when a variable rejected - but not flagged) mode=12 - after factorize but before permute stuff mode=13 - at end of simplex to delete stuff*
- virtual int **updatePivot** (ClpSimplex \*model, double oldInValue, double oldOutValue)

- update information for a pivot (and effective rhs)*
- virtual void `createVariable` (`ClpSimplex` \*model, int &bestSequence)  
*Creates a variable.*
- virtual int `checkFeasible` (`ClpSimplex` \*model, double &sum) const  
*Just for debug if odd type matrix.*
- double `reducedCost` (`ClpSimplex` \*model, int sequence) const  
*Returns reduced cost of a variable.*
- virtual void `correctSequence` (const `ClpSimplex` \*model, int &sequenceIn, int &sequenceOut)  
*Correct sequence in and out to give true value (if both -1 maybe do whole matrix)*

#### Matrix times vector methods

*They can be faster if scalar is +- 1 Also for simplex I am not using basic/non-basic split*

- virtual void `times` (double scalar, const double \*x, double \*y) const =0  
*Return  $y + A * x * scalar$  in  $y$ .*
- virtual void `times` (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale) const  
*And for scaling - default aborts for when scaling not supported (unless pointers NULL when as normal)*
- virtual void `transposeTimes` (double scalar, const double \*x, double \*y) const =0  
*Return  $y + x * scalar * A$  in  $y$ .*
- virtual void `transposeTimes` (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale, double \*spare=NULL) const  
*And for scaling - default aborts for when scaling not supported (unless pointers NULL when as normal)*
- virtual void `transposeTimes` (const `ClpSimplex` \*model, double scalar, const `CoinIndexedVector` \*x, `CoinIndexedVector` \*y, `CoinIndexedVector` \*z) const =0  
*Return  $x * scalar * A + y$  in  $z$ .*
- virtual void `subsetTransposeTimes` (const `ClpSimplex` \*model, const `CoinIndexedVector` \*x, const `CoinIndexedVector` \*y, `CoinIndexedVector` \*z) const =0  
*Return  $x * A$  in  $z$  but just for indices in  $y$ .*
- virtual bool `canCombine` (const `ClpSimplex` \*, const `CoinIndexedVector` \*) const  
*Returns true if can combine transposeTimes and subsetTransposeTimes and if it would be faster.*
- virtual void `transposeTimes2` (const `ClpSimplex` \*model, const `CoinIndexedVector` \*pi1, `CoinIndexedVector` \*dj1, const `CoinIndexedVector` \*pi2, `CoinIndexedVector` \*spare, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)  
*Updates two arrays for steepest and does devex weights (need not be coded)*
- virtual void `subsetTimes2` (const `ClpSimplex` \*model, `CoinIndexedVector` \*dj1, const `CoinIndexedVector` \*pi2, `CoinIndexedVector` \*dj2, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)  
*Updates second array for steepest and does devex weights (need not be coded)*
- virtual void `listTransposeTimes` (const `ClpSimplex` \*model, double \*x, int \*y, int number, double \*z) const  
*Return  $x * A$  in  $z$  but just for number indices in  $y$ .*

## Other

## Clone

- virtual [ClpMatrixBase](#) \* **clone** () const =0
- virtual [ClpMatrixBase](#) \* **subsetClone** (int numberOfRows, const int \*whichRows, int numberOfColumns, const int \*whichColumns) const  
*Subset clone (without gaps).*
- virtual void **backToBasics** ()  
*Gets rid of any mutable by products.*
- int **type** () const  
*Returns type.*
- void **setType** (int newtype)  
*Sets type.*
- void **useEffectiveRhs** ([ClpSimplex](#) \*model)  
*Sets up an effective RHS.*
- virtual double \* **rhsOffset** ([ClpSimplex](#) \*model, bool forceRefresh=false, bool check=false)  
*Returns effective RHS offset if it is being used.*
- int **lastRefresh** () const  
*If rhsOffset used this is iteration last refreshed.*
- int **refreshFrequency** () const  
*If rhsOffset used this is refresh frequency (0==off)*
- void **setRefreshFrequency** (int value)
- bool **skipDualCheck** () const  
*whether to skip dual checks most of time*
- void **setSkipDualCheck** (bool yes)
- int **minimumObjectsScan** () const  
*Partial pricing tuning parameter - minimum number of "objects" to scan.*
- void **setMinimumObjectsScan** (int value)
- int **minimumGoodReducedCosts** () const  
*Partial pricing tuning parameter - minimum number of negative reduced costs to get.*
- void **setMinimumGoodReducedCosts** (int value)
- double **startFraction** () const  
*Current start of search space in matrix (as fraction)*
- void **setStartFraction** (double value)
- double **endFraction** () const  
*Current end of search space in matrix (as fraction)*
- void **setEndFraction** (double value)
- double **savedBestDj** () const  
*Current best reduced cost.*
- void **setSavedBestDj** (double value)
- int **originalWanted** () const  
*Initial number of negative reduced costs wanted.*
- void **setOriginalWanted** (int value)
- int **currentWanted** () const  
*Current number of negative reduced costs which we still need.*
- void **setCurrentWanted** (int value)
- int **savedBestSequence** () const  
*Current best sequence.*
- void **setSavedBestSequence** (int value)

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- double \* [rhsOffset\\_](#)  
*Effective RHS offset if it is being used.*
- double [startFraction\\_](#)  
*Current start of search space in matrix (as fraction)*
- double [endFraction\\_](#)  
*Current end of search space in matrix (as fraction)*
- double [savedBestDj\\_](#)  
*Best reduced cost so far.*
- int [originalWanted\\_](#)  
*Initial number of negative reduced costs wanted.*
- int [currentWanted\\_](#)  
*Current number of negative reduced costs which we still need.*
- int [savedBestSequence\\_](#)  
*Saved best sequence in pricing.*
- int [type\\_](#)  
*type (may be useful)*
- int [lastRefresh\\_](#)  
*If rhsOffset used this is iteration last refreshed.*
- int [refreshFrequency\\_](#)  
*If rhsOffset used this is refresh frequency (0==off)*
- int [minimumObjectsScan\\_](#)  
*Partial pricing tuning parameter - minimum number of "objects" to scan.*
- int [minimumGoodReducedCosts\\_](#)  
*Partial pricing tuning parameter - minimum number of negative reduced costs to get.*
- int [trueSequenceIn\\_](#)  
*True sequence in (i.e. from larger problem)*
- int [trueSequenceOut\\_](#)  
*True sequence out (i.e. from larger problem)*
- bool [skipDualCheck\\_](#)  
*whether to skip dual checks most of time*

## Constructors, destructor&lt;br&gt;

**NOTE:** All constructors are protected.

There's no need to expose them, after all, this is an abstract class.

- virtual [~ClpMatrixBase](#) ()  
*Destructor (has to be public)*
- [ClpMatrixBase](#) ()  
*Default constructor.*
- **ClpMatrixBase** (const [ClpMatrixBase](#) &)
- [ClpMatrixBase](#) & **operator=** (const [ClpMatrixBase](#) &)

## 3.31.1 Detailed Description

Abstract base class for Clp Matrices.

Since this class is abstract, no object of this type can be created.

If a derived class provides all methods then all Clp algorithms should work. Some can be very inefficient e.g. `getElements` etc is only used for tightening bounds for dual and the copies are deleted. Many methods can just be dummy i.e. `abort()`; if not all features are being used. So if column generation was being done then it makes no sense to do steepest edge so there would be no point providing `subsetTransposeTimes`.

Definition at line 30 of file `ClpMatrixBase.hpp`.

## 3.31.2 Constructor &amp; Destructor Documentation

3.31.2.1 `ClpMatrixBase::ClpMatrixBase ( )` `[protected]`

Default constructor.

## 3.31.3 Member Function Documentation

3.31.3.1 `virtual bool ClpMatrixBase::isColOrdered ( ) const` `[pure virtual]`

Whether the packed matrix is column major ordered or not.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.2 `virtual CoinBigIndex ClpMatrixBase::getNumElements ( ) const` `[pure virtual]`

Number of entries in the packed matrix.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.3 `virtual int ClpMatrixBase::getNumCols ( ) const` `[pure virtual]`

Number of columns.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.4 `virtual int ClpMatrixBase::getNumRows ( ) const` `[pure virtual]`

Number of rows.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.5** `virtual const double* ClpMatrixBase::getElements ( ) const` [pure virtual]

A vector containing the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.6** `virtual const int* ClpMatrixBase::getIndices ( ) const` [pure virtual]

A vector containing the minor indices of the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.7** `virtual const int* ClpMatrixBase::getVectorLengths ( ) const` [pure virtual]

The lengths of the major-dimension vectors.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.8** `virtual int ClpMatrixBase::getVectorLength ( int index ) const` [virtual]

The length of a single major-dimension vector.

Reimplemented in [ClpPackedMatrix](#).

**3.31.3.9** `virtual void ClpMatrixBase::deleteCols ( const int numDel, const int * indDel )`  
[pure virtual]

Delete the columns whose indices are listed in `indDel`.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.10** `virtual void ClpMatrixBase::deleteRows ( const int numDel, const int * indDel )`  
[pure virtual]

Delete the rows whose indices are listed in `indDel`.

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.11** `virtual void ClpMatrixBase::modifyCoefficient ( int row, int column, double newElement, bool keepZero = false )` [virtual]

Modify one element of packed matrix.

An element may be added. This works for either ordering. If the new element is zero it will be deleted unless keepZero true

Reimplemented in [ClpPackedMatrix](#).

```
3.31.3.12  virtual int ClpMatrixBase::appendMatrix ( int number, int type, const CoinBigIndex *
           starts, const int * index, const double * element, int numberOther = -1 )
           [virtual]
```

Append a set of rows/columns to the end of the matrix.

Returns number of errors i.e. if any of the new rows/columns contain an index that's larger than the number of columns-1/rows-1 (if numberOther>0) or duplicates. If 0 then rows, 1 if columns

Reimplemented in [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

```
3.31.3.13  virtual ClpMatrixBase* ClpMatrixBase::scaledColumnCopy ( ClpModel * ) const
           [inline, virtual]
```

Really really scales column copy. Only called if scales already exist.

Up to user to delete

Reimplemented in [ClpPackedMatrix](#).

Definition at line 118 of file [ClpMatrixBase.hpp](#).

```
3.31.3.14  virtual bool ClpMatrixBase::allElementsInRange ( ClpModel *, double, double,
           int = 15 ) [inline, virtual]
```

Checks if all elements are in valid range.

Can just return true if you are not paranoid. For Clp I will probably expect no zeros. Code can modify matrix to get rid of small elements. check bits (can be turned off to save time) : 1 - check if matrix has gaps 2 - check if zero elements 4 - check and compress duplicates 8 - report on large and small

Reimplemented in [ClpPackedMatrix](#).

Definition at line 132 of file [ClpMatrixBase.hpp](#).

```
3.31.3.15  virtual void ClpMatrixBase::setDimensions ( int numrows, int numcols )
           [virtual]
```

Set the dimensions of the matrix.

In effect, append new empty columns/rows to the matrix. A negative number for either dimension means that that dimension doesn't change. Otherwise the new dimensions MUST be at least as large as the current ones otherwise an exception is thrown.

Reimplemented in [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.16 `virtual void ClpMatrixBase::rangeOfElements ( double & smallestNegative,  
double & largestNegative, double & smallestPositive, double & largestPositive )  
[virtual]`

Returns largest and smallest elements of both signs.

Largest refers to largest absolute value. If returns zeros then can't tell anything

Reimplemented in [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.17 `virtual void ClpMatrixBase::unpackPacked ( ClpSimplex * model,  
CoinIndexedVector * rowArray, int column ) const [pure virtual]`

Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.

Bounds and objective could be modified if doing column generation (just for this variable)

Implemented in [ClpDummyMatrix](#), [ClpGubMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.18 `virtual int ClpMatrixBase::refresh ( ClpSimplex * ) [inline, virtual]`

Purely for column generation and similar ideas.

Allows matrix and any bounds or costs to be updated (sensibly). Returns non-zero if any changes.

Reimplemented in [ClpDynamicMatrix](#), and [ClpPackedMatrix](#).

Definition at line 164 of file ClpMatrixBase.hpp.

3.31.3.19 `virtual CoinBigIndex* ClpMatrixBase::dubiousWeights ( const ClpSimplex * model,  
int * inputWeights ) const [virtual]`

Given positive integer weights for each row fills in sum of weights for each column (and slack).

Returns weights vector Default returns vector of ones

Reimplemented in [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

3.31.3.20 `virtual int ClpMatrixBase::extendUpdated ( ClpSimplex * model, CoinIndexedVector  
* update, int mode ) [virtual]`

expands an updated column to allow for extra rows which the main solver does not know about and returns number added.

This will normally be a no-op - it is in for GUB but may get extended to general non-overlapping and embedded networks.

mode 0 - extend mode 1 - delete etc

Reimplemented in [ClpGubMatrix](#).

**3.31.3.21** `virtual void ClpMatrixBase::primalExpanded ( ClpSimplex * model, int mode )`  
`[virtual]`

utility primal function for dealing with dynamic constraints mode=0 - Set up before "update" and "times" for primal solution using extended rows mode=1 - Cleanup primal solution after "times" using extended rows.

mode=2 - Check (or report on) primal infeasibilities

Reimplemented in [ClpGubMatrix](#).

**3.31.3.22** `virtual void ClpMatrixBase::dualExpanded ( ClpSimplex * model,`  
`CoinIndexedVector * array, double * other, int mode ) [virtual]`

utility dual function for dealing with dynamic constraints mode=0 - Set up before "updateTranspose" and "transposeTimes" for duals using extended updates array (and may use other if dual values pass) mode=1 - Update dual solution after "transposeTimes" using extended rows.

mode=2 - Compute all djs and compute key dual infeasibilities mode=3 - Report on key dual infeasibilities mode=4 - Modify before updateTranspose in partial pricing

Reimplemented in [ClpDynamicMatrix](#), and [ClpGubMatrix](#).

**3.31.3.23** `virtual int ClpMatrixBase::generalExpanded ( ClpSimplex * model, int mode, int &`  
`number ) [virtual]`

general utility function for dealing with dynamic constraints mode=0 - Create list of non-key basics in pivotVariable\_ using number as numberBasic in and out mode=1 - Set all key variables as basic mode=2 - return number extra rows needed, number gives maximum number basic mode=3 - before replaceColumn mode=4 - return 1 if can do primal, 2 if dual, 3 if both mode=5 - save any status stuff (when in good state) mode=6 - restore status stuff mode=7 - flag given variable (normally sequenceIn) mode=8 - unflag all variables mode=9 - synchronize costs and bounds mode=10 - return 1 if there may be changing bounds on variable (column generation) mode=11 - make sure set is clean (used when a variable rejected - but not flagged) mode=12 - after factorize but before permute stuff mode=13 - at end of simplex to delete stuff

Reimplemented in [ClpDynamicMatrix](#), and [ClpGubMatrix](#).

**3.31.3.24** `virtual void ClpMatrixBase::createVariable ( ClpSimplex * model, int &`  
`bestSequence ) [virtual]`

Creates a variable.

This is called after partial pricing and may modify matrix. May update bestSequence.

Reimplemented in [ClpDynamicExampleMatrix](#), and [ClpDynamicMatrix](#).

**3.31.3.25** `virtual int ClpMatrixBase::checkFeasible ( ClpSimplex * model, double & sum )`  
`const [virtual]`

Just for debug if odd type matrix.

Returns number of primal infeasibilities.

Reimplemented in [ClpGubDynamicMatrix](#).

**3.31.3.26** `virtual void ClpMatrixBase::times ( double scalar, const double * x, double * y ) const` `[pure virtual]`

Return  $y + A * x * scalar$  in  $y$ .

#### Precondition

$x$  must be of size `numColumns()`  
 $y$  must be of size `numRows()`

Implemented in [ClpDummyMatrix](#), [ClpDynamicMatrix](#), [ClpGubDynamicMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.27** `virtual void ClpMatrixBase::transposeTimes ( double scalar, const double * x, double * y ) const` `[pure virtual]`

Return  $y + x * scalar * A$  in  $y$ .

#### Precondition

$x$  must be of size `numRows()`  
 $y$  must be of size `numColumns()`

Implemented in [ClpDummyMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.28** `virtual void ClpMatrixBase::transposeTimes ( const ClpSimplex * model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z ) const` `[pure virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#)

Implemented in [ClpDummyMatrix](#), [ClpGubMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.29** `virtual void ClpMatrixBase::subsetTransposeTimes ( const ClpSimplex * model, const CoinIndexedVector * x, const CoinIndexedVector * y, CoinIndexedVector * z ) const` `[pure virtual]`

Return  $x * A$  in  $z$  but just for indices in  $y$ .

This is only needed for primal steepest edge. Note -  $z$  always packed mode

Implemented in [ClpDummyMatrix](#), [ClpGubMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.30** `virtual void ClpMatrixBase::listTransposeTimes ( const ClpSimplex * model, double * x, int * y, int number, double * z ) const` `[virtual]`

Return  $x * A$  in  $z$  but just for number indices in  $y$ .

Default cheats with fake CoinIndexedVector and then calls subsetTransposeTimes

**3.31.3.31** `virtual ClpMatrixBase* ClpMatrixBase::subsetClone ( int numberRows, const int * whichRows, int numberColumns, const int * whichColumns ) const` [virtual]

Subset clone (without gaps).

Duplicates are allowed and order is as given. Derived classes need not provide this as it may not always make sense

Reimplemented in [ClpGubMatrix](#), [ClpNetworkMatrix](#), [ClpPackedMatrix](#), and [ClpPlusMinusOneMatrix](#).

**3.31.3.32** `int ClpMatrixBase::type ( ) const` [inline]

Returns type.

The types which code may need to know about are: 1 - [ClpPackedMatrix](#) 11 - [ClpNetworkMatrix](#) 12 - [ClpPlusMinusOneMatrix](#)

Definition at line 362 of file [ClpMatrixBase.hpp](#).

**3.31.3.33** `virtual double* ClpMatrixBase::rhsOffset ( ClpSimplex * model, bool forceRefresh = false, bool check = false )` [virtual]

Returns effective RHS offset if it is being used.

This is used for long problems or big gub or anywhere where going through full columns is expensive. This may re-compute

Reimplemented in [ClpDynamicMatrix](#), [ClpGubDynamicMatrix](#), and [ClpGubMatrix](#).

**3.31.3.34** `int ClpMatrixBase::minimumObjectsScan ( ) const` [inline]

Partial pricing tuning parameter - minimum number of "objects" to scan.

e.g. number of Gub sets but could be number of variables

Definition at line 396 of file [ClpMatrixBase.hpp](#).

### 3.31.4 Member Data Documentation

**3.31.4.1** `double* ClpMatrixBase::rhsOffset_` [protected]

Effective RHS offset if it is being used.

This is used for long problems or big gub or anywhere where going through full columns is expensive

Definition at line 480 of file [ClpMatrixBase.hpp](#).

The documentation for this class was generated from the following file:

- [ClpMatrixBase.hpp](#)

### 3.32 ClpMessage Class Reference

This deals with Clp messages (as against Osi messages etc)

```
#include <ClpMessage.hpp>
```

#### Public Member Functions

##### Constructors etc

- [ClpMessage](#) (Language language=us\_en)  
*Constructor.*

#### 3.32.1 Detailed Description

This deals with Clp messages (as against Osi messages etc)


Definition at line 118 of file ClpMessage.hpp.

The documentation for this class was generated from the following file:


- ClpMessage.hpp

### 3.33 ClpModel Class Reference

Inheritance diagram for ClpModel:



Collaboration diagram for ClpModel:



### Public Member Functions

- `const double * rowScale () const`  
*Scaling.*
- `double objectiveScale () const`  
*Scaling of objective.*
- `double rhsScale () const`  
*Scaling of rhs and bounds.*
- `void scaling (int mode=1)`  
*Sets or unsets scaling, 0 -off, 1 equilibrium, 2 geometric, 3 auto, 4 auto-but-as-initialSolve-in-bab.*
- `void unscale ()`  
*If we constructed a "really" scaled model then this reverses the operation.*
- `int scalingFlag () const`  
*Gets scalingFlag.*
- `double * objective () const`  
*Objective.*
- `double * rowObjective () const`  
*Row Objective.*
- `double * columnLower () const`  
*Column Lower.*
- `double * columnUpper () const`  
*Column Upper.*
- `CoinPackedMatrix * matrix () const`  
*Matrix (if not ClpPackedmatrix be careful about memory leak.*

- int [getNumElements](#) () const  
*Number of elements in matrix.*
- double [getSmallElementValue](#) () const  
*Small element value - elements less than this set to zero, default is 1.0e-20.*
- [ClpMatrixBase](#) \* [rowCopy](#) () const  
*Row Matrix.*
- void [setNewRowCopy](#) ([ClpMatrixBase](#) \*newCopy)  
*Set new row matrix.*
- [ClpMatrixBase](#) \* [clpMatrix](#) () const  
*Clp Matrix.*
- [ClpPackedMatrix](#) \* [clpScaledMatrix](#) () const  
*Scaled ClpPackedMatrix.*
- void [setClpScaledMatrix](#) ([ClpPackedMatrix](#) \*scaledMatrix)  
*Sets pointer to scaled ClpPackedMatrix.*
- void [replaceMatrix](#) ([ClpMatrixBase](#) \*matrix, bool deleteCurrent=false)  
*Replace Clp Matrix (current is not deleted unless told to and new is used) So up to user to delete current.*
- void [replaceMatrix](#) ([CoinPackedMatrix](#) \*newmatrix, bool deleteCurrent=false)  
*Replace Clp Matrix (current is not deleted unless told to and new is used) So up to user to delete current.*
- double [objectiveValue](#) () const  
*Objective value.*
- char \* [integerInformation](#) () const  
*Integer information.*
- double \* [infeasibilityRay](#) () const  
*Infeasibility/unbounded ray (NULL returned if none/wrong) Up to user to use delete [] on these arrays.*
- bool [rayExists](#) () const  
*just test if infeasibility or unbounded Ray exists*
- void [deleteRay](#) ()  
*just delete ray if exists*
- bool [statusExists](#) () const  
*See if status (i.e. basis) array exists (partly for OsiClp)*
- unsigned char \* [statusArray](#) () const  
*Return address of status (i.e. basis) array (char[numberRows+numberColumns])*
- unsigned char \* [statusCopy](#) () const  
*Return copy of status (i.e.*
- void [copyinStatus](#) (const unsigned char \*statusArray)  
*Copy in status (basis) vector.*
- void [setUserPointer](#) (void \*pointer)  
*User pointer for whatever reason.*
- void [setTrustedUserPointer](#) ([ClpTrustedData](#) \*pointer)  
*Trusted user pointer.*
- int [whatsChanged](#) () const

*What has changed in model (only for masochistic users)*

- int [numberThreads](#) () const  
*Number of threads (not really being used)*

#### Constructors and destructor

*Note - copy methods copy ALL data so can chew up memory until other copy is freed*

- [ClpModel](#) (bool emptyMessages=false)  
*Default constructor.*
- [ClpModel](#) (const [ClpModel](#) &rhs, int scalingMode=-1)  
*Copy constructor.*
- [ClpModel](#) & [operator=](#) (const [ClpModel](#) &rhs)  
*Assignment operator. This copies the data.*
- [ClpModel](#) (const [ClpModel](#) \*wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns, bool dropNames=true, bool dropIntegers=true)  
*Subproblem constructor.*
- [~ClpModel](#) ()  
*Destructor.*

#### Load model - loads some stuff and initializes others

- void [loadProblem](#) (const [ClpMatrixBase](#) &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)  
*Loads a problem (the constraints on the rows are given by lower and upper bounds).*
- void [loadProblem](#) (const [CoinPackedMatrix](#) &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)
- void [loadProblem](#) (const int numcols, const int numRows, const [CoinBigIndex](#) \*start, const int \*index, const double \*value, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)  
*Just like the other [loadProblem\(\)](#) method except that the matrix is given in a standard column major ordered format (without gaps).*
- int [loadProblem](#) ([CoinModel](#) &modelObject, bool tryPlusMinusOne=false)  
*This loads a model from a coinModel object - returns number of errors.*
- void [loadProblem](#) (const int numcols, const int numRows, const [CoinBigIndex](#) \*start, const int \*index, const double \*value, const int \*length, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)  
*This one is for after presolve to save memory.*
- void [loadQuadraticObjective](#) (const int numberColumns, const [CoinBigIndex](#) \*start, const int \*column, const double \*element)  
*Load up quadratic objective.*
- void [loadQuadraticObjective](#) (const [CoinPackedMatrix](#) &matrix)
- void [deleteQuadraticObjective](#) ()  
*Get rid of quadratic objective.*

- void [setRowObjective](#) (const double \*rowObjective)  
*This just loads up a row objective.*
- int [readMps](#) (const char \*filename, bool keepNames=false, bool ignoreErrors=false)  
*Read an mps file from the given filename.*
- int [readGMPL](#) (const char \*filename, const char \*dataName, bool keepNames=false)  
*Read GMPL files from the given filenames.*
- void [copyIntegerInformation](#) (const char \*information)  
*Copy in integer informations.*
- void [deleteIntegerInformation](#) ()  
*Drop integer informations.*
- void [setContinuous](#) (int index)  
*Set the index-th variable to be a continuous variable.*
- void [setInteger](#) (int index)  
*Set the index-th variable to be an integer variable.*
- bool [isInteger](#) (int index) const  
*Return true if the index-th variable is an integer variable.*
- void [resize](#) (int newNumberRows, int newNumberColumns)  
*Resizes rim part of model.*
- void [deleteRows](#) (int number, const int \*which)  
*Deletes rows.*
- void [addRow](#) (int numberInRow, const int \*columns, const double \*elements, double rowLower=-COIN\_DBL\_MAX, double rowUpper=COIN\_DBL\_MAX)  
*Add one row.*
- void [addRows](#) (int number, const double \*rowLower, const double \*rowUpper, const CoinBigIndex \*rowStarts, const int \*columns, const double \*elements)  
*Add rows.*
- void [addRows](#) (int number, const double \*rowLower, const double \*rowUpper, const CoinBigIndex \*rowStarts, const int \*rowLengths, const int \*columns, const double \*elements)  
*Add rows.*
- void [addRows](#) (int number, const double \*rowLower, const double \*rowUpper, const CoinPackedVectorBase \*const \*rows)  
*Add rows from a build object.*
- int [addRows](#) (const CoinBuild &buildObject, bool tryPlusMinusOne=false, bool checkDuplicates=true)  
*Add rows from a model object.*
- void [deleteColumns](#) (int number, const int \*which)  
*Deletes columns.*
- void [addColumn](#) (int numberInColumn, const int \*rows, const double \*elements, double columnLower=0.0, double columnUpper=COIN\_DBL\_MAX, double objective=0.0)  
*Add one column.*
- void [addColumnns](#) (int number, const double \*columnLower, const double \*columnUpper, const double \*objective, const CoinBigIndex \*columnStarts, const int \*rows, const double \*elements)

*Add columns.*

- void **addColumns** (int number, const double \*columnLower, const double \*columnUpper, const double \*objective, const CoinBigIndex \*columnStarts, const int \*columnLengths, const int \*rows, const double \*elements)
- void **addColumns** (int number, const double \*columnLower, const double \*columnUpper, const double \*objective, const CoinPackedVectorBase \*const \*columns)
- int **addColumns** (const CoinBuild &buildObject, bool tryPlusMinusOne=false, bool checkDuplicates=true)

*Add columns from a build object If tryPlusMinusOne then will try adding as +-1 matrix if no matrix exists.*

- int **addColumns** (CoinModel &modelObject, bool tryPlusMinusOne=false, bool checkDuplicates=true)

*Add columns from a model object.*

- void **modifyCoefficient** (int row, int column, double newElement, bool keepZero=false)

*Modify one element of a matrix.*

- void **chgRowLower** (const double \*rowLower)

*Change row lower bounds.*

- void **chgRowUpper** (const double \*rowUpper)

*Change row upper bounds.*

- void **chgColumnLower** (const double \*columnLower)

*Change column lower bounds.*

- void **chgColumnUpper** (const double \*columnUpper)

*Change column upper bounds.*

- void **chgObjCoefficients** (const double \*objIn)

*Change objective coefficients.*

- void **borrowModel** (ClpModel &otherModel)

*Borrow model.*

- void **returnModel** (ClpModel &otherModel)

*Return model - nulls all arrays so can be deleted safely also updates any scalars.*

- void **createEmptyMatrix** ()

*Create empty ClpPackedMatrix.*

- int **cleanMatrix** (double threshold=1.0e-20)

*Really clean up matrix (if ClpPackedMatrix).*

- void **copy** (const ClpMatrixBase \*from, ClpMatrixBase \*&to)

*Copy contents - resizing if necessary - otherwise re-use memory.*

- void **dropNames** ()

*Drops names - makes lengthnames 0 and names empty.*

- void **copyNames** (std::vector< std::string > &rowNames, std::vector< std::string > &columnNames)

*Copies in names.*

- void **copyRowNames** (const std::vector< std::string > &rowNames, int first, int last)

*Copies in Row names - modifies names first .. last-1.*

- void **copyColumnNames** (const std::vector< std::string > &columnNames, int first, int last)

*Copies in Column names - modifies names first .. last-1.*

- void **copyRowNames** (const char \*const \*rowNames, int first, int last)

- Copies in Row names - modifies names first .. last-1.*
- void **copyColumnNames** (const char \*const \*columnNames, int first, int last)
  - Copies in Column names - modifies names first .. last-1.*
- void **setRowName** (int rowIndex, std::string &name)
  - Set name of row.*
- void **setColumnName** (int colIndex, std::string &name)
  - Set name of col.*
- int **findNetwork** (char \*rotate, double fractionNeeded=0.75)
  - Find a network subset.*
- CoinModel \* **createCoinModel** () const
  - This creates a coinModel object.*
- int **writeMps** (const char \*filename, int formatType=0, int numberAcross=2, double objSense=0.0) const
  - Write the problem in MPS format to the specified file.*

#### gets and sets

- int **numberRows** () const
  - Number of rows.*
- int **getNumRows** () const
- int **getNumCols** () const
  - Number of columns.*
- int **numberColumns** () const
- double **primalTolerance** () const
  - Primal tolerance to use.*
- void **setPrimalTolerance** (double value)
- double **dualTolerance** () const
  - Dual tolerance to use.*
- void **setDualTolerance** (double value)
- double **primalObjectiveLimit** () const
  - Primal objective limit.*
- void **setPrimalObjectiveLimit** (double value)
- double **dualObjectiveLimit** () const
  - Dual objective limit.*
- void **setDualObjectiveLimit** (double value)
- double **objectiveOffset** () const
  - Objective offset.*
- void **setObjectiveOffset** (double value)
- double **presolveTolerance** () const
  - Presolve tolerance to use.*
- std::string **problemName** () const
- int **numberIterations** () const
  - Number of iterations.*
- int **getIterationCount** () const
- void **setNumberIterations** (int numberIterationsNew)
- int **solveType** () const
  - Solve type - 1 simplex, 2 simplex interface, 3 Interior.*
- void **setSolveType** (int type)
- int **maximumIterations** () const

- Maximum number of iterations.*
- void **setMaximumIterations** (int value)
- double **maximumSeconds** () const
- Maximum time in seconds (from when set called)*
- void **setMaximumSeconds** (double value)
- bool **hitMaximumIterations** () const
- Returns true if hit maximum iterations (or time)*
- int **status** () const
- Status of problem:*
- int **problemStatus** () const
- void **setProblemStatus** (int problemStatusNew)
- Set problem status.*
- int **secondaryStatus** () const
- Secondary status of problem - may get extended 0 - none 1 - primal infeasible because dual limit reached OR (probably primal infeasible but can't prove it - main status was 4) 2 - scaled problem optimal - unscaled problem has primal infeasibilities 3 - scaled problem optimal - unscaled problem has dual infeasibilities 4 - scaled problem optimal - unscaled problem has primal and dual infeasibilities 5 - giving up in primal with flagged variables 6 - failed due to empty problem check 7 - postSolve says not optimal 8 - failed due to bad element check 9 - status was 3 and stopped on time 100 up - translation of enum from [ClpEventHandler](#).*
- void **setSecondaryStatus** (int newstatus)
- bool **isAbandoned** () const
- Are there a numerical difficulties?*
- bool **isProvenOptimal** () const
- Is optimality proven?*
- bool **isProvenPrimalInfeasible** () const
- Is primal infeasibility proven?*
- bool **isProvenDualInfeasible** () const
- Is dual infeasibility proven?*
- bool **isPrimalObjectiveLimitReached** () const
- Is the given primal objective limit reached?*
- bool **isDualObjectiveLimitReached** () const
- Is the given dual objective limit reached?*
- bool **isIterationLimitReached** () const
- Iteration limit reached?*
- double **optimizationDirection** () const
- Direction of optimization (1 - minimize, -1 - maximize, 0 - ignore.*
- double **getObjSense** () const
- void **setOptimizationDirection** (double value)
- double \* **primalRowSolution** () const
- Primal row solution.*
- const double \* **getRowActivity** () const
- double \* **primalColumnSolution** () const
- Primal column solution.*
- const double \* **getColSolution** () const
- void **setColSolution** (const double \*input)
- double \* **dualRowSolution** () const
- Dual row solution.*

- const double \* **getRowPrice** () const
- double \* **dualColumnSolution** () const  
*Reduced costs.*
- const double \* **getReducedCost** () const
- double \* **rowLower** () const  
*Row lower.*
- const double \* **getRowLower** () const
- double \* **rowUpper** () const  
*Row upper.*
- const double \* **getRowUpper** () const

#### Changing bounds on variables and constraints

- void **setObjectiveCoefficient** (int elementIndex, double elementValue)  
*Set an objective function coefficient.*
- void **setObjCoeff** (int elementIndex, double elementValue)  
*Set an objective function coefficient.*
- void **setColumnLower** (int elementIndex, double elementValue)  
*Set a single column lower bound*  
*Use -DBL\_MAX for -infinity.*
- void **setColumnUpper** (int elementIndex, double elementValue)  
*Set a single column upper bound*  
*Use DBL\_MAX for infinity.*
- void **setColumnBounds** (int elementIndex, double lower, double upper)  
*Set a single column lower and upper bound.*
- void **setColumnSetBounds** (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of columns simultaneously*  
*The default implementation just invokes **setColLower()** and **setColUpper()** over and over again.*
- void **setColLower** (int elementIndex, double elementValue)  
*Set a single column lower bound*  
*Use -DBL\_MAX for -infinity.*
- void **setColUpper** (int elementIndex, double elementValue)  
*Set a single column upper bound*  
*Use DBL\_MAX for infinity.*
- void **setColBounds** (int elementIndex, double lower, double upper)  
*Set a single column lower and upper bound.*
- void **setColSetBounds** (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of columns simultaneously*
- void **setRowLower** (int elementIndex, double elementValue)  
*Set a single row lower bound*  
*Use -DBL\_MAX for -infinity.*
- void **setRowUpper** (int elementIndex, double elementValue)  
*Set a single row upper bound*  
*Use DBL\_MAX for infinity.*
- void **setRowBounds** (int elementIndex, double lower, double upper)  
*Set a single row lower and upper bound.*
- void **setRowSetBounds** (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of rows simultaneously*

## Message handling

- void [passInMessageHandler](#) (CoinMessageHandler \*handler)  
*Pass in Message handler (not deleted at end)*
- CoinMessageHandler \* [pushMessageHandler](#) (CoinMessageHandler \*handler, bool &oldDefault)  
*Pass in Message handler (not deleted at end) and return current.*
- void [popMessageHandler](#) (CoinMessageHandler \*oldHandler, bool oldDefault)  
*back to previous message handler*
- void [newLanguage](#) (CoinMessages::Language language)  
*Set language.*
- void [setLanguage](#) (CoinMessages::Language language)
- CoinMessageHandler \* [messageHandler](#) () const  
*Return handler.*
- CoinMessages [messages](#) () const  
*Return messages.*
- CoinMessages \* [messagesPointer](#) ()  
*Return pointer to messages.*
- CoinMessages [coinMessages](#) () const  
*Return Coin messages.*
- CoinMessages \* [coinMessagesPointer](#) ()  
*Return pointer to Coin messages.*
- void [setLogLevel](#) (int value)  
*Amount of print out: 0 - none 1 - just final 2 - just factorizations 3 - as 2 plus a bit more 4 - verbose above that 8, 16, 32 etc just for selective debug.*
- int [logLevel](#) () const
- bool [defaultHandler](#) () const  
*Return true if default handler.*
- void [passInEventHandler](#) (const [ClpEventHandler](#) \*eventHandler)  
*Pass in Event handler (cloned and deleted at end)*
- [ClpEventHandler](#) \* [eventHandler](#) () const  
*Event handler.*
- CoinThreadRandom \* [randomNumberGenerator](#) ()  
*Thread specific random number generator.*
- CoinThreadRandom & [mutableRandomNumberGenerator](#) ()  
*Thread specific random number generator.*
- void [setRandomSeed](#) (int value)  
*Set seed for thread specific random number generator.*
- int [lengthNames](#) () const  
*length of names (0 means no names)*
- void [setLengthNames](#) (int value)  
*length of names (0 means no names)*
- const std::vector< std::string > \* [rowNames](#) () const  
*Row names.*
- const std::string & [rowName](#) (int iRow) const
- std::string [getRowName](#) (int iRow) const  
*Return name or Rnnnnnnn.*

- `const std::vector< std::string > * columnNames () const`  
*Column names.*
- `const std::string & columnName (int iColumn) const`
- `std::string getColumnName (int iColumn) const`  
*Return name or Cnnnnnnn.*
- `ClpObjective * objectiveAsObject () const`  
*Objective methods.*
- `void setObjective (ClpObjective *objective)`
- `void setObjectivePointer (ClpObjective *newobjective)`
- `int emptyProblem (int *infeasNumber=NULL, double *infeasSum=NULL, bool printMessage=true)`  
*Solve a problem with no elements - return status and dual and primal infeasibilities.*

#### Matrix times vector methods

*They can be faster if scalar is +- 1 These are covers so user need not worry about scaling Also for simplex I am not using basic/non-basic split*

- `void times (double scalar, const double *x, double *y) const`  
*Return  $y + A * x * scalar$  in  $y$ .*
- `void transposeTimes (double scalar, const double *x, double *y) const`  
*Return  $y + x * scalar * A$  in  $y$ .*

#### Parameter set/get methods

*The set methods return true if the parameter was set to the given value, false otherwise.*

*There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.*

*The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.*

*once it has been decided where solver sits this may be redone*

- `bool setIntParam (ClpIntParam key, int value)`  
*Set an integer parameter.*
- `bool setDbIParam (ClpDbIParam key, double value)`  
*Set an double parameter.*
- `bool setStrParam (ClpStrParam key, const std::string &value)`  
*Set an string parameter.*
- `bool getIntParam (ClpIntParam key, int &value) const`
- `bool getDbIParam (ClpDbIParam key, double &value) const`
- `bool getStrParam (ClpStrParam key, std::string &value) const`
- `void generateCpp (FILE *fp)`  
*Create C++ lines to get to current state.*
- `unsigned int specialOptions () const`

For advanced options 1 - Don't keep changing infeasibility weight 2 - Keep non-LinearCost round solves 4 - Force outgoing variables to exact bound (primal) 8 - Safe to use dense initial factorization 16 -Just use basic variables for operation if column generation 32 -Create ray even in BAB 64 -Treat problem as feasible until last minute (i.e.

- void **setSpecialOptions** (unsigned int value)
- bool **inCbcBranchAndBound** () const

#### Protected Member Functions

##### private or protected methods

- void **gutsOfDelete** (int type)  
*Does most of deletion (0 = all, 1 = most)*
- void **gutsOfCopy** (const **ClpModel** &rhs, int trueCopy=1)  
*Does most of copying If trueCopy 0 then just points to arrays If -1 leaves as much as possible.*
- void **getRowBound** (int iRow, double &lower, double &upper) const  
*gets lower and upper bounds on rows*
- void **gutsOfLoadModel** (int numberOfRows, int numberColumns, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)  
*puts in format I like - 4 array matrix - may make row copy*
- void **gutsOfScaling** ()  
*Does much of scaling.*
- double **rawObjectiveValue** () const  
*Objective value - always minimize.*
- bool **permanentArrays** () const  
*If we are using maximumRows\_ and Columns\_.*
- void **startPermanentArrays** ()  
*Start using maximumRows\_ and Columns\_.*
- void **stopPermanentArrays** ()  
*Stop using maximumRows\_ and Columns\_.*
- const char \*const **rowNamesAsChar** () const  
*Create row names as char \*\*.*
- const char \*const **columnNamesAsChar** () const  
*Create column names as char \*\*.*
- void **deleteNamesAsChar** (const char \*const \*names, int number) const  
*Delete char \* version of names.*
- void **onStopped** ()  
*On stopped - sets secondary status.*

#### Protected Attributes

##### data

- double **optimizationDirection\_**  
*Direction of optimization (1 - minimize, -1 - maximize, 0 - ignore.*

- double [dblParam\\_](#) [ClpLastDbiParam]  
*Array of double parameters.*
- double [objectiveValue\\_](#)  
*Objective value.*
- double [smallElement\\_](#)  
*Small element value.*
- double [objectiveScale\\_](#)  
*Scaling of objective.*
- double [rhsScale\\_](#)  
*Scaling of rhs and bounds.*
- int [numberRows\\_](#)  
*Number of rows.*
- int [numberColumns\\_](#)  
*Number of columns.*
- double \* [rowActivity\\_](#)  
*Row activities.*
- double \* [columnActivity\\_](#)  
*Column activities.*
- double \* [dual\\_](#)  
*Duals.*
- double \* [reducedCost\\_](#)  
*Reduced costs.*
- double \* [rowLower\\_](#)  
*Row lower.*
- double \* [rowUpper\\_](#)  
*Row upper.*
- [ClpObjective](#) \* [objective\\_](#)  
*Objective.*
- double \* [rowObjective\\_](#)  
*Row Objective (? sign) - may be NULL.*
- double \* [columnLower\\_](#)  
*Column Lower.*
- double \* [columnUpper\\_](#)  
*Column Upper.*
- [ClpMatrixBase](#) \* [matrix\\_](#)  
*Packed matrix.*
- [ClpMatrixBase](#) \* [rowCopy\\_](#)  
*Row copy if wanted.*
- [ClpPackedMatrix](#) \* [scaledMatrix\\_](#)  
*Scaled packed matrix.*
- double \* [ray\\_](#)  
*Infeasible/unbounded ray.*
- double \* [rowScale\\_](#)  
*Row scale factors for matrix.*
- double \* [columnScale\\_](#)  
*Column scale factors.*
- double \* [inverseRowScale\\_](#)

- Inverse row scale factors for matrix (end of rowScale\_)*
- double \* [inverseColumnScale\\_](#)
  - Inverse column scale factors for matrix (end of columnScale\_)*
- int [scalingFlag\\_](#)
  - Scale flag, 0 none, 1 equilibrium, 2 geometric, 3, auto, 4 dynamic, 5 geometric on rows.*
- unsigned char \* [status\\_](#)
  - Status (i.e.*
- char \* [integerType\\_](#)
  - Integer information.*
- void \* [userPointer\\_](#)
  - User pointer for whatever reason.*
- [ClpTrustedData](#) \* [trustedUserPointer\\_](#)
  - Trusted user pointer e.g. for heuristics.*
- int [intParam\\_](#) [[ClpLastIntParam](#)]
  - Array of integer parameters.*
- int [numberIterations\\_](#)
  - Number of iterations.*
- int [solveType\\_](#)
  - Solve type - 1 simplex, 2 simplex interface, 3 Interior.*
- unsigned int [whatsChanged\\_](#)
  - Whats changed since last solve.*
- int [problemStatus\\_](#)
  - Status of problem.*
- int [secondaryStatus\\_](#)
  - Secondary status of problem.*
- int [lengthNames\\_](#)
  - length of names (0 means no names)*
- int [numberThreads\\_](#)
  - Number of threads (not very operational)*
- unsigned int [specialOptions\\_](#)
  - For advanced options See get and set for meaning.*
- [CoinMessageHandler](#) \* [handler\\_](#)
  - Message handler.*
- bool [defaultHandler\\_](#)
  - Flag to say if default handler (so delete)*
- [CoinThreadRandom](#) [randomNumberGenerator\\_](#)
  - Thread specific random number generator.*
- [ClpEventHandler](#) \* [eventHandler\\_](#)
  - Event handler.*
- std::vector< std::string > [rowNames\\_](#)
  - Row names.*
- std::vector< std::string > [columnNames\\_](#)
  - Column names.*
- [CoinMessages](#) [messages\\_](#)
  - Messages.*
- [CoinMessages](#) [coinMessages\\_](#)

- Coin messages.*
- int [maximumColumns\\_](#)  
*Maximum number of columns in model.*
- int [maximumRows\\_](#)  
*Maximum number of rows in model.*
- int [maximumInternalColumns\\_](#)  
*Maximum number of columns (internal arrays) in model.*
- int [maximumInternalRows\\_](#)  
*Maximum number of rows (internal arrays) in model.*
- CoinPackedMatrix [baseMatrix\\_](#)  
*Base packed matrix.*
- CoinPackedMatrix [baseRowCopy\\_](#)  
*Base row copy.*
- double \* [savedRowScale\\_](#)  
*Saved row scale factors for matrix.*
- double \* [savedColumnScale\\_](#)  
*Saved column scale factors.*
- std::string [strParam\\_](#) [ClpLastStrParam]  
*Array of string parameters.*

### 3.33.1 Detailed Description

Definition at line 38 of file ClpModel.hpp.

### 3.33.2 Constructor & Destructor Documentation

#### 3.33.2.1 ClpModel::ClpModel ( const ClpModel & rhs, int scalingMode = -1 )

Copy constructor.

May scale depending on mode -1 leave mode as is 0 -off, 1 equilibrium, 2 geometric, 3, auto, 4 auto-but-as-initialSolve-in-bab

#### 3.33.2.2 ClpModel::ClpModel ( const ClpModel \* wholeModel, int numberOfRows, const int \* whichRows, int numberColumns, const int \* whichColumns, bool dropNames = true, bool dropIntegers = true )

Subproblem constructor.

A subset of whole model is created from the row and column lists given. The new order is given by list order and duplicates are allowed. Name and integer information can be dropped

### 3.33.3 Member Function Documentation

#### 3.33.3.1 void ClpModel::loadProblem ( const ClpMatrixBase & matrix, const double \* collb, const double \* colub, const double \* obj, const double \* rowlb, const double \* rowub, const double \* rowObjective = NULL )

Loads a problem (the constraints on the rows are given by lower and upper bounds).

If a pointer is 0 then the following values are the default:

- `colub`: all columns have upper bound infinity
- `collb`: all columns have lower bound 0
- `rowub`: all rows have upper bound infinity
- `rowlb`: all rows have lower bound -infinity
- `obj`: all variables have 0 objective coefficient

Reimplemented in [ClpInterior](#), and [ClpSimplex](#).

```
3.33.3.2 void ClpModel::loadProblem ( const int numcols, const int numrows, const
CoinBigIndex * start, const int * index, const double * value, const double * collb,
const double * colub, const double * obj, const double * rowlb, const double *
rowub, const double * rowObjective = NULL )
```

Just like the other [loadProblem\(\)](#) method except that the matrix is given in a standard column major ordered format (without gaps).

Reimplemented in [ClpInterior](#), and [ClpSimplex](#).

```
3.33.3.3 int ClpModel::loadProblem ( CoinModel & modelObject, bool tryPlusMinusOne =
false )
```

This loads a model from a coinModel object - returns number of errors.

`modelObject` not const as may be changed as part of process If `tryPlusMinusOne` then will try adding as +-1 matrix

Reimplemented in [ClpSimplex](#).

```
3.33.3.4 void ClpModel::loadQuadraticObjective ( const int numberColumns, const
CoinBigIndex * start, const int * column, const double * element )
```

Load up quadratic objective.

This is stored as a `CoinPackedMatrix`

```
3.33.3.5 int ClpModel::addRows ( const CoinBuild & buildObject, bool tryPlusMinusOne =
false, bool checkDuplicates = true )
```

Add rows from a build object.

If `tryPlusMinusOne` then will try adding as +-1 matrix if no matrix exists. Returns number of errors e.g. duplicates

```
3.33.3.6 int ClpModel::addRows ( CoinModel & modelObject, bool tryPlusMinusOne = false,
bool checkDuplicates = true )
```

Add rows from a model object.

returns -1 if object in bad state (i.e. has column information) otherwise number of errors.

modelObject non const as can be regularized as part of build If tryPlusMinusOne then will try adding as +-1 matrix if no matrix exists.

**3.33.3.7** `int ClpModel::addColumns ( const CoinBuild & buildObject, bool tryPlusMinusOne = false, bool checkDuplicates = true )`

Add columns from a build object If tryPlusMinusOne then will try adding as +-1 matrix if no matrix exists.

Returns number of errors e.g. duplicates

**3.33.3.8** `int ClpModel::addColumns ( CoinModel & modelObject, bool tryPlusMinusOne = false, bool checkDuplicates = true )`

Add columns from a model object.

returns -1 if object in bad state (i.e. has row information) otherwise number of errors modelObject non const as can be regularized as part of build If tryPlusMinusOne then will try adding as +-1 matrix if no matrix exists.

**3.33.3.9** `void ClpModel::borrowModel ( ClpModel & otherModel )`

Borrow model.

This is so we don't have to copy large amounts of data around. It assumes a derived class wants to overwrite an empty model with a real one - while it does an algorithm

Reimplemented in [ClpInterior](#), and [ClpSimplex](#).

**3.33.3.10** `int ClpModel::cleanMatrix ( double threshold = 1.0e-20 )`

Really clean up matrix (if [ClpPackedMatrix](#)).

a) eliminate all duplicate AND small elements in matrix b) remove all gaps and set extraGap\_ and extraMajor\_ to 0.0 c) reallocate arrays and make max lengths equal to lengths d) orders elements returns number of elements eliminated or -1 if not [ClpPackedMatrix](#)

**3.33.3.11** `int ClpModel::findNetwork ( char * rotate, double fractionNeeded = 0.75 )`

Find a network subset.

rotate array should be numberOfRows. On output -1 not in network 0 in network as is 1 in network with signs swapped Returns number of network rows

**3.33.3.12** `int ClpModel::writeMps ( const char * filename, int formatType = 0, int numberAcross = 2, double objSense = 0.0 ) const`

Write the problem in MPS format to the specified file.

Row and column names may be null. formatType is

- 0 - normal
- 1 - extra accuracy

- 2 - IEEE hex

Returns non-zero on I/O error

**3.33.3.13** `int ClpModel::solveType ( ) const` `[inline]`

Solve type - 1 simplex, 2 simplex interface, 3 Interior.

Definition at line 370 of file ClpModel.hpp.

**3.33.3.14** `int ClpModel::status ( ) const` `[inline]`

Status of problem:

-1 - unknown e.g. before solve or if postSolve says not optimal  
0 - optimal  
1 - primal infeasible  
2 - dual infeasible  
3 - stopped on iterations or time  
4 - stopped due to errors  
5 - stopped by event handler (virtual int [ClpEventHandler::event\(\)](#))

Definition at line 397 of file ClpModel.hpp.

**3.33.3.15** `void ClpModel::setColumnLower ( int elementIndex, double elementValue )`

Set a single column lower bound

Use -DBL\_MAX for -infinity.

Reimplemented in [ClpSimplex](#).

**3.33.3.16** `void ClpModel::setColumnUpper ( int elementIndex, double elementValue )`

Set a single column upper bound

Use DBL\_MAX for infinity.

Reimplemented in [ClpSimplex](#).

**3.33.3.17** `void ClpModel::setColumnSetBounds ( const int * indexFirst, const int * indexLast, const double * boundList )`

Set the bounds on a number of columns simultaneously

The default implementation just invokes [setColLower\(\)](#) and [setColUpper\(\)](#) over and over again.

#### Parameters

|                        |  |
|------------------------|--|
| <i>index-</i>          | pointers to the beginning and after the end of the array of the indices of the |
| <i>First, indexLas</i> | variables whose <i>either</i> bound changes                                    |
| <i>boundList</i>       | the new lower/upper bound pairs for the variables                              |

Reimplemented in [ClpSimplex](#).

**3.33.3.18** `void ClpModel::setColLower ( int elementIndex, double elementValue )`  
`[inline]`

Set a single column lower bound

Use `-DBL_MAX` for `-infinity`.

Reimplemented in [ClpSimplex](#).

Definition at line 540 of file `ClpModel.hpp`.

**3.33.3.19** `void ClpModel::setColUpper ( int elementIndex, double elementValue )`  
`[inline]`

Set a single column upper bound

Use `DBL_MAX` for `infinity`.

Reimplemented in [ClpSimplex](#).

Definition at line 545 of file `ClpModel.hpp`.

**3.33.3.20** `void ClpModel::setColSetBounds ( const int * indexFirst, const int * indexLast, const double * boundList )` `[inline]`

Set the bounds on a number of columns simultaneously

#### Parameters

|                  |   |
|------------------|---|
| <i>index-</i>    | pointers to the beginning and after the end of the array of the indices of the <i>First, indexLas</i> variables whose <i>either</i> bound changes |
| <i>boundList</i> | the new lower/upper bound pairs for the variables   |

Reimplemented in [ClpSimplex](#).

Definition at line 561 of file `ClpModel.hpp`.

**3.33.3.21** `void ClpModel::setRowLower ( int elementIndex, double elementValue )`

Set a single row lower bound

Use `-DBL_MAX` for `-infinity`.

Reimplemented in [ClpSimplex](#).

**3.33.3.22** `void ClpModel::setRowUpper ( int elementIndex, double elementValue )`

Set a single row upper bound

Use `DBL_MAX` for `infinity`.

Reimplemented in [ClpSimplex](#).

**3.33.3.23** `void ClpModel::setRowSetBounds ( const int * indexFirst, const int * indexLast, const double * boundList )`

Set the bounds on a number of rows simultaneously

#### Parameters

|                  |   |
|------------------|---|
| <i>index-</i>    | pointers to the beginning and after the end of the array of the indices of the <i>First, indexLas</i> constraints whose <i>either</i> bound changes |
| <i>boundList</i> | the new lower/upper bound pairs for the constraints   |

Reimplemented in [ClpSimplex](#).

**3.33.3.24** void ClpModel::unscale ( )

If we constructed a "really" scaled model then this reverses the operation.

Quantities may not be exactly as they were before due to rounding errors

**3.33.3.25** void ClpModel::replaceMatrix ( ClpMatrixBase \* *matrix*, bool *deleteCurrent* = false )

Replace Clp Matrix (current is not deleted unless told to and new is used) So up to user to delete current.

This was used where matrices were being rotated. [ClpModel](#) takes ownership.

**3.33.3.26** void ClpModel::replaceMatrix ( CoinPackedMatrix \* *newmatrix*, bool *deleteCurrent* = false ) [inline]

Replace Clp Matrix (current is not deleted unless told to and new is used) So up to user to delete current.

This was used where matrices were being rotated. This version changes CoinPacked-Matrix to [ClpPackedMatrix](#). [ClpModel](#) takes ownership.

Definition at line 733 of file ClpModel.hpp.

**3.33.3.27** double\* ClpModel::infeasibilityRay ( ) const

Infeasibility/unbounded ray (NULL returned if none/wrong) Up to user to use delete [] on these arrays.

**3.33.3.28** unsigned char\* ClpModel::statusCopy ( ) const

Return copy of status (i.e.

basis) array (char[numberRows+numberColumns]), use delete []

**3.33.3.29** void ClpModel::times ( double *scalar*, const double \* *x*, double \* *y* ) const

Return  $y + A * x * scalar$  in *y*.

#### Precondition

*x* must be of size numColumns ( )

*y* must be of size numRows ( )

**3.33.3.30** void ClpModel::transposeTimes ( double *scalar*, const double \* *x*, double \* *y* ) const

Return  $y + x * scalar * A$  in *y*.

#### Precondition

*x* must be of size numRows ( )

*y* must be of size numColumns ( )

### 3.33.3.31 unsigned int ClpModel::specialOptions ( ) const [inline]

For advanced options 1 - Don't keep changing infeasibility weight 2 - Keep nonLinearCost round solves 4 - Force outgoing variables to exact bound (primal) 8 - Safe to use dense initial factorization 16 - Just use basic variables for operation if column generation 32 - Create ray even in BAB 64 - Treat problem as feasible until last minute (i.e.

minimize infeasibilities) 128 - Switch off all matrix sanity checks 256 - No row copy 512 - If not in values pass, solution guaranteed, skip as much as possible 1024 - In branch and bound 2048 - Don't bother to re-factorize if < 20 iterations 4096 - Skip some optimality checks 8192 - Do Primal when cleaning up primal 16384 - In fast dual (so we can switch off things) 32768 - called from Osi 65536 - keep arrays around as much as possible (also use maximumR/C) 131072 - transposeTimes is -1.0 and can skip basic and fixed 262144 - extra copy of scaled matrix 524288 - Clp fast dual 1048576 - don't need to finish dual (can return 3) NOTE - many applications can call Clp but there may be some short cuts which are taken which are not guaranteed safe from all applications. Vetted applications will have a bit set and the code may test this At present I expect a few such applications - if too many I will have to re-think. It is up to application owner to change the code if she/he needs these short cuts. I will not debug unless in Coin repository. See COIN\_CLP\_VETTED comments. 0x01000000 is Cbc (and in branch and bound) 0x02000000 is in a different branch and bound

Definition at line 1026 of file ClpModel.hpp.

### 3.33.4 Member Data Documentation

#### 3.33.4.1 unsigned char\* ClpModel::status\_ [protected]

Status (i.e.

basis) Region. I know that not all algorithms need a status array, but it made sense for things like crossover and put all permanent stuff in one place. No assumption is made about what is in status array (although it might be good to reserve bottom 3 bits (i.e. 0-7 numeric) for classic status). This is number of columns + number of rows long (in that order).

Definition at line 1145 of file ClpModel.hpp.

#### 3.33.4.2 int ClpModel::solveType\_ [protected]

Solve type - 1 simplex, 2 simplex interface, 3 Interior.

Definition at line 1157 of file ClpModel.hpp.

#### 3.33.4.3 unsigned int ClpModel::whatsChanged\_ [protected]

Whats changed since last solve.

This is a work in progress It is designed so careful people can make go faster. It is only used when startFinishOptions used in dual or primal. Bit 1 - number of rows/columns has not changed (so work arrays valid) 2 - matrix has not changed 4 - if matrix has changed only by adding rows 8 - if matrix has changed only by adding columns 16 - row lbs not changed 32 - row ubs not changed 64 - column objective not changed 128

- column lbs not changed 256 - column ubs not changed 512 - basis not changed (up to user to set this to 0) top bits may be used internally shift by 65536 is 3 all same, 1 all except col bounds

Definition at line 1174 of file ClpModel.hpp.

The documentation for this class was generated from the following file:


- ClpModel.hpp

### 3.34 ClpNetworkBasis Class Reference

This deals with Factorization and Updates for network structures.

```
#include <ClpNetworkBasis.hpp>
```

Collaboration diagram for ClpNetworkBasis:



#### Public Member Functions

## Constructors and destructor and copy

- [ClpNetworkBasis](#) ()  
*Default constructor.*
- [ClpNetworkBasis](#) (const [ClpSimplex](#) \*model, int numberOfRows, const CoinFactorizationDouble \*pivotRegion, const int \*permuteBack, const CoinBigIndex \*startColumn, const int \*numberInColumn, const int \*indexRow, const CoinFactorizationDouble \*element)  
*Constructor from CoinFactorization.*
- [ClpNetworkBasis](#) (const [ClpNetworkBasis](#) &other)  
*Copy constructor.*
- [~ClpNetworkBasis](#) ()  
*Destructor.*
- [ClpNetworkBasis](#) & [operator=](#) (const [ClpNetworkBasis](#) &other)  
*= copy*

## Do factorization

- int [factorize](#) (const [ClpMatrixBase](#) \*matrix, int rowsBasic[], int columnsBasic[])  
*When part of LP - given by basic variables.*

## rank one updates which do exist

- int [replaceColumn](#) (CoinIndexedVector \*column, int pivotRow)  
*Replaces one Column to basis, returns 0=OK, 1=Probably OK, 2=singular!!*

## various uses of factorization (return code number elements)

## which user may want to know about

- double [updateColumn](#) (CoinIndexedVector \*regionSparse, CoinIndexedVector \*regionSparse2, int pivotRow)  
*Updates one column (FTRAN) from region, Returns pivot value if "pivotRow" >=0.*
- int [updateColumn](#) (CoinIndexedVector \*regionSparse, double array[]) const  
*Updates one column (FTRAN) to/from array For large problems you should ALWAYS know where the nonzeros are, so please try and migrate to previous method after you have got code working using this simple method - thank you! (the only exception is if you know input is dense e.g.*
- int [updateColumnTranspose](#) (CoinIndexedVector \*regionSparse, double array[]) const  
*Updates one column transpose (BTRAN) For large problems you should ALWAYS know where the nonzeros are, so please try and migrate to previous method after you have got code working using this simple method - thank you! (the only exception is if you know input is dense e.g.*
- int [updateColumnTranspose](#) (CoinIndexedVector \*regionSparse, CoinIndexedVector \*regionSparse2) const  
*Updates one column (BTRAN) from region2.*

## 3.34.1 Detailed Description

This deals with Factorization and Updates for network structures.

Definition at line 26 of file ClpNetworkBasis.hpp.

## 3.34.2 Member Function Documentation

**3.34.2.1** `int ClpNetworkBasis::factorize ( const ClpMatrixBase * matrix, int rowsBasic[], int columnsBasic[] )`

When part of LP - given by basic variables.

Actually does factorization. Arrays passed in have non negative value to say basic. If status is okay, basic variables have pivot row - this is only needed if `increasingRows_ > 1`. If status is singular, then basic variables have pivot row and ones thrown out have -1 returns 0 -okay, -1 singular, -2 too many in basis

**3.34.2.2** `int ClpNetworkBasis::updateColumn ( CoinIndexedVector * regionSparse, double array[] ) const`

Updates one column (FTRAN) to/from array For large problems you should ALWAYS know where the nonzeros are, so please try and migrate to previous method after you have got code working using this simple method - thank you! (the only exception is if you know input is dense e.g.

rhs)

**3.34.2.3** `int ClpNetworkBasis::updateColumnTranspose ( CoinIndexedVector * regionSparse, double array[] ) const`

Updates one column transpose (BTRAN) For large problems you should ALWAYS know where the nonzeros are, so please try and migrate to previous method after you have got code working using this simple method - thank you! (the only exception is if you know input is dense e.g.

dense objective) returns number of nonzeros

The documentation for this class was generated from the following file:


- ClpNetworkBasis.hpp

## 3.35 ClpNetworkMatrix Class Reference


This implements a simple network matrix as derived from [ClpMatrixBase](#).

```
#include <ClpNetworkMatrix.hpp>
```

Inheritance diagram for ClpNetworkMatrix:



Collaboration diagram for ClpNetworkMatrix:



## Public Member Functions

### Useful methods

- virtual CoinPackedMatrix \* [getPackedMatrix](#) () const  
*Return a complete CoinPackedMatrix.*
- virtual bool [isColOrdered](#) () const  
*Whether the packed matrix is column major ordered or not.*
- virtual CoinBigIndex [getNumElements](#) () const  
*Number of entries in the packed matrix.*
- virtual int [getNumCols](#) () const  
*Number of columns.*
- virtual int [getNumRows](#) () const

*Number of rows.*

- virtual const double \* [getElements](#) () const

*A vector containing the elements in the packed matrix.*

- virtual const int \* [getIndices](#) () const

*A vector containing the minor indices of the elements in the packed matrix.*

- virtual const CoinBigIndex \* [getVectorStarts](#) () const
- virtual const int \* [getVectorLengths](#) () const

*The lengths of the major-dimension vectors.*

- virtual void [deleteCols](#) (const int numDel, const int \*indDel)

*Delete the columns whose indices are listed in indDel.*

- virtual void [deleteRows](#) (const int numDel, const int \*indDel)

*Delete the rows whose indices are listed in indDel.*

- virtual void [appendCols](#) (int number, const CoinPackedVectorBase \*const \*columns)

*Append Columns.*

- virtual void [appendRows](#) (int number, const CoinPackedVectorBase \*const \*rows)

*Append Rows.*

- virtual int [appendMatrix](#) (int number, int type, const CoinBigIndex \*starts, const int \*index, const double \*element, int numberOther=-1)

*Append a set of rows/columns to the end of the matrix.*

- virtual [ClpMatrixBase](#) \* [reverseOrderedCopy](#) () const

*Returns a new matrix in reverse order without gaps.*

- virtual CoinBigIndex [countBasis](#) (const int \*whichColumn, int &numberColumn-Basic)

*Returns number of elements in column part of basis.*

- virtual void [fillBasis](#) ([ClpSimplex](#) \*model, const int \*whichColumn, int &numberColumnBasic, int \*row, int \*start, int \*rowCount, int \*columnCount, [CoinFactorizationDouble](#) \*element)

*Fills in column part of basis.*

- virtual CoinBigIndex \* [dubiousWeights](#) (const [ClpSimplex](#) \*model, int \*inputWeights) const

*Given positive integer weights for each row fills in sum of weights for each column (and slack).*

- virtual void [rangeOfElements](#) (double &smallestNegative, double &largestNegative, double &smallestPositive, double &largestPositive)

*Returns largest and smallest elements of both signs.*

- virtual void [unpack](#) (const [ClpSimplex](#) \*model, [CoinIndexedVector](#) \*rowArray, int column) const

*Unpacks a column into an [CoinIndexedvector](#).*

- virtual void [unpackPacked](#) ([ClpSimplex](#) \*model, [CoinIndexedVector](#) \*rowArray, int column) const

*Unpacks a column into an [CoinIndexedvector](#) in packed format Note that model is NOT const.*

- virtual void [add](#) (const [ClpSimplex](#) \*model, [CoinIndexedVector](#) \*rowArray, int column, double multiplier) const

*Adds multiple of a column into an [CoinIndexedvector](#) You can use [quickAdd](#) to add to vector.*

- virtual void [add](#) (const [ClpSimplex](#) \*model, double \*array, int column, double multiplier) const

- virtual void [releasePackedMatrix](#) () const  
*Adds multiple of a column into an array.*
- virtual bool [canDoPartialPricing](#) () const  
*Allow any parts of a created CoinMatrix to be deleted.*
- virtual void [partialPricing](#) (ClpSimplex \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Says whether it can do partial pricing.*  
*Partial pricing.*

#### Matrix times vector methods

- virtual void [times](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + A * scalar * x$  in  $y$ .*
- virtual void [times](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale) const  
*And for scaling.*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + x * scalar * A$  in  $y$ .*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale, double \*spare=NULL) const  
*And for scaling.*
- virtual void [transposeTimes](#) (const ClpSimplex \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const  
*Return  $x * scalar * A + y$  in  $z$ .*
- virtual void [subsetTransposeTimes](#) (const ClpSimplex \*model, const CoinIndexedVector \*x, const CoinIndexedVector \*y, CoinIndexedVector \*z) const  
*Return  $x * A$  in  $z$  but just for indices in  $y$ .*

#### Other

- bool [trueNetwork](#) () const  
*Return true if really network, false if has slacks.*

#### Constructors, destructor

- [ClpNetworkMatrix](#) ()  
*Default constructor.*
- [ClpNetworkMatrix](#) (int numberColumns, const int \*head, const int \*tail)  
*Constructor from two arrays.*
- virtual [~ClpNetworkMatrix](#) ()  
*Destructor.*

#### Copy method

- [ClpNetworkMatrix](#) (const [ClpNetworkMatrix](#) &)  
*The copy constructor.*
- [ClpNetworkMatrix](#) (const CoinPackedMatrix &)  
*The copy constructor from an CoinNetworkMatrix.*
- [ClpNetworkMatrix](#) & **operator=** (const [ClpNetworkMatrix](#) &)
- virtual [ClpMatrixBase](#) \* [clone](#) () const

*Clone.*

- [ClpNetworkMatrix](#) (const [ClpNetworkMatrix](#) &wholeModel, int numberOfRows, const int \*whichRows, int numberOfColumns, const int \*whichColumns)

*Subset constructor (without gaps).*

- virtual [ClpMatrixBase](#) \* [subsetClone](#) (int numberOfRows, const int \*whichRows, int numberOfColumns, const int \*whichColumns) const

*Subset clone (without gaps).*

### Protected Attributes

#### Data members

*The data members are protected to allow access for derived classes.*

- CoinPackedMatrix \* [matrix\\_](#)

*For fake CoinPackedMatrix.*

- int \* [lengths\\_](#)

- int \* [indices\\_](#)

*Data -1, then +1 rows in pairs (row==1 if one entry)*

- int [numberOfRows\\_](#)

*Number of rows.*

- int [numberOfColumns\\_](#)

*Number of columns.*

- bool [trueNetwork\\_](#)

*True if all entries have two elements.*

### 3.35.1 Detailed Description

This implements a simple network matrix as derived from [ClpMatrixBase](#).

If you want more sophisticated version then you could inherit from this. Also you might want to allow networks with gain

Definition at line 19 of file [ClpNetworkMatrix.hpp](#).

### 3.35.2 Constructor & Destructor Documentation

#### 3.35.2.1 [ClpNetworkMatrix::ClpNetworkMatrix \( \)](#)

Default constructor.

#### 3.35.2.2 [ClpNetworkMatrix::ClpNetworkMatrix \( const \[ClpNetworkMatrix\]\(#\) & \)](#)

The copy constructor.

#### 3.35.2.3 [ClpNetworkMatrix::ClpNetworkMatrix \( const \[CoinPackedMatrix\]\(#\) & \)](#)

The copy constructor from an [CoinNetworkMatrix](#).

3.35.2.4 `ClpNetworkMatrix::ClpNetworkMatrix ( const ClpNetworkMatrix & wholeModel, int numberRows, const int * whichRows, int numberColumns, const int * whichColumns )`

Subset constructor (without gaps).

Duplicates are allowed and order is as given

### 3.35.3 Member Function Documentation

3.35.3.1 `virtual bool ClpNetworkMatrix::isColOrdered ( ) const [inline, virtual]`

Whether the packed matrix is column major ordered or not.

Implements [ClpMatrixBase](#).

Definition at line 27 of file `ClpNetworkMatrix.hpp`.

3.35.3.2 `virtual CoinBigIndex ClpNetworkMatrix::getNumElements ( ) const [inline, virtual]`

Number of entries in the packed matrix.

Implements [ClpMatrixBase](#).

Definition at line 31 of file `ClpNetworkMatrix.hpp`.

3.35.3.3 `virtual int ClpNetworkMatrix::getNumCols ( ) const [inline, virtual]`

Number of columns.

Implements [ClpMatrixBase](#).

Definition at line 35 of file `ClpNetworkMatrix.hpp`.

3.35.3.4 `virtual int ClpNetworkMatrix::getNumRows ( ) const [inline, virtual]`

Number of rows.

Implements [ClpMatrixBase](#).

Definition at line 39 of file `ClpNetworkMatrix.hpp`.

3.35.3.5 `virtual const double* ClpNetworkMatrix::getElements ( ) const [virtual]`

A vector containing the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

**3.35.3.6** `virtual const int* ClpNetworkMatrix::getIndices ( ) const [inline, virtual]`

A vector containing the minor indices of the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

Definition at line 53 of file `ClpNetworkMatrix.hpp`.

**3.35.3.7** `virtual const int* ClpNetworkMatrix::getVectorLengths ( ) const [virtual]`

The lengths of the major-dimension vectors.

Implements [ClpMatrixBase](#).

**3.35.3.8** `virtual void ClpNetworkMatrix::deleteCols ( const int numDel, const int * indDel ) [virtual]`

Delete the columns whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.35.3.9** `virtual void ClpNetworkMatrix::deleteRows ( const int numDel, const int * indDel ) [virtual]`

Delete the rows whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.35.3.10** `virtual int ClpNetworkMatrix::appendMatrix ( int number, int type, const CoinBigIndex * starts, const int * index, const double * element, int numberOther = -1 ) [virtual]`

Append a set of rows/columns to the end of the matrix.

Returns number of errors i.e. if any of the new rows/columns contain an index that's larger than the number of columns-1/rows-1 (if `numberOther`>0) or duplicates. If 0 then rows, 1 if columns.

Reimplemented from [ClpMatrixBase](#).

**3.35.3.11** `virtual CoinBigIndex* ClpNetworkMatrix::dubiousWeights ( const ClpSimplex * model, int * inputWeights ) const [virtual]`

Given positive integer weights for each row fills in sum of weights for each column (and slack).

Returns weights vector

Reimplemented from [ClpMatrixBase](#).

3.35.3.12 `virtual void ClpNetworkMatrix::rangeOfElements ( double & smallestNegative,  
double & largestNegative, double & smallestPositive, double & largestPositive )  
[virtual]`

Returns largest and smallest elements of both signs.

Largest refers to largest absolute value.

Reimplemented from [ClpMatrixBase](#).

3.35.3.13 `virtual void ClpNetworkMatrix::unpackPacked ( ClpSimplex * model,  
CoinIndexedVector * rowArray, int column ) const [virtual]`

Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.

Bounds and objective could be modified if doing column generation (just for this variable)

Implements [ClpMatrixBase](#).

3.35.3.14 `virtual void ClpNetworkMatrix::times ( double scalar, const double * x, double * y )  
const [virtual]`

Return  $y + A * scalar * x$  in  $y$ .

#### Precondition

$x$  must be of size `numColumns()`  
 $y$  must be of size `numRows()`

Implements [ClpMatrixBase](#).

3.35.3.15 `virtual void ClpNetworkMatrix::transposeTimes ( double scalar, const double * x,  
double * y ) const [virtual]`

Return  $y + x * scalar * A$  in  $y$ .

#### Precondition

$x$  must be of size `numRows()`  
 $y$  must be of size `numColumns()`

Implements [ClpMatrixBase](#).

3.35.3.16 `virtual void ClpNetworkMatrix::transposeTimes ( const ClpSimplex * model, double  
scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z )  
const [virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#)

Implements [ClpMatrixBase](#).

3.35.3.17 `virtual void ClpNetworkMatrix::subsetTransposeTimes ( const ClpSimplex * model,  
const CoinIndexedVector * x, const CoinIndexedVector * y, CoinIndexedVector * z )  
const` [virtual]

Return  $x^T A$  in  $z$  but just for indices in  $y$ .

Note -  $z$  always packed mode

Implements [ClpMatrixBase](#).

3.35.3.18 `virtual ClpMatrixBase* ClpNetworkMatrix::subsetClone ( int numberRows,  
const int * whichRows, int numberColumns, const int * whichColumns ) const`  
[virtual]

Subset clone (without gaps).


Duplicates are allowed and order is as given

Reimplemented from [ClpMatrixBase](#).

The documentation for this class was generated from the following file:

- `ClpNetworkMatrix.hpp`

Collaboration diagram for ClpNode:



- struct **branchState**

## Useful methods

- void **applyNode** (ClpSimplex \*model, int doBoundsEtc)
  - Applies node to model 0 - just tree bounds 1 - tree bounds and basis etc 2 - saved bounds and basis etc.*
- void **chooseVariable** (ClpSimplex \*model, ClpNodeStuff \*info)

- *Choose a new variable.*  
int `fixOnReducedCosts` (`ClpSimplex` \*model)
- *Fix on reduced costs.*  
void `createArrays` (`ClpSimplex` \*model)
- *Create odd arrays.*  
void `cleanUpForCrunch` ()
- *Clean up as crunch is different model.*

#### Gets and sets

- double `objectiveValue` () const  
*Objective value.*
- void `setObjectiveValue` (double value)  
*Set objective value.*
- const double \* `primalSolution` () const  
*Primal solution.*
- const double \* `dualSolution` () const  
*Dual solution.*
- double `branchingValue` () const  
*Initial value of integer variable.*
- double `sumInfeasibilities` () const  
*Sum infeasibilities.*
- int `numberInfeasibilities` () const  
*Number infeasibilities.*
- int `depth` () const  
*Relative depth.*
- double `estimatedSolution` () const  
*Estimated solution value.*
- int `way` () const  
*Way for integer variable -1 down , +1 up.*
- bool `fathomed` () const  
*Return true if branch exhausted.*
- void `changeState` ()  
*Change state of variable i.e. go other way.*
- int `sequence` () const  
*Sequence number of integer variable (-1 if none)*
- bool `oddArraysExist` () const  
*If odd arrays exist.*
- const unsigned char \* `statusArray` () const  
*Status array.*

#### Constructors, destructor

- `ClpNode` ()  
*Default constructor.*
- `ClpNode` (`ClpSimplex` \*model, const `ClpNodeStuff` \*stuff, int depth)  
*Constructor from model.*
- void `gutsOfConstructor` (`ClpSimplex` \*model, const `ClpNodeStuff` \*stuff, int arraysExist, int depth)  
*Does work of constructor (partly so gdb will work)*
- virtual `~ClpNode` ()  
*Destructor.*

Copy methods (at present illegal - will abort)

- [ClpNode](#) (const [ClpNode](#) &)  
*The copy constructor.*
- [ClpNode](#) & [operator=](#) (const [ClpNode](#) &)  
*Operator =.*

#### Protected Attributes

##### Data

- double [branchingValue\\_](#)  
*Initial value of integer variable.*
- double [objectiveValue\\_](#)  
*Value of objective.*
- double [sumInfeasibilities\\_](#)  
*Sum of infeasibilities.*
- double [estimatedSolution\\_](#)  
*Estimated solution value.*
- [ClpFactorization](#) \* [factorization\\_](#)  
*Factorization.*
- [ClpDualRowSteepest](#) \* [weights\\_](#)  
*Steepest edge weights.*
- unsigned char \* [status\\_](#)  
*Status vector.*
- double \* [primalSolution\\_](#)  
*Primal solution.*
- double \* [dualSolution\\_](#)  
*Dual solution.*
- int \* [lower\\_](#)  
*Integer lower bounds (only used in fathomMany)*
- int \* [upper\\_](#)  
*Integer upper bounds (only used in fathomMany)*
- int \* [pivotVariables\\_](#)  
*Pivot variables for factorization.*
- int \* [fixed\\_](#)  
*Variables fixed by reduced costs (at end of branch) 0x10000000 added if fixed to UB.*
- [branchState](#) [branchState\\_](#)  
*State of branch.*
- int [sequence\\_](#)  
*Sequence number of integer variable (-1 if none)*
- int [numberInfeasibilities\\_](#)  
*Number of infeasibilities.*
- int [depth\\_](#)  
*Relative depth.*
- int [numberFixed\\_](#)  
*Number fixed by reduced cost.*

- int [flags\\_](#)  
*Flags - 1 duals scaled.*
- int [maximumFixed\\_](#)  
*Maximum number fixed by reduced cost.*
- int [maximumRows\\_](#)  
*Maximum rows so far.*
- int [maximumColumns\\_](#)  
*Maximum columns so far.*
- int [maximumIntegers\\_](#)  
*Maximum Integers so far.*

### 3.36.1 Detailed Description

Definition at line 19 of file ClpNode.hpp.

### 3.36.2 Constructor & Destructor Documentation

#### 3.36.2.1 ClpNode::ClpNode ( )

Default constructor.

#### 3.36.2.2 ClpNode::ClpNode ( const ClpNode & )


The copy constructor.

The documentation for this class was generated from the following file:

- ClpNode.hpp

Collaboration diagram for ClpNodeStuff:

Collaboration diagram for ClpNodeStuff:



## Constructors, destructor

## Constructors, destructor

- `ClpNodeStuff ()`  
*Default constructor.*
- `virtual ~ClpNodeStuff ()`  
*Destructor.*

### Copy methods (only copies ints etc, nulls arrays)

- `ClpNodeStuff` (const `ClpNodeStuff` &)  
*The copy constructor.*
- `ClpNodeStuff` & `operator=` (const `ClpNodeStuff` &)  
*Operator =.*
- void `zap` (int type)  
*Zaps stuff 1 - arrays, 2 ints, 3 both.*

## Fill methods

- void [fillPseudoCosts](#) (const double \*down, const double \*up, const int \*priority, const int \*numberDown, const int \*numberUp, const int \*numberDownInfeasible, const int \*numberUpInfeasible, int number)  
*Fill with pseudocosts.*
- void [update](#) (int way, int sequence, double change, bool feasible)  
*Update pseudo costs.*
- int [maximumNodes](#) () const  
*Return maximum number of nodes.*
- int [maximumSpace](#) () const  
*Return maximum space for nodes.*

## Public Attributes

## Data

- double [integerTolerance\\_](#)  
*Integer tolerance.*
- double [integerIncrement\\_](#)  
*Integer increment.*
- double [smallChange\\_](#)  
*Small change in branch.*
- double \* [downPseudo\\_](#)  
*Down pseudo costs.*
- double \* [upPseudo\\_](#)  
*Up pseudo costs.*
- int \* [priority\\_](#)  
*Priority.*
- int \* [numberDown\\_](#)  
*Number of times down.*
- int \* [numberUp\\_](#)  
*Number of times up.*
- int \* [numberDownInfeasible\\_](#)  
*Number of times down infeasible.*
- int \* [numberUpInfeasible\\_](#)  
*Number of times up infeasible.*
- double \* [saveCosts\\_](#)  
*Copy of costs (local)*
- [ClpNode](#) \*\* [nodeInfo\\_](#)  
*Array of ClpNodes.*
- [ClpSimplex](#) \* [large\\_](#)  
*Large model if crunched.*
- int \* [whichRow\\_](#)  
*Which rows in large model.*
- int \* [whichColumn\\_](#)  
*Which columns in large model.*
- CoinMessageHandler \* [handler\\_](#)

- Cbc's message handler.*
- int [nBound\\_](#)  
*Number bounds in large model.*
- int [saveOptions\\_](#)  
*Save of specialOptions\_ (local)*
- int [solverOptions\\_](#)  
*Options to pass to solver 1 - create external reduced costs for columns 2 - create external reduced costs for rows 4 - create external row activity (columns always done) Above only done if feasible 32 - just create up to nDepth\_+1 nodes 65536 - set if activated.*
- int [maximumNodes\\_](#)  
*Maximum number of nodes to do.*
- int [numberBeforeTrust\\_](#)  
*Number before trust from CbcModel.*
- int [stateOfSearch\\_](#)  
*State of search from CbcModel.*
- int [nDepth\\_](#)  
*Number deep.*
- int [nNodes\\_](#)  
*Number nodes returned (-1 if fathom aborted)*
- int [numberNodesExplored\\_](#)  
*Number of nodes explored.*
- int [numberIterations\\_](#)  
*Number of iterations.*
- int [presolveType\\_](#)  
*Type of presolve - 0 none, 1 crunch.*
- int [startingDepth\\_](#)  
*Depth passed in.*
- int [nodeCalled\\_](#)  
*Node at which called.*

### 3.37.1 Detailed Description

Definition at line 176 of file ClpNode.hpp.

### 3.37.2 Constructor & Destructor Documentation

#### 3.37.2.1 ClpNodeStuff::ClpNodeStuff ( )

Default constructor.


#### 3.37.2.2 ClpNodeStuff::ClpNodeStuff ( const ClpNodeStuff & )

The copy constructor.

The documentation for this class was generated from the following file:

- ClpNode.hpp

Collaboration diagram for ClpNonLinearCost:



## Constructors, destructor

## Constructors, destructor

- `ClpNonLinearCost ()`  
*Default constructor.*
- `ClpNonLinearCost (ClpSimplex *model, int method=1)`  
*Constructor from simplex.*
- `ClpNonLinearCost (ClpSimplex *model, const int *starts, const double *lower, const double *cost)`

Constructor from simplex and list of non-linearities (columns only) First lower of each column has to match real lower Last lower has to be  $\leq$  upper (if == then cost ignored) This could obviously be changed to make more user friendly.

- `~ClpNonLinearCost ()`  
Destructor.
- `ClpNonLinearCost (const ClpNonLinearCost &)`
- `ClpNonLinearCost & operator= (const ClpNonLinearCost &)`

#### Actual work in primal

- void `checkInfeasibilities` (double oldTolerance=0.0)  
*Changes infeasible costs and computes number and cost of infeas. Puts all non-basic (non free) variables to bounds and all free variables to zero if oldTolerance is non-zero.*
- void `checkInfeasibilities` (int numberInArray, const int \*index)  
*Changes infeasible costs for each variable. The indices are row indices and need converting to sequences.*
- void `checkChanged` (int numberInArray, CoinIndexedVector \*update)  
*Puts back correct infeasible costs for each variable. The input indices are row indices and need converting to sequences for costs.*
- void `goThru` (int numberInArray, double multiplier, const int \*index, const double \*work, double \*rhs)  
*Goes through one bound for each variable.*
- void `goBack` (int numberInArray, const int \*index, double \*rhs)  
*Takes off last iteration (i.e.).*
- void `goBackAll` (const CoinIndexedVector \*update)  
*Puts back correct infeasible costs for each variable. The input indices are row indices and need converting to sequences for costs.*
- void `zapCosts` ()  
*Temporary zeroing of feasible costs.*
- void `refreshCosts` (const double \*columnCosts)  
*Refreshes costs always makes row costs zero.*
- void `feasibleBounds` ()  
*Puts feasible bounds into lower and upper.*
- double `setOne` (int sequence, double solutionValue)  
*Sets bounds and cost for one variable. Returns change in cost. May need to be inline for speed.*
- void `setOne` (int sequence, double solutionValue, double lowerValue, double upperValue, double costValue=0.0)  
*Sets bounds and infeasible cost and true cost for one variable. This is for gub and column generation etc.*
- int `setOneOutgoing` (int sequence, double &solutionValue)  
*Sets bounds and cost for outgoing variable may change value. Returns direction.*
- double `nearest` (int sequence, double solutionValue)  
*Returns nearest bound.*
- double `changeInCost` (int sequence, double alpha) const  
*Returns change in cost - one down if  $\alpha > 0.0$ , up if  $\alpha < 0.0$ . Value is current - new.*
- double `changeUpInCost` (int sequence) const
- double `changeDownInCost` (int sequence) const
- double `changeInCost` (int sequence, double alpha, double &rhs)

- This also updates next bound.*
- double **lower** (int sequence) const  
*Returns current lower bound.*
- double **upper** (int sequence) const  
*Returns current upper bound.*
- double **cost** (int sequence) const  
*Returns current cost.*

#### Gets and sets

- int **numberInfeasibilities** () const  
*Number of infeasibilities.*
- double **changeInCost** () const  
*Change in cost.*
- double **feasibleCost** () const  
*Feasible cost.*
- double **feasibleReportCost** () const  
*Feasible cost with offset and direction (i.e. for reporting)*
- double **sumInfeasibilities** () const  
*Sum of infeasibilities.*
- double **largestInfeasibility** () const  
*Largest infeasibility.*
- double **averageTheta** () const  
*Average theta.*
- void **setAverageTheta** (double value)
- void **setChangeInCost** (double value)
- void **setMethod** (int value)
- bool **lookBothWays** () const  
*See if may want to look both ways.*

#### Private functions to deal with infeasible regions

- bool **infeasible** (int i) const
- void **setInfeasible** (int i, bool trueFalse)
- unsigned char \* **statusArray** () const
- void **validate** ()  
*For debug.*

#### 3.38.1 Detailed Description

Definition at line 78 of file ClpNonLinearCost.hpp.

#### 3.38.2 Constructor & Destructor Documentation

##### 3.38.2.1 ClpNonLinearCost::ClpNonLinearCost ( ClpSimplex \* model, int method = 1 )

Constructor from simplex.

This will just set up wasteful arrays for linear, but later may do dual analysis and even finding duplicate columns .

## 3.38.3 Member Function Documentation

3.38.3.1 void ClpNonLinearCost::checkInfeasibilities ( double *oldTolerance* = 0.0 )

Changes infeasible costs and computes number and cost of infeas. Puts all non-basic (non free) variables to bounds and all free variables to zero if *oldTolerance* is non-zero.

- but does not move those  $\leq$  *oldTolerance* away

3.38.3.2 void ClpNonLinearCost::checkChanged ( int *numberInArray*, CoinIndexedVector \* *update* )

Puts back correct infeasible costs for each variable. The input indices are row indices and need converting to sequences for costs.

On input array is empty (but indices exist). On exit just changed costs will be stored as normal CoinIndexedVector

3.38.3.3 void ClpNonLinearCost::goThru ( int *numberInArray*, double *multiplier*, const int \* *index*, const double \* *work*, double \* *rhs* )

Goes through one bound for each variable.

If  $\text{multiplier} * \text{work}[\text{iRow}] > 0$  goes down, otherwise up. The indices are row indices and need converting to sequences. Temporary offsets may be set. Rhs entries are increased.

3.38.3.4 void ClpNonLinearCost::goBack ( int *numberInArray*, const int \* *index*, double \* *rhs* )

Takes off last iteration (i.e.

offsets closer to 0)

3.38.3.5 void ClpNonLinearCost::goBackAll ( const CoinIndexedVector \* *update* )

Puts back correct infeasible costs for each variable. The input indices are row indices and need converting to sequences for costs.

At the end of this all temporary offsets are zero

The documentation for this class was generated from the following file:


- ClpNonLinearCost.hpp

## 3.39 ClpObjective Class Reference

Objective Abstract Base Class.

```
#include <ClpObjective.hpp>
```

Inheritance diagram for ClpObjective:



#### Public Member Functions

##### Stuff

- virtual double \* [gradient](#) (const [ClpSimplex](#) \*model, const double \*solution, double &offset, bool refresh, int includeLinear=2)=0  
*Returns gradient.*
- virtual double [reducedGradient](#) ([ClpSimplex](#) \*model, double \*region, bool useFeasibleCosts)=0  
*Returns reduced gradient. Returns an offset (to be added to current one).*
- virtual double [stepLength](#) ([ClpSimplex](#) \*model, const double \*solution, const double \*change, double maximumTheta, double &currentObj, double &predictedObj, double &thetaObj)=0  
*Returns step length which gives minimum of objective for solution + theta \* change vector up to maximum theta.*
- virtual double [objectiveValue](#) (const [ClpSimplex](#) \*model, const double \*solution) const =0  
*Return objective value (without any [ClpModel](#) offset) (model may be NULL)*
- virtual void [resize](#) (int newNumberColumns)=0  
*Resize objective.*
- virtual void [deleteSome](#) (int numberToDelete, const int \*which)=0  
*Delete columns in objective.*
- virtual void [reallyScale](#) (const double \*columnScale)=0  
*Scale objective.*
- virtual int [markNonlinear](#) (char \*which)  
*Given a zeroed array sets nonlinear columns to 1.*
- virtual void [newXValues](#) ()  
*Say we have new primal solution - so may need to recompute.*

**Constructors and destructors**

- [ClpObjective](#) ()  
*Default Constructor.*
- [ClpObjective](#) (const [ClpObjective](#) &)  
*Copy constructor.*
- [ClpObjective](#) & [operator=](#) (const [ClpObjective](#) &rhs)  
*Assignment operator.*
- virtual [~ClpObjective](#) ()  
*Destructor.*
- virtual [ClpObjective](#) \* [clone](#) () const =0  
*Clone.*
- virtual [ClpObjective](#) \* [subsetClone](#) (int numberColumns, const int \*whichColumns) const  
*Subset clone.*

**Other**

- int [type](#) ()  
*Returns type (above 63 is extra information)*
- int [activated](#) () const  
*Whether activated.*
- void [setActivated](#) (int value)  
*Set whether activated.*
- double [nonlinearOffset](#) () const  
*Objective offset.*

**Protected Attributes****Protected member data**

- double [offset\\_](#)  
*Value of non-linear part of objective.*
- int [type\\_](#)  
*Type of objective - linear is 1.*
- int [activated\\_](#)  
*Whether activated.*

**3.39.1 Detailed Description**

Objective Abstract Base Class.

Abstract Base Class for describing an objective function

Definition at line 19 of file [ClpObjective.hpp](#).

## 3.39.2 Member Function Documentation

**3.39.2.1** `virtual double* ClpObjective::gradient ( const ClpSimplex * model, const double * solution, double & offset, bool refresh, int includeLinear = 2 )` [pure virtual]

Returns gradient.

If Linear then solution may be NULL, also returns an offset (to be added to current one)  
If refresh is false then uses last solution Uses model for scaling includeLinear 0 - no, 1 as is, 2 as feasible

Implemented in [ClpLinearObjective](#), and [ClpQuadraticObjective](#).

**3.39.2.2** `virtual double ClpObjective::stepLength ( ClpSimplex * model, const double * solution, const double * change, double maximumTheta, double & currentObj, double & predictedObj, double & thetaObj )` [pure virtual]

Returns step length which gives minimum of objective for solution + theta \* change vector up to maximum theta.

arrays are numberColumns+numberRows Also sets current objective, predicted and at maximumTheta

Implemented in [ClpLinearObjective](#), and [ClpQuadraticObjective](#).

**3.39.2.3** `virtual int ClpObjective::markNonlinear ( char * which )` [virtual]

Given a zeroed array sets nonlinear columns to 1.

Returns number of nonlinear columns

Reimplemented in [ClpQuadraticObjective](#).

**3.39.2.4** `virtual ClpObjective* ClpObjective::subsetClone ( int numberColumns, const int * whichColumns ) const` [virtual]

Subset clone.

Duplicates are allowed and order is as given. Derived classes need not provide this as it may not always make sense


Reimplemented in [ClpLinearObjective](#), and [ClpQuadraticObjective](#).

The documentation for this class was generated from the following file:


- [ClpObjective.hpp](#)

## 3.40 ClpPackedMatrix Class Reference

Inheritance diagram for ClpPackedMatrix:



Collaboration diagram for ClpPackedMatrix:



## Public Member Functions

### Useful methods

- virtual `CoinPackedMatrix *` [`getPackedMatrix`](#) () const  
*Return a complete CoinPackedMatrix.*
- virtual bool [`isColOrdered`](#) () const  
*Whether the packed matrix is column major ordered or not.*
- virtual `CoinBigIndex` [`getNumElements`](#) () const  
*Number of entries in the packed matrix.*
- virtual int [`getNumCols`](#) () const  
*Number of columns.*
- virtual int [`getNumRows`](#) () const  
*Number of rows.*
- virtual const double \* [`getElements`](#) () const  
*A vector containing the elements in the packed matrix.*
- double \* [`getMutableElements`](#) () const  
*Mutable elements.*
- virtual const int \* [`getIndices`](#) () const  
*A vector containing the minor indices of the elements in the packed matrix.*
- virtual const `CoinBigIndex *` [`getVectorStarts`](#) () const
- virtual const int \* [`getVectorLengths`](#) () const  
*The lengths of the major-dimension vectors.*
- virtual int [`getVectorLength`](#) (int index) const

- The length of a single major-dimension vector.*
- virtual void [deleteCols](#) (const int numDel, const int \*indDel)  
*Delete the columns whose indices are listed in indDel.*
  - virtual void [deleteRows](#) (const int numDel, const int \*indDel)  
*Delete the rows whose indices are listed in indDel.*
  - virtual void [appendCols](#) (int number, const CoinPackedVectorBase \*const \*columns)
- Append Columns.*
- virtual void [appendRows](#) (int number, const CoinPackedVectorBase \*const \*rows)
- Append Rows.*
- virtual int [appendMatrix](#) (int number, int type, const CoinBigIndex \*starts, const int \*index, const double \*element, int numberOther=-1)  
*Append a set of rows/columns to the end of the matrix.*
  - virtual void [replaceVector](#) (const int index, const int numReplace, const double \*newElements)  
*Replace the elements of a vector.*
  - virtual void [modifyCoefficient](#) (int row, int column, double newElement, bool keepZero=false)  
*Modify one element of packed matrix.*
  - virtual [ClpMatrixBase](#) \* [reverseOrderedCopy](#) () const  
*Returns a new matrix in reverse order without gaps.*
  - virtual CoinBigIndex [countBasis](#) (const int \*whichColumn, int &numberColumnBasic)  
*Returns number of elements in column part of basis.*
  - virtual void [fillBasis](#) ([ClpSimplex](#) \*model, const int \*whichColumn, int &numberColumnBasic, int \*row, int \*start, int \*rowCount, int \*columnCount, CoinFactorizationDouble \*element)  
*Fills in column part of basis.*
  - virtual int [scale](#) ([ClpModel](#) \*model, const [ClpSimplex](#) \*baseModel=NULL) const  
*Creates scales for column copy (rowCopy in model may be modified) returns non-zero if no scaling done.*
  - virtual void [scaleRowCopy](#) ([ClpModel](#) \*model) const  
*Scales rowCopy if column copy scaled Only called if scales already exist.*
  - void [createScaledMatrix](#) ([ClpSimplex](#) \*model) const  
*Creates scaled column copy if scales exist.*
  - virtual [ClpMatrixBase](#) \* [scaledColumnCopy](#) ([ClpModel](#) \*model) const  
*Really really scales column copy Only called if scales already exist.*
  - virtual bool [allElementsInRange](#) ([ClpModel](#) \*model, double smallest, double largest, int check=15)  
*Checks if all elements are in valid range.*
  - virtual void [rangeOfElements](#) (double &smallestNegative, double &largestNegative, double &smallestPositive, double &largestPositive)  
*Returns largest and smallest elements of both signs.*
  - virtual void [unpack](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const  
*Unpacks a column into an CoinIndexedvector.*

- virtual void [unpackPacked](#) (ClpSimplex \*model, CoinIndexedVector \*rowArray, int column) const  
*Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.*
- virtual void [add](#) (const ClpSimplex \*model, CoinIndexedVector \*rowArray, int column, double multiplier) const  
*Adds multiple of a column into an CoinIndexedvector You can use quickAdd to add to vector.*
- virtual void [add](#) (const ClpSimplex \*model, double \*array, int column, double multiplier) const  
*Adds multiple of a column into an array.*
- virtual void [releasePackedMatrix](#) () const  
*Allow any parts of a created CoinPackedMatrix to be deleted.*
- virtual CoinBigIndex \* [dubiousWeights](#) (const ClpSimplex \*model, int \*inputWeights) const  
*Given positive integer weights for each row fills in sum of weights for each column (and slack).*
- virtual bool [canDoPartialPricing](#) () const  
*Says whether it can do partial pricing.*
- virtual void [partialPricing](#) (ClpSimplex \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Partial pricing.*
- virtual int [refresh](#) (ClpSimplex \*model)  
*makes sure active columns correct*
- virtual void [reallyScale](#) (const double \*rowScale, const double \*columnScale)
- virtual void [setDimensions](#) (int numRows, int numcols)  
*Set the dimensions of the matrix.*

#### Matrix times vector methods

- virtual void [times](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + A * scalar * x$  in  $y$ .*
- virtual void [times](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale) const  
*And for scaling.*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + x * scalar * A$  in  $y$ .*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale, double \*spare=NULL) const  
*And for scaling.*
- void [transposeTimesSubset](#) (int number, const int \*which, const double \*pi, double \*y, const double \*rowScale, const double \*columnScale, double \*spare=NULL) const  
*Return  $y - pi * A$  in  $y$ .*
- virtual void [transposeTimes](#) (const ClpSimplex \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const  
*Return  $x * scalar * A + y$  in  $z$ .*
- void [transposeTimesByColumn](#) (const ClpSimplex \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const

*Return  $x * scalar * A + y$  in  $z$ .*

- virtual void [transposeTimesByRow](#) (const [ClpSimplex](#) \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const

*Return  $x * scalar * A + y$  in  $z$ .*

- virtual void [subsetTransposeTimes](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*x, const CoinIndexedVector \*y, CoinIndexedVector \*z) const

*Return  $x * A$  in  $z$  but just for indices in  $y$ .*

- virtual bool [canCombine](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*pi) const

*Returns true if can combine transposeTimes and subsetTransposeTimes and if it would be faster.*

- virtual void [transposeTimes2](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*pi1, CoinIndexedVector \*dj1, const CoinIndexedVector \*pi2, CoinIndexedVector \*spare, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)

*Updates two arrays for steepest.*

- virtual void [subsetTimes2](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*dj1, const CoinIndexedVector \*pi2, CoinIndexedVector \*dj2, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)

*Updates second array for steepest and does devex weights.*

- void [useEffectiveRhs](#) ([ClpSimplex](#) \*model)

*Sets up an effective RHS.*

#### Other

- CoinPackedMatrix \* [matrix](#) () const

*Returns CoinPackedMatrix (non const)*

- void [setMatrixNull](#) ()

*Just sets matrix\_ to NULL so it can be used elsewhere.*

- void [makeSpecialColumnCopy](#) ()

*Say we want special column copy.*

- void [releaseSpecialColumnCopy](#) ()

*Say we don't want special column copy.*

- bool [zeros](#) () const

*Are there zeros?*

- bool [wantsSpecialColumnCopy](#) () const

*Do we want special column copy.*

- int [flags](#) () const

*Flags.*

- void [checkGaps](#) ()

*Sets flags\_ correctly.*

#### Constructors, destructor

- [ClpPackedMatrix](#) ()

*Default constructor.*

- virtual [~ClpPackedMatrix](#) ()

*Destructor.*

## Copy method

- [ClpPackedMatrix](#) (const [ClpPackedMatrix](#) &)  
*The copy constructor.*
- [ClpPackedMatrix](#) (const [CoinPackedMatrix](#) &)  
*The copy constructor from an [CoinPackedMatrix](#).*
- [ClpPackedMatrix](#) (const [ClpPackedMatrix](#) &wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns)  
*Subset constructor (without gaps).*
- **ClpPackedMatrix** (const [CoinPackedMatrix](#) &wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns)
- [ClpPackedMatrix](#) ([CoinPackedMatrix](#) \*matrix)  
*This takes over ownership (for space reasons)*
- [ClpPackedMatrix](#) & **operator=** (const [ClpPackedMatrix](#) &)
- virtual [ClpMatrixBase](#) \* **clone** () const  
*Clone.*
- virtual void **copy** (const [ClpPackedMatrix](#) \*from)  
*Copy contents - resizing if necessary - otherwise re-use memory.*
- virtual [ClpMatrixBase](#) \* **subsetClone** (int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns) const  
*Subset clone (without gaps).*
- void **specialRowCopy** ([ClpSimplex](#) \*model, const [ClpMatrixBase](#) \*rowCopy)  
*make special row copy*
- void **specialColumnCopy** ([ClpSimplex](#) \*model)  
*make special column copy*
- virtual void **correctSequence** (const [ClpSimplex](#) \*model, int &sequenceIn, int &sequenceOut)  
*Correct sequence in and out to give true value.*

## Protected Member Functions

- void **checkFlags** (int type) const  
*Check validity.*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- [CoinPackedMatrix](#) \* **matrix\_**  
*Data.*
- int **numberActiveColumns\_**  
*number of active columns (normally same as number of columns)*
- int **flags\_**  
*Flags - 1 - has zero elements 2 - has gaps 4 - has special row copy 8 - has special column copy 16 - wants special column copy.*
- [ClpPackedMatrix2](#) \* **rowCopy\_**  
*Special row copy.*
- [ClpPackedMatrix3](#) \* **columnCopy\_**  
*Special column copy.*

### 3.40.1 Detailed Description

Definition at line 30 of file ClpPackedMatrix.hpp.

### 3.40.2 Constructor & Destructor Documentation

#### 3.40.2.1 ClpPackedMatrix::ClpPackedMatrix ( )

Default constructor.

#### 3.40.2.2 ClpPackedMatrix::ClpPackedMatrix ( const ClpPackedMatrix & )

The copy constructor.

#### 3.40.2.3 ClpPackedMatrix::ClpPackedMatrix ( const CoinPackedMatrix & )

The copy constructor from an CoinPackedMatrix.

#### 3.40.2.4 ClpPackedMatrix::ClpPackedMatrix ( const ClpPackedMatrix & *wholeModel*, int *numberOfRows*, const int \* *whichRows*, int *numberOfColumns*, const int \* *whichColumns* )

Subset constructor (without gaps).

Duplicates are allowed and order is as given

### 3.40.3 Member Function Documentation

#### 3.40.3.1 virtual bool ClpPackedMatrix::isColOrdered ( ) const [inline, virtual]

Whether the packed matrix is column major ordered or not.

Implements [ClpMatrixBase](#).

Definition at line 40 of file ClpPackedMatrix.hpp.

#### 3.40.3.2 virtual CoinBigIndex ClpPackedMatrix::getNumElements ( ) const [inline, virtual]

Number of entries in the packed matrix.

Implements [ClpMatrixBase](#).

Definition at line 44 of file ClpPackedMatrix.hpp.

#### 3.40.3.3 virtual int ClpPackedMatrix::getNumCols ( ) const [inline, virtual]

Number of columns.

Implements [ClpMatrixBase](#).

Definition at line 48 of file ClpPackedMatrix.hpp.

**3.40.3.4** `virtual int ClpPackedMatrix::getNumRows ( ) const [inline, virtual]`

Number of rows.

Implements [ClpMatrixBase](#).

Definition at line 52 of file ClpPackedMatrix.hpp.

**3.40.3.5** `virtual const double* ClpPackedMatrix::getElements ( ) const [inline, virtual]`

A vector containing the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

Definition at line 60 of file ClpPackedMatrix.hpp.

**3.40.3.6** `virtual const int* ClpPackedMatrix::getIndices ( ) const [inline, virtual]`

A vector containing the minor indices of the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

Definition at line 72 of file ClpPackedMatrix.hpp.

**3.40.3.7** `virtual const int* ClpPackedMatrix::getVectorLengths ( ) const [inline, virtual]`

The lengths of the major-dimension vectors.

Implements [ClpMatrixBase](#).

Definition at line 80 of file ClpPackedMatrix.hpp.

**3.40.3.8** `virtual int ClpPackedMatrix::getVectorLength ( int index ) const [inline, virtual]`

The length of a single major-dimension vector.

Reimplemented from [ClpMatrixBase](#).

Definition at line 84 of file ClpPackedMatrix.hpp.

**3.40.3.9** `virtual void ClpPackedMatrix::deleteCols ( const int numDel, const int * indDel ) [virtual]`

Delete the columns whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.40.3.10** `virtual void ClpPackedMatrix::deleteRows ( const int numDel, const int * indDel )`  
`[virtual]`

Delete the rows whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.40.3.11** `virtual int ClpPackedMatrix::appendMatrix ( int number, int type, const CoinBigIndex * starts, const int * index, const double * element, int numberOther = -1 )`  
`[virtual]`

Append a set of rows/columns to the end of the matrix.

Returns number of errors i.e. if any of the new rows/columns contain an index that's larger than the number of columns-1/rows-1 (if `numberOther`>0) or duplicates If 0 then rows, 1 if columns

Reimplemented from [ClpMatrixBase](#).

**3.40.3.12** `virtual void ClpPackedMatrix::replaceVector ( const int index, const int numReplace, const double * newElements )` `[inline, virtual]`

Replace the elements of a vector.

The indices remain the same. This is only needed if scaling and a row copy is used. At most the number specified will be replaced. The index is between 0 and major dimension of matrix

Definition at line 109 of file `ClpPackedMatrix.hpp`.

**3.40.3.13** `virtual void ClpPackedMatrix::modifyCoefficient ( int row, int column, double newElement, bool keepZero = false )` `[inline, virtual]`

Modify one element of packed matrix.

An element may be added. This works for either ordering If the new element is zero it will be deleted unless `keepZero` true

Reimplemented from [ClpMatrixBase](#).

Definition at line 116 of file `ClpPackedMatrix.hpp`.

**3.40.3.14** `virtual ClpMatrixBase* ClpPackedMatrix::scaledColumnCopy ( ClpModel * model ) const` `[virtual]`

Really really scales column copy Only called if scales already exist.

Up to user to delete

Reimplemented from [ClpMatrixBase](#).

**3.40.3.15** `virtual bool ClpPackedMatrix::allElementsInRange ( ClpModel * model, double smallest, double largest, int check = 15 )` `[virtual]`

Checks if all elements are in valid range.

Can just return true if you are not paranoid. For Clp I will probably expect no zeros.

Code can modify matrix to get rid of small elements. check bits (can be turned off to save time) : 1 - check if matrix has gaps 2 - check if zero elements 4 - check and compress duplicates 8 - report on large and small

Reimplemented from [ClpMatrixBase](#).

```
3.40.3.16 virtual void ClpPackedMatrix::rangeOfElements ( double & smallestNegative,
double & largestNegative, double & smallestPositive, double & largestPositive )
[virtual]
```

Returns largest and smallest elements of both signs.

Largest refers to largest absolute value.

Reimplemented from [ClpMatrixBase](#).

```
3.40.3.17 virtual void ClpPackedMatrix::unpackPacked ( ClpSimplex * model,
CoinIndexedVector * rowArray, int column ) const [virtual]
```

Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.

Bounds and objective could be modified if doing column generation (just for this variable)

Implements [ClpMatrixBase](#).

Reimplemented in [ClpGubMatrix](#).

```
3.40.3.18 virtual CoinBigIndex* ClpPackedMatrix::dubiousWeights ( const ClpSimplex *
model, int * inputWeights ) const [virtual]
```

Given positive integer weights for each row fills in sum of weights for each column (and slack).

Returns weights vector

Reimplemented from [ClpMatrixBase](#).

```
3.40.3.19 virtual void ClpPackedMatrix::setDimensions ( int numrows, int numcols )
[virtual]
```

Set the dimensions of the matrix.

In effect, append new empty columns/rows to the matrix. A negative number for either dimension means that that dimension doesn't change. Otherwise the new dimensions MUST be at least as large as the current ones otherwise an exception is thrown.

Reimplemented from [ClpMatrixBase](#).

```
3.40.3.20 virtual void ClpPackedMatrix::times ( double scalar, const double * x, double * y )
const [virtual]
```

Return  $y + A * scalar * x$  in  $y$ .

#### Precondition

$x$  must be of size `numColumns()`

$y$  must be of size `numRows()`

Implements [ClpMatrixBase](#).

Reimplemented in [ClpDynamicMatrix](#), and [ClpGubDynamicMatrix](#).

**3.40.3.21** `virtual void ClpPackedMatrix::transposeTimes ( double scalar, const double * x, double * y ) const` [virtual]

Return  $y + x * scalar * A$  in  $y$ .

#### Precondition

$x$  must be of size `numRows()`  
 $y$  must be of size `numColumns()`

Implements [ClpMatrixBase](#).

**3.40.3.22** `void ClpPackedMatrix::transposeTimesSubset ( int number, const int * which, const double * pi, double * y, const double * rowScale, const double * columnScale, double * spare = NULL ) const`

Return  $y - pi * A$  in  $y$ .

#### Precondition

$pi$  must be of size `numRows()`  
 $y$  must be of size `numColumns()` This just does subset (but puts in correct place in  $y$ )

**3.40.3.23** `virtual void ClpPackedMatrix::transposeTimes ( const ClpSimplex * model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z ) const` [virtual]

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#)

Implements [ClpMatrixBase](#).

Reimplemented in [ClpGubMatrix](#).

**3.40.3.24** `void ClpPackedMatrix::transposeTimesByColumn ( const ClpSimplex * model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y, CoinIndexedVector * z ) const`

Return  $x * scalar * A + y$  in  $z$ .

Note - If  $x$  packed mode - then  $z$  packed mode This does by column and knows no gaps Squashes small elements and knows about [ClpSimplex](#)

3.40.3.25 `virtual void ClpPackedMatrix::transposeTimesByRow ( const ClpSimplex *  
model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y,  
CoinIndexedVector * z ) const [virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#). This version uses row copy

Reimplemented in [ClpGubMatrix](#).

3.40.3.26 `virtual void ClpPackedMatrix::subsetTransposeTimes ( const ClpSimplex * model,  
const CoinIndexedVector * x, const CoinIndexedVector * y, CoinIndexedVector * z )  
const [virtual]`

Return  $x * A$  in  $z$  but just for indices in  $y$ .

Note -  $z$  always packed mode

Implements [ClpMatrixBase](#).

Reimplemented in [ClpGubMatrix](#).

3.40.3.27 `void ClpPackedMatrix::setMatrixNull ( ) [inline]`

Just sets `matrix_` to NULL so it can be used elsewhere.

used in GUB

Definition at line 311 of file `ClpPackedMatrix.hpp`.

3.40.3.28 `virtual ClpMatrixBase* ClpPackedMatrix::subsetClone ( int numberOfRows,  
const int * whichRows, int numberColumns, const int * whichColumns ) const  
[virtual]`

Subset clone (without gaps).

Duplicates are allowed and order is as given

Reimplemented from [ClpMatrixBase](#).

Reimplemented in [ClpGubMatrix](#).

The documentation for this class was generated from the following file:

- `ClpPackedMatrix.hpp`

## 3.41 ClpPackedMatrix2 Class Reference

### Public Member Functions

#### Useful methods

- void [transposeTimes](#) (const [ClpSimplex](#) \*model, const [CoinPackedMatrix](#) \*rowCopy, const [CoinIndexedVector](#) \*x, [CoinIndexedVector](#) \*spareArray, [CoinIndexed-](#)

Vector \*z) const

*Return  $x * -1 * A$  in  $z$ .*

- bool [usefulInfo](#) () const  
*Returns true if copy has useful information.*

#### Constructors, destructor

- [ClpPackedMatrix2](#) ()  
*Default constructor.*
- [ClpPackedMatrix2](#) ([ClpSimplex](#) \*model, const [CoinPackedMatrix](#) \*rowCopy)  
*Constructor from copy.*
- virtual [~ClpPackedMatrix2](#) ()  
*Destructor.*

#### Copy method

- [ClpPackedMatrix2](#) (const [ClpPackedMatrix2](#) &)  
*The copy constructor.*
- [ClpPackedMatrix2](#) & **operator=** (const [ClpPackedMatrix2](#) &)

#### Protected Attributes

##### Data members

*The data members are protected to allow access for derived classes.*

- int [numberBlocks\\_](#)  
*Number of blocks.*
- int [numberRows\\_](#)  
*Number of rows.*
- int \* [offset\\_](#)  
*Column offset for each block (plus one at end)*
- unsigned short \* [count\\_](#)  
*Counts of elements in each part of row.*
- [CoinBigIndex](#) \* [rowStart\\_](#)  
*Row starts.*
- unsigned short \* [column\\_](#)  
*columns within block*
- double \* [work\\_](#)  
*work arrays*

#### 3.41.1 Detailed Description

Definition at line 503 of file [ClpPackedMatrix.hpp](#).

#### 3.41.2 Constructor & Destructor Documentation

##### 3.41.2.1 [ClpPackedMatrix2::ClpPackedMatrix2](#) ( )

Default constructor.

3.41.2.2 `ClpPackedMatrix2::ClpPackedMatrix2 ( ClpSimplex * model, const CoinPackedMatrix * rowCopy )`

Constructor from copy.

3.41.2.3 `ClpPackedMatrix2::ClpPackedMatrix2 ( const ClpPackedMatrix2 & )`

The copy constructor.

### 3.41.3 Member Function Documentation

3.41.3.1 `void ClpPackedMatrix2::transposeTimes ( const ClpSimplex * model, const CoinPackedMatrix * rowCopy, const CoinIndexedVector * x, CoinIndexedVector * spareArray, CoinIndexedVector * z ) const`

Return  $x * -1 * A$  in  $z$ .


Note -  $x$  packed and  $z$  will be packed mode Squashes small elements and knows about [ClpSimplex](#)

The documentation for this class was generated from the following file:

- `ClpPackedMatrix.hpp`

## 3.42 ClpPackedMatrix3 Class Reference

Collaboration diagram for ClpPackedMatrix3:



### Public Member Functions

## Useful methods

- void [transposeTimes](#) (const [ClpSimplex](#) \*model, const double \*pi, CoinIndexedVector \*output) const  
*Return  $x * -1 * A$  in  $z$ .*
- void [transposeTimes2](#) (const [ClpSimplex](#) \*model, const double \*pi, CoinIndexedVector \*dj1, const double \*piWeight, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)  
*Updates two arrays for steepest.*

## Constructors, destructor

- [ClpPackedMatrix3](#) ()  
*Default constructor.*
- [ClpPackedMatrix3](#) ([ClpSimplex](#) \*model, const CoinPackedMatrix \*columnCopy)  
*Constructor from copy.*
- virtual [~ClpPackedMatrix3](#) ()  
*Destructor.*

## Copy method

- [ClpPackedMatrix3](#) (const [ClpPackedMatrix3](#) &)  
*The copy constructor.*
- [ClpPackedMatrix3](#) & **operator=** (const [ClpPackedMatrix3](#) &)

## Sort methods

- void [sortBlocks](#) (const [ClpSimplex](#) \*model)  
*Sort blocks.*
- void [swapOne](#) (const [ClpSimplex](#) \*model, const [ClpPackedMatrix](#) \*matrix, int iColumn)  
*Swap one variable.*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- int [numberBlocks\\_](#)  
*Number of blocks.*
- int [numberColumns\\_](#)  
*Number of columns.*
- int \* [column\\_](#)  
*Column indices and reverse lookup (within block)*
- CoinBigIndex \* [start\\_](#)  
*Starts for odd/long vectors.*
- int \* [row\\_](#)  
*Rows.*
- double \* [element\\_](#)  
*Elements.*
- [blockStruct](#) \* [block\\_](#)  
*Blocks (ordinary start at 0 and go to first block)*

## 3.42.1 Detailed Description

Definition at line 572 of file ClpPackedMatrix.hpp.

## 3.42.2 Constructor &amp; Destructor Documentation

## 3.42.2.1 ClpPackedMatrix3::ClpPackedMatrix3 ( )

Default constructor.

3.42.2.2 ClpPackedMatrix3::ClpPackedMatrix3 ( ClpSimplex \* *model*, const CoinPackedMatrix \* *columnCopy* )

Constructor from copy.

## 3.42.2.3 ClpPackedMatrix3::ClpPackedMatrix3 ( const ClpPackedMatrix3 &amp; )

The copy constructor.

## 3.42.3 Member Function Documentation

3.42.3.1 void ClpPackedMatrix3::transposeTimes ( const ClpSimplex \* *model*, const double \* *pi*, CoinIndexedVector \* *output* ) const

Return  $x * -1 * A$  in  $z$ .

Note -  $x$  packed and  $z$  will be packed mode Squashes small elements and knows about [ClpSimplex](#)

The documentation for this class was generated from the following file:


- ClpPackedMatrix.hpp

## 3.43 ClpPdco Class Reference


This solves problems in Primal Dual Convex Optimization.

```
#include <ClpPdco.hpp>
```

Inheritance diagram for ClpPdco:



Collaboration diagram for ClpPdco:



## Public Member Functions

## Description of algorithm

- int **pdco** ()  
*Pdco algorithm.*
- int **pdco** (ClpPdcoBase \*stuff, Options &options, Info &info, Outfo &outfo)

## Functions used in pdco

- void **lsqr** ()  
*LSQR.*
- void **matVecMult** (int, double \*, double \*)
- void **matVecMult** (int, CoinDenseVector< double > &, double \*)
- void **matVecMult** (int, CoinDenseVector< double > &, CoinDenseVector< double > &)
- void **matVecMult** (int, CoinDenseVector< double > \*, CoinDenseVector< double > \*)
- void **getBoundTypes** (int \*, int \*, int \*, int \*\*)
- void **getGrad** (CoinDenseVector< double > &x, CoinDenseVector< double > &grad)
- void **getHessian** (CoinDenseVector< double > &x, CoinDenseVector< double > &H)
- double **getObj** (CoinDenseVector< double > &x)
- void **matPrecon** (double, double \*, double \*)
- void **matPrecon** (double, CoinDenseVector< double > &, double \*)
- void **matPrecon** (double, CoinDenseVector< double > &, CoinDenseVector< double > &)
- void **matPrecon** (double, CoinDenseVector< double > \*, CoinDenseVector< double > \*)

## 3.43.1 Detailed Description

This solves problems in Primal Dual Convex Optimization.

It inherits from [ClpInterior](#). It has no data of its own and is never created - only cast from a [ClpInterior](#) object at algorithm time.

Definition at line 22 of file ClpPdco.hpp.

## 3.43.2 Member Function Documentation

## 3.43.2.1 int ClpPdco::pdco ( )

Pdco algorithm.

Method

Reimplemented from [ClpInterior](#).

The documentation for this class was generated from the following file:


- ClpPdco.hpp

### 3.44 ClpPdcoBase Class Reference

Abstract base class for tailoring everything for Pcdco.

```
#include <ClpPdcoBase.hpp>
```

Inheritance diagram for ClpPdcoBase:



#### Public Member Functions

Virtual methods that the derived classes must provide

- virtual void **matVecMult** ([ClpInterior](#) \*model, int mode, double \*x, double \*y) const =0
- virtual void **getGrad** ([ClpInterior](#) \*model, CoinDenseVector< double > &x, CoinDenseVector< double > &grad) const =0
- virtual void **getHessian** ([ClpInterior](#) \*model, CoinDenseVector< double > &x, CoinDenseVector< double > &H) const =0
- virtual double **getObj** ([ClpInterior](#) \*model, CoinDenseVector< double > &x) const =0
- virtual void **matPrecon** ([ClpInterior](#) \*model, double delta, double \*x, double \*y) const =0

#### Other

##### Clone

- virtual [ClpPdcoBase](#) \* **clone** () const =0
- int **type** () const  
*Returns type.*
- void **setType** (int type)  
*Sets type.*
- int **sizeD1** () const  
*Returns size of d1.*
- double **getD1** () const

- Returns d1 as scalar.*
- int [sizeD2](#) () const  
*Returns size of d2.*
- double [getD2](#) () const  
*Returns d2 as scalar.*

#### Protected Attributes

##### Data members

*The data members are protected to allow access for derived classes.*

- double [d1\\_](#)  
*Should be dense vectors.*
- double [d2\\_](#)
- int [type\\_](#)  
*type (may be useful)*

#### Constructors, destructor<br>

**NOTE:** All constructors are protected.

There's no need to expose them, after all, this is an abstract class.

- virtual [~ClpPdcoBase](#) ()  
*Destructor (has to be public)*
- [ClpPdcoBase](#) ()  
*Default constructor.*
- **ClpPdcoBase** (const [ClpPdcoBase](#) &)
- [ClpPdcoBase](#) & **operator=** (const [ClpPdcoBase](#) &)

#### 3.44.1 Detailed Description

Abstract base class for tailoring everything for Pcd.

Since this class is abstract, no object of this type can be created.

If a derived class provides all methods then all ClpPcd algorithms should work.

Eventually we should be able to use [ClpObjective](#) and [ClpMatrixBase](#).

Definition at line 25 of file ClpPdcoBase.hpp.

#### 3.44.2 Constructor & Destructor Documentation

##### 3.44.2.1 [ClpPdcoBase::ClpPdcoBase](#) ( ) [protected]

Default constructor.

The documentation for this class was generated from the following file:


- [ClpPdcoBase.hpp](#)

### 3.45 ClpPlusMinusOneMatrix Class Reference


This implements a simple +- one matrix as derived from [ClpMatrixBase](#).

```
#include <ClpPlusMinusOneMatrix.hpp>
```

Inheritance diagram for ClpPlusMinusOneMatrix:



Collaboration diagram for ClpPlusMinusOneMatrix:



#### Public Member Functions

##### Useful methods

- virtual `CoinPackedMatrix *` [getPackedMatrix](#) () const  
*Return a complete CoinPackedMatrix.*
- virtual bool [isColOrdered](#) () const  
*Whether the packed matrix is column major ordered or not.*

- virtual CoinBigIndex [getNumElements](#) () const  
*Number of entries in the packed matrix.*
- virtual int [getNumCols](#) () const  
*Number of columns.*
- virtual int [getNumRows](#) () const  
*Number of rows.*
- virtual const double \* [getElements](#) () const  
*A vector containing the elements in the packed matrix.*
- virtual const int \* [getIndices](#) () const  
*A vector containing the minor indices of the elements in the packed matrix.*
- int \* [getMutableIndices](#) () const
- virtual const CoinBigIndex \* [getVectorStarts](#) () const
- virtual const int \* [getVectorLengths](#) () const  
*The lengths of the major-dimension vectors.*
- virtual void [deleteCols](#) (const int numDel, const int \*indDel)  
*Delete the columns whose indices are listed in indDel.*
- virtual void [deleteRows](#) (const int numDel, const int \*indDel)  
*Delete the rows whose indices are listed in indDel.*
- virtual void [appendCols](#) (int number, const CoinPackedVectorBase \*const \*columns)  
  
*Append Columns.*
- virtual void [appendRows](#) (int number, const CoinPackedVectorBase \*const \*rows)  
  
*Append Rows.*
- virtual int [appendMatrix](#) (int number, int type, const CoinBigIndex \*starts, const int \*index, const double \*element, int numberOther=-1)  
*Append a set of rows/columns to the end of the matrix.*
- virtual [ClpMatrixBase](#) \* [reverseOrderedCopy](#) () const  
*Returns a new matrix in reverse order without gaps.*
- virtual CoinBigIndex [countBasis](#) (const int \*whichColumn, int &numberColumn-Basic)  
  
*Returns number of elements in column part of basis.*
- virtual void [fillBasis](#) ([ClpSimplex](#) \*model, const int \*whichColumn, int &numberColumnBasic, int \*row, int \*start, int \*rowCount, int \*columnCount, CoinFactorizationDouble \*element)  
  
*Fills in column part of basis.*
- virtual CoinBigIndex \* [dubiousWeights](#) (const [ClpSimplex](#) \*model, int \*inputWeights) const  
  
*Given positive integer weights for each row fills in sum of weights for each column (and slack).*
- virtual void [rangeOfElements](#) (double &smallestNegative, double &largestNegative, double &smallestPositive, double &largestPositive)  
  
*Returns largest and smallest elements of both signs.*
- virtual void [unpack](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const  
  
*Unpacks a column into an CoinIndexedvector.*
- virtual void [unpackPacked](#) ([ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column) const  
  
*Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.*

- virtual void [add](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*rowArray, int column, double multiplier) const  
*Adds multiple of a column into an CoinIndexedvector You can use quickAdd to add to vector.*
- virtual void [add](#) (const [ClpSimplex](#) \*model, double \*array, int column, double multiplier) const  
*Adds multiple of a column into an array.*
- virtual void [releasePackedMatrix](#) () const  
*Allow any parts of a created CoinMatrix to be deleted.*
- virtual void [setDimensions](#) (int numRows, int numcols)  
*Set the dimensions of the matrix.*
- void [checkValid](#) (bool detail) const  
*Just checks matrix valid - will say if dimensions not quite right if detail.*

#### Matrix times vector methods

- virtual void [times](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + A * scalar * x$  in  $y$ .*
- virtual void [times](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale) const  
*And for scaling.*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y) const  
*Return  $y + x * scalar * A$  in  $y$ .*
- virtual void [transposeTimes](#) (double scalar, const double \*x, double \*y, const double \*rowScale, const double \*columnScale, double \*spare=NULL) const  
*And for scaling.*
- virtual void [transposeTimes](#) (const [ClpSimplex](#) \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const  
*Return  $x * scalar * A + y$  in  $z$ .*
- virtual void [transposeTimesByRow](#) (const [ClpSimplex](#) \*model, double scalar, const CoinIndexedVector \*x, CoinIndexedVector \*y, CoinIndexedVector \*z) const  
*Return  $x * scalar * A + y$  in  $z$ .*
- virtual void [subsetTransposeTimes](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*x, const CoinIndexedVector \*y, CoinIndexedVector \*z) const  
*Return  $x * A$  in  $z$  but just for indices in  $y$ .*
- virtual bool [canCombine](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*pi) const  
*Returns true if can combine transposeTimes and subsetTransposeTimes and if it would be faster.*
- virtual void [transposeTimes2](#) (const [ClpSimplex](#) \*model, const CoinIndexedVector \*pi1, CoinIndexedVector \*dj1, const CoinIndexedVector \*pi2, CoinIndexedVector \*spare, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)  
*Updates two arrays for steepest.*
- virtual void [subsetTimes2](#) (const [ClpSimplex](#) \*model, CoinIndexedVector \*dj1, const CoinIndexedVector \*pi2, CoinIndexedVector \*dj2, double referenceIn, double devex, unsigned int \*reference, double \*weights, double scaleFactor)  
*Updates second array for steepest and does devex weights.*

## Other

- CoinBigIndex \* [startPositive](#) () const  
*Return starts of +1s.*
- CoinBigIndex \* [startNegative](#) () const  
*Return starts of -1s.*

## Constructors, destructor

- [ClpPlusMinusOneMatrix](#) ()  
*Default constructor.*
- virtual [~ClpPlusMinusOneMatrix](#) ()  
*Destructor.*

## Copy method

- [ClpPlusMinusOneMatrix](#) (const [ClpPlusMinusOneMatrix](#) &)  
*The copy constructor.*
- [ClpPlusMinusOneMatrix](#) (const CoinPackedMatrix &)  
*The copy constructor from an CoinPlusMinusOneMatrix.*
- [ClpPlusMinusOneMatrix](#) (int numberOfRows, int numberColumns, bool columnOrdered, const int \*indices, const CoinBigIndex \*startPositive, const CoinBigIndex \*startNegative)  
*Constructor from arrays.*
- [ClpPlusMinusOneMatrix](#) (const [ClpPlusMinusOneMatrix](#) &wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns)  
*Subset constructor (without gaps).*
- [ClpPlusMinusOneMatrix](#) & **operator=** (const [ClpPlusMinusOneMatrix](#) &)
- virtual [ClpMatrixBase](#) \* [clone](#) () const  
*Clone.*
- virtual [ClpMatrixBase](#) \* [subsetClone](#) (int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns) const  
*Subset clone (without gaps).*
- void [passInCopy](#) (int numberOfRows, int numberColumns, bool columnOrdered, int \*indices, CoinBigIndex \*startPositive, CoinBigIndex \*startNegative)  
*pass in copy (object takes ownership)*
- virtual bool [canDoPartialPricing](#) () const  
*Says whether it can do partial pricing.*
- virtual void [partialPricing](#) ([ClpSimplex](#) \*model, double start, double end, int &bestSequence, int &numberWanted)  
*Partial pricing.*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- CoinPackedMatrix \* [matrix\\_](#)

*For fake CoinPackedMatrix.*

- int \* **lengths\_**
- CoinBigIndex \* **startPositive\_**  
*Start of +1's for each.*
- CoinBigIndex \* **startNegative\_**  
*Start of -1's for each.*
- int \* **indices\_**  
*Data -1, then +1 rows in pairs (row==-1 if one entry)*
- int **numberRows\_**  
*Number of rows.*
- int **numberColumns\_**  
*Number of columns.*
- bool **columnOrdered\_**  
*True if column ordered.*

### 3.45.1 Detailed Description

This implements a simple +- one matrix as derived from [ClpMatrixBase](#).

Definition at line 18 of file ClpPlusMinusOneMatrix.hpp.

### 3.45.2 Constructor & Destructor Documentation

#### 3.45.2.1 ClpPlusMinusOneMatrix::ClpPlusMinusOneMatrix ( )

Default constructor.

#### 3.45.2.2 ClpPlusMinusOneMatrix::ClpPlusMinusOneMatrix ( const ClpPlusMinusOneMatrix & )

The copy constructor.

#### 3.45.2.3 ClpPlusMinusOneMatrix::ClpPlusMinusOneMatrix ( const CoinPackedMatrix & )

The copy constructor from an CoinPlusMinusOneMatrix.

If not a valid matrix then getIndices will be NULL and startPositive[0] will have number of +1, startPositive[1] will have number of -1, startPositive[2] will have number of others,

#### 3.45.2.4 ClpPlusMinusOneMatrix::ClpPlusMinusOneMatrix ( const ClpPlusMinusOneMatrix & wholeModel, int numberOfRows, const int \* whichRows, int numberColumns, const int \* whichColumns )

Subset constructor (without gaps).

Duplicates are allowed and order is as given

### 3.45.3 Member Function Documentation

**3.45.3.1** `virtual bool ClpPlusMinusOneMatrix::isColOrdered ( ) const [virtual]`

Whether the packed matrix is column major ordered or not.

Implements [ClpMatrixBase](#).

**3.45.3.2** `virtual CoinBigIndex ClpPlusMinusOneMatrix::getNumElements ( ) const [virtual]`

Number of entries in the packed matrix.

Implements [ClpMatrixBase](#).

**3.45.3.3** `virtual int ClpPlusMinusOneMatrix::getNumCols ( ) const [inline, virtual]`

Number of columns.

Implements [ClpMatrixBase](#).

Definition at line 30 of file `ClpPlusMinusOneMatrix.hpp`.

**3.45.3.4** `virtual int ClpPlusMinusOneMatrix::getNumRows ( ) const [inline, virtual]`

Number of rows.

Implements [ClpMatrixBase](#).

Definition at line 34 of file `ClpPlusMinusOneMatrix.hpp`.

**3.45.3.5** `virtual const double* ClpPlusMinusOneMatrix::getElements ( ) const [virtual]`

A vector containing the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

**3.45.3.6** `virtual const int* ClpPlusMinusOneMatrix::getIndices ( ) const [inline, virtual]`

A vector containing the minor indices of the elements in the packed matrix.

Note that there might be gaps in this list, entries that do not belong to any major-dimension vector. To get the actual elements one should look at this vector together with `vectorStarts` and `vectorLengths`.

Implements [ClpMatrixBase](#).

Definition at line 48 of file `ClpPlusMinusOneMatrix.hpp`.

**3.45.3.7** `virtual const int* ClpPlusMinusOneMatrix::getVectorLengths ( ) const`  
`[virtual]`

The lengths of the major-dimension vectors.

Implements [ClpMatrixBase](#).

**3.45.3.8** `virtual void ClpPlusMinusOneMatrix::deleteCols ( const int numDel, const int * indDel`  
`) [virtual]`

Delete the columns whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.45.3.9** `virtual void ClpPlusMinusOneMatrix::deleteRows ( const int numDel, const int * indDel`  
`) [virtual]`

Delete the rows whose indices are listed in `indDel`.

Implements [ClpMatrixBase](#).

**3.45.3.10** `virtual int ClpPlusMinusOneMatrix::appendMatrix ( int number, int type, const`  
`CoinBigIndex * starts, const int * index, const double * element, int numberOther =`  
`-1 ) [virtual]`

Append a set of rows/columns to the end of the matrix.

Returns number of errors i.e. if any of the new rows/columns contain an index that's larger than the number of columns-1/rows-1 (if `numberOther>0`) or duplicates If 0 then rows, 1 if columns

Reimplemented from [ClpMatrixBase](#).

**3.45.3.11** `virtual CoinBigIndex* ClpPlusMinusOneMatrix::dubiousWeights ( const ClpSimplex`  
`* model, int * inputWeights ) const [virtual]`

Given positive integer weights for each row fills in sum of weights for each column (and slack).

Returns weights vector

Reimplemented from [ClpMatrixBase](#).

**3.45.3.12** `virtual void ClpPlusMinusOneMatrix::rangeOfElements ( double & smallestNegative,`  
`double & largestNegative, double & smallestPositive, double & largestPositive )`  
`[virtual]`

Returns largest and smallest elements of both signs.

Largest refers to largest absolute value.

Reimplemented from [ClpMatrixBase](#).

**3.45.3.13** `virtual void ClpPlusMinusOneMatrix::unpackPacked ( ClpSimplex * model,  
CoinIndexedVector * rowArray, int column ) const [virtual]`

Unpacks a column into an CoinIndexedvector in packed format Note that model is NOT const.

Bounds and objective could be modified if doing column generation (just for this variable)

Implements [ClpMatrixBase](#).

**3.45.3.14** `virtual void ClpPlusMinusOneMatrix::setDimensions ( int numRows, int numcols )  
[virtual]`

Set the dimensions of the matrix.

In effect, append new empty columns/rows to the matrix. A negative number for either dimension means that that dimension doesn't change. Otherwise the new dimensions MUST be at least as large as the current ones otherwise an exception is thrown.

Reimplemented from [ClpMatrixBase](#).

**3.45.3.15** `virtual void ClpPlusMinusOneMatrix::times ( double scalar, const double * x, double  
* y ) const [virtual]`

Return  $y + A * scalar * x$  in  $y$ .

#### Precondition

$x$  must be of size `numColumns()`  
 $y$  must be of size `numRows()`

Implements [ClpMatrixBase](#).

**3.45.3.16** `virtual void ClpPlusMinusOneMatrix::transposeTimes ( double scalar, const double *  
x, double * y ) const [virtual]`

Return  $y + x * scalar * A$  in  $y$ .

#### Precondition

$x$  must be of size `numRows()`  
 $y$  must be of size `numColumns()`

Implements [ClpMatrixBase](#).

**3.45.3.17** `virtual void ClpPlusMinusOneMatrix::transposeTimes ( const ClpSimplex *  
model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y,  
CoinIndexedVector * z ) const [virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#)

Implements [ClpMatrixBase](#).

**3.45.3.18** `virtual void ClpPlusMinusOneMatrix::transposeTimesByRow ( const ClpSimplex *  
model, double scalar, const CoinIndexedVector * x, CoinIndexedVector * y,  
CoinIndexedVector * z ) const [virtual]`

Return  $x * scalar * A + y$  in  $z$ .

Can use  $y$  as temporary array (will be empty at end) Note - If  $x$  packed mode - then  $z$  packed mode Squashes small elements and knows about [ClpSimplex](#). This version uses row copy

**3.45.3.19** `virtual void ClpPlusMinusOneMatrix::subsetTransposeTimes ( const ClpSimplex  
* model, const CoinIndexedVector * x, const CoinIndexedVector * y,  
CoinIndexedVector * z ) const [virtual]`

Return  $x * A$  in  $z$  but just for indices in  $y$ .

Note -  $z$  always packed mode

Implements [ClpMatrixBase](#).

**3.45.3.20** `virtual ClpMatrixBase* ClpPlusMinusOneMatrix::subsetClone ( int numberRows,  
const int * whichRows, int numberColumns, const int * whichColumns ) const  
[virtual]`

Subset clone (without gaps).

Duplicates are allowed and order is as given

Reimplemented from [ClpMatrixBase](#).

The documentation for this class was generated from the following file:


- `ClpPlusMinusOneMatrix.hpp`

## 3.46 ClpPredictorCorrector Class Reference


This solves LPs using the predictor-corrector method due to Mehrotra.

```
#include <ClpPredictorCorrector.hpp>
```

Inheritance diagram for ClpPredictorCorrector:



Collaboration diagram for ClpPredictorCorrector:



## Public Member Functions

## Description of algorithm

- int `solve` ()  
*Primal Dual Predictor Corrector algorithm.*

## Functions used in algorithm

- CoinWorkDouble `findStepLength` (int phase)  
*findStepLength.*
- CoinWorkDouble `findDirectionVector` (const int phase)  
*findDirectionVector.*
- int `createSolution` ()  
*createSolution. Creates solution from scratch (- code if no memory)*
- CoinWorkDouble `complementarityGap` (int &numberComplementarityPairs, int &numberComplementarityItems, const int phase)  
*complementarityGap. Computes gap*
- void `setupForSolve` (const int phase)  
*setupForSolve.*
- void `solveSystem` (CoinWorkDouble \*region1, CoinWorkDouble \*region2, const CoinWorkDouble \*region1In, const CoinWorkDouble \*region2In, const CoinWorkDouble \*saveRegion1, const CoinWorkDouble \*saveRegion2, bool gentleRefine)  
*Does solve.*
- bool `checkGoodMove` (const bool doCorrector, CoinWorkDouble &bestNextGap, bool allowIncreasingGap)  
*sees if looks plausible change in complementarity*
- bool `checkGoodMove2` (CoinWorkDouble move, CoinWorkDouble &bestNextGap, bool allowIncreasingGap)  
*: checks for one step size*
- int `updateSolution` (CoinWorkDouble nextGap)  
*updateSolution. Updates solution at end of iteration*
- CoinWorkDouble `affineProduct` ()  
*Save info on products of affine  $\delta T * \delta W$  and  $\delta S * \delta Z$ .*
- void `debugMove` (int phase, CoinWorkDouble primalStep, CoinWorkDouble dualStep)  
*See exactly what would happen given current deltas.*

## 3.46.1 Detailed Description

This solves LPs using the predictor-corrector method due to Mehrotra.

It also uses multiple centrality corrections as in Gondzio.

See; S. Mehrotra, "On the implementation of a primal-dual interior point method", SIAM Journal on optimization, 2 (1992) J. Gondzio, "Multiple centrality corrections in a primal-dual method for linear programming", Computational Optimization and Applications", 6 (1996)

It is rather basic as Interior point is not my speciality

It inherits from [ClpInterior](#). It has no data of its own and is never created - only cast from a [ClpInterior](#) object at algorithm time.

It can also solve QPs

Definition at line 37 of file ClpPredictorCorrector.hpp.

### 3.46.2 Member Function Documentation

#### 3.46.2.1 int ClpPredictorCorrector::solve ( )

Primal Dual Predictor Corrector algorithm.

Method

Big TODO

**3.46.2.2** void ClpPredictorCorrector::solveSystem ( CoinWorkDouble \* *region1*,  
CoinWorkDouble \* *region2*, const CoinWorkDouble \* *region1In*, const  
CoinWorkDouble \* *region2In*, const CoinWorkDouble \* *saveRegion1*, const  
CoinWorkDouble \* *saveRegion2*, bool *gentleRefine* )

Does solve.

region1 is for deltaX (columns+rows), region2 for deltaPi (rows)

The documentation for this class was generated from the following file:


- ClpPredictorCorrector.hpp

## 3.47 ClpPresolve Class Reference

This is the Clp interface to CoinPresolve.

```
#include <ClpPresolve.hpp>
```

Collaboration diagram for ClpPresolve:



## Public Member Functions

### Main Constructor, destructor

- `ClpPresolve ()`  
*Default constructor.*
- `virtual ~ClpPresolve ()`  
*Virtual destructor.*

**presolve** - presolves a model, transforming the model

and saving information in the `ClpPresolve` object needed for postsolving.

*This underlying (protected) method is virtual; the idea is that in the future, one could override this method to customize how the various presolve techniques are applied.*

*This version of presolve returns a pointer to a new presolved model. NULL if infeasible or unbounded. This should be paired with postsolve below. The advantage of going back to original model is that it will be exactly as it was i.e. 0.0 will not become 1.0e-19. If keepIntegers is true then bounds may be tightened in original. Bounds will be moved by up to feasibilityTolerance to try and stay feasible. Names will be dropped in presolved model if asked*

- **ClpSimplex \* presolvedModel** (**ClpSimplex** &si, double feasibilityTolerance=0.0, bool keepIntegers=true, int numberPasses=5, bool dropNames=false, bool doRowObjective=false)
- int **presolvedModelToFile** (**ClpSimplex** &si, std::string fileName, double feasibilityTolerance=0.0, bool keepIntegers=true, int numberPasses=5, bool dropNames=false, bool doRowObjective=false)

*This version saves data in a file.*

- `ClpSimplex * model () const`  
*Return pointer to presolved model, Up to user to destroy.*
- `ClpSimplex * originalModel () const`  
*Return pointer to original model.*
- `void setOriginalModel (ClpSimplex *model)`  
*Set pointer to original model.*
- `const int * originalColumns () const`  
*return pointer to original columns*
- `const int * originalRows () const`  
*return pointer to original rows*
- `void setNonLinearValue (double value)`  
*"Magic" number.*
- `double nonLinearValue () const`
- `bool doDual () const`  
*Whether we want to do dual part of presolve.*
- `void setDoDual (bool doDual)`
- `bool doSingleton () const`  
*Whether we want to do singleton part of presolve.*
- `void setDoSingleton (bool doSingleton)`
- `bool doDoubleton () const`  
*Whether we want to do doubleton part of presolve.*
- `void setDoDoubleton (bool doDoubleton)`
- `bool doTripletion () const`  
*Whether we want to do tripletion part of presolve.*
- `void setDoTripletion (bool doTripletion)`
- `bool doTighten () const`  
*Whether we want to do tighten part of presolve.*
- `void setDoTighten (bool doTighten)`
- `bool doForcing () const`  
*Whether we want to do forcing part of presolve.*
- `void setDoForcing (bool doForcing)`
- `bool doImpliedFree () const`  
*Whether we want to do impliedfree part of presolve.*
- `void setDoImpliedFree (bool doImpliedfree)`
- `bool doDupcol () const`  
*Whether we want to do dupcol part of presolve.*
- `void setDoDupcol (bool doDupcol)`
- `bool doDuprow () const`  
*Whether we want to do duprow part of presolve.*
- `void setDoDuprow (bool doDuprow)`
- `bool doSingletonColumn () const`  
*Whether we want to do singleton column part of presolve.*
- `void setDoSingletonColumn (bool doSingleton)`
- `bool doGubrow () const`  
*Whether we want to do gubrow part of presolve.*
- `void setDoGubrow (bool doGubrow)`
- `int presolveActions () const`  
*Set whole group.*
- `void setPresolveActions (int action)`
- `void setSubstitution (int value)`  
*Substitution level.*
- `void statistics ()`  
*Asks for statistics.*
- `int presolveStatus () const`  
*Return presolve status (0,1,2)*

**postsolve** - postsolve the problem. If the problem

*has not been solved to optimality, there are no guarantees.*

*If you are using an algorithm like simplex that has a concept of "basic" rows/cols, then set `updateStatus`*

*Note that if you modified the original problem after presolving, then you must "undo" these modifications before calling `postsolve`. This version updates original*

- virtual void **postsolve** (bool `updateStatus`=true)
- void `destroyPresolve` ()

*Gets rid of presolve actions (e.g. when infeasible)*

**private or protected data**

- virtual const CoinPresolveAction \* `presolve` (CoinPresolveMatrix \*`prob`)  
*If you want to apply the individual presolve routines differently, or perhaps add your own to the mix, define a derived class and override this method.*
- virtual void `postsolve` (CoinPostsolveMatrix &`prob`)  
*Postsolving is pretty generic; just apply the transformations in reverse order.*
- virtual `ClpSimplex` \* `gutsOfPresolvedModel` (`ClpSimplex` \*`originalModel`, double `feasibilityTolerance`, bool `keepIntegers`, int `numberPasses`, bool `dropNames`, bool `doRowObjective`)  
*This is main part of Presolve.*

### 3.47.1 Detailed Description

This is the Clp interface to CoinPresolve.

Definition at line 15 of file `ClpPresolve.hpp`.

### 3.47.2 Member Function Documentation

**3.47.2.1** int `ClpPresolve::presolvedModelToFile` ( `ClpSimplex` & *si*, std::string *fileName*, double *feasibilityTolerance* = 0.0, bool *keepIntegers* = true, int *numberPasses* = 5, bool *dropNames* = false, bool *doRowObjective* = false )

This version saves data in a file.

The passed in model is updated to be presolved model. Returns non-zero if infeasible

**3.47.2.2** void `ClpPresolve::setNonLinearValue` ( double *value* ) [inline]

"Magic" number.

If this is non-zero then any elements with this value may change and so presolve is very limited in what can be done to the row and column. This is for non-linear problems.

Definition at line 74 of file `ClpPresolve.hpp`.

3.47.2.3 `virtual void ClpPresolve::postsolve ( CoinPostsolveMatrix & prob )`  
[protected, virtual]

Postsolving is pretty generic; just apply the transformations in reverse order.

You will probably only be interested in overriding this method if you want to add code to test for consistency while debugging new presolve techniques.

The documentation for this class was generated from the following file:


- ClpPresolve.hpp

### 3.48 ClpPrimalColumnDantzig Class Reference


Primal Column Pivot Dantzig Algorithm Class.

```
#include <ClpPrimalColumnDantzig.hpp>
```

Inheritance diagram for ClpPrimalColumnDantzig:



Collaboration diagram for ClpPrimalColumnDantzig:



## Public Member Functions

## Algorithmic methods

- virtual int **pivotColumn** (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow1, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Returns pivot column, -1 if none.*
- virtual void **saveWeights** (ClpSimplex \*model, int)  
*Just sets model.*

## Constructors and destructors

- `ClpPrimalColumnDantzig ()`  
*Default Constructor.*

- [ClpPrimalColumnDantzig](#) (const [ClpPrimalColumnDantzig](#) &)  
*Copy constructor.*
- [ClpPrimalColumnDantzig](#) & [operator=](#) (const [ClpPrimalColumnDantzig](#) &rhs)  
*Assignment operator.*
- virtual [~ClpPrimalColumnDantzig](#) ()  
*Destructor.*
- virtual [ClpPrimalColumnPivot](#) \* [clone](#) (bool copyData=true) const  
*Clone.*

#### 3.48.1 Detailed Description

Primal Column Pivot Dantzig Algorithm Class.

This is simplest choice - choose largest infeasibility

Definition at line 19 of file [ClpPrimalColumnDantzig.hpp](#).

#### 3.48.2 Member Function Documentation

- 3.48.2.1 virtual int [ClpPrimalColumnDantzig::pivotColumn](#) ( [CoinIndexedVector](#) \* *updates*,  
[CoinIndexedVector](#) \* *spareRow1*, [CoinIndexedVector](#) \* *spareRow2*, [CoinIndexedVector](#)  
\* *spareColumn1*, [CoinIndexedVector](#) \* *spareColumn2* ) [virtual]

Returns pivot column, -1 if none.

Lumbers over all columns - slow The Packed [CoinIndexedVector](#) updates has cost updates - for normal LP that is just +-weight where a feasibility changed. It also has reduced cost from last iteration in pivot row Can just do full price if you really want to be slow

Implements [ClpPrimalColumnPivot](#).

The documentation for this class was generated from the following file:


- [ClpPrimalColumnDantzig.hpp](#)

### 3.49 ClpPrimalColumnPivot Class Reference


Primal Column Pivot Abstract Base Class.

```
#include <ClpPrimalColumnPivot.hpp>
```

Inheritance diagram for ClpPrimalColumnPivot:



Collaboration diagram for ClpPrimalColumnPivot:



## Public Member Functions

## Algorithmic methods

- virtual int [pivotColumn](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow1, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)=0  
*Returns pivot column, -1 if none.*
- virtual void [updateWeights](#) (CoinIndexedVector \*input)  
*Updates weights - part 1 (may be empty)*
- virtual void [saveWeights](#) ([ClpSimplex](#) \*model, int mode)=0  
*Saves any weights round factorization as pivot rows may change Will be empty unless steepest edge (will save model) May also recompute infeasibility stuff 1) before factorization 2) after good factorization (if weights empty may initialize) 3) after something happened but no factorization (e.g.*
- virtual int [pivotRow](#) (double &way)  
*Signals pivot row choice:*
- virtual void [clearArrays](#) ()  
*Gets rid of all arrays (may be empty)*
- virtual bool [looksOptimal](#) () const  
*Returns true if would not find any column.*
- virtual void [setLooksOptimal](#) (bool flag)  
*Sets optimality flag (for advanced use)*

## Constructors and destructors

- [ClpPrimalColumnPivot](#) ()  
*Default Constructor.*
- [ClpPrimalColumnPivot](#) (const [ClpPrimalColumnPivot](#) &)  
*Copy constructor.*
- [ClpPrimalColumnPivot](#) & [operator=](#) (const [ClpPrimalColumnPivot](#) &rhs)  
*Assignment operator.*
- virtual [~ClpPrimalColumnPivot](#) ()  
*Destructor.*
- virtual [ClpPrimalColumnPivot](#) \* [clone](#) (bool copyData=true) const =0  
*Clone.*

## Other

- [ClpSimplex](#) \* [model](#) ()  
*Returns model.*
- void [setModel](#) ([ClpSimplex](#) \*newmodel)  
*Sets model.*
- int [type](#) ()  
*Returns type (above 63 is extra information)*
- virtual int [numberSprintColumns](#) (int &numberIterations) const  
*Returns number of extra columns for sprint algorithm - 0 means off.*
- virtual void [switchOffSprint](#) ()  
*Switch off sprint idea.*
- virtual void [maximumPivotsChanged](#) ()  
*Called when maximum pivots changes.*

## Protected Attributes

## Protected member data

- [ClpSimplex](#) \* [model\\_](#)  
*Pointer to model.*
- int [type\\_](#)  
*Type of column pivot algorithm.*
- bool [looksOptimal\\_](#)  
*Says if looks optimal (normally computed)*

## 3.49.1 Detailed Description

Primal Column Pivot Abstract Base Class.

Abstract Base Class for describing an interface to an algorithm to choose column pivot in primal simplex algorithm. For some algorithms e.g. Dantzig choice then some functions may be null. For Dantzig the only one of any importance is pivotColumn.

If you wish to inherit from this look at ClpPrimalColumnDantzig.cpp as that is simplest version.

Definition at line 25 of file ClpPrimalColumnPivot.hpp.

## 3.49.2 Member Function Documentation

**3.49.2.1** `virtual int ClpPrimalColumnPivot::pivotColumn ( CoinIndexedVector * updates, CoinIndexedVector * spareRow1, CoinIndexedVector * spareRow2, CoinIndexedVector * spareColumn1, CoinIndexedVector * spareColumn2 ) [pure virtual]`

Returns pivot column, -1 if none.

Normally updates reduced costs using result of last iteration before selecting incoming column.

The Packed CoinIndexedVector updates has cost updates - for normal LP that is just +-weight where a feasibility changed. It also has reduced cost from last iteration in pivot row

Inside pivotColumn the pivotRow\_ and reduced cost from last iteration are also used.

So in the simplest case i.e. feasible we compute the row of the tableau corresponding to last pivot and add a multiple of this to current reduced costs.

We can use other arrays to help updates

Implemented in [ClpPrimalColumnDantzig](#), [ClpPrimalColumnSteepest](#), and [ClpPrimalQuadraticDantzig](#).

**3.49.2.2** `virtual void ClpPrimalColumnPivot::saveWeights ( ClpSimplex * model, int mode ) [pure virtual]`

Saves any weights round factorization as pivot rows may change Will be empty unless steepest edge (will save model) May also recompute infeasibility stuff 1) before factor-

ization 2) after good factorization (if weights empty may initialize) 3) after something happened but no factorization (e.g.

check for infeasible) 4) as 2 but restore weights from previous snapshot 5) forces some initialization e.g. weights Also sets model

Implemented in [ClpPrimalColumnDantzig](#), [ClpPrimalColumnSteepest](#), and [ClpPrimalQuadraticDantzig](#).

```
3.49.2.3 virtual int ClpPrimalColumnPivot::pivotRow ( double & way ) [inline,
virtual]
```

Signals pivot row choice:

-2 (default) - use normal pivot row choice -1 to numberRows-1 - use this (will be checked) way should be -1 to go to lower bound, +1 to upper bound

Definition at line 76 of file [ClpPrimalColumnPivot.hpp](#).

```
3.49.2.4 virtual int ClpPrimalColumnPivot::numberSprintColumns ( int & numberIterations )
const [virtual]
```

Returns number of extra columns for sprint algorithm - 0 means off.

Also number of iterations before recompute

Reimplemented in [ClpPrimalColumnSteepest](#).

The documentation for this class was generated from the following file:


- [ClpPrimalColumnPivot.hpp](#)

### 3.50 ClpPrimalColumnSteepest Class Reference


Primal Column Pivot Steepest Edge Algorithm Class.

```
#include <ClpPrimalColumnSteepest.hpp>
```

Inheritance diagram for ClpPrimalColumnSteepest:



Collaboration diagram for ClpPrimalColumnSteepest:



## Public Types

- enum Persistence
  - enums for persistence*

## Public Member Functions

## Algorithmic methods

- virtual int **pivotColumn** (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow1, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Returns pivot column, -1 if none.*

- int [pivotColumnOldMethod](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow1, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*For quadratic or funny nonlinearities.*
- void [justDjs](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Just update djs.*
- int [partialPricing](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, int numberWanted, int numberLook)  
*Update djs doing partial pricing (dantzig)*
- void [djsAndDevex](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Update djs, weights for Devex using djs.*
- void [djsAndSteepest](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Update djs, weights for Steepest using djs.*
- void [djsAndDevex2](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Update djs, weights for Devex using pivot row.*
- void [djsAndSteepest2](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Update djs, weights for Steepest using pivot row.*
- void [justDevex](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Update weights for Devex.*
- void [justSteepest](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Update weights for Steepest.*
- void [transposeTimes2](#) (const CoinIndexedVector \*pi1, CoinIndexedVector \*dj1, const CoinIndexedVector \*pi2, CoinIndexedVector \*dj2, CoinIndexedVector \*spare, double scaleFactor)  
*Updates two arrays for steepest.*
- virtual void [updateWeights](#) (CoinIndexedVector \*input)  
*Updates weights - part 1 - also checks accuracy.*
- void [checkAccuracy](#) (int sequence, double relativeTolerance, CoinIndexedVector \*rowArray1, CoinIndexedVector \*rowArray2)  
*Checks accuracy - just for debug.*
- void [initializeWeights](#) ()  
*Initialize weights.*
- virtual void [saveWeights](#) (ClpSimplex \*model, int mode)  
*Save weights - this may initialize weights as well mode is - 1) before factorization 2) after factorization 3) just redo infeasibilities 4) restore weights 5) at end of values pass (so need initialization)*
- virtual void [unrollWeights](#) ()  
*Gets rid of last update.*
- virtual void [clearArrays](#) ()  
*Gets rid of all arrays.*
- virtual bool [looksOptimal](#) () const  
*Returns true if would not find any column.*
- virtual void [maximumPivotsChanged](#) ()  
*Called when maximum pivots changes.*

## gets and sets

- int `mode` () const  
*Mode.*
- virtual int `numberSprintColumns` (int &numberIterations) const  
*Returns number of extra columns for sprint algorithm - 0 means off.*
- virtual void `switchOffSprint` ()  
*Switch off sprint idea.*

## Constructors and destructors

- `ClpPrimalColumnSteepest` (int mode=3)  
*Default Constructor 0 is exact devex, 1 full steepest, 2 is partial exact devex 3 switches between 0 and 2 depending on factorization 4 starts as partial dantzig/devex but then may switch between 0 and 2.*
- `ClpPrimalColumnSteepest` (const `ClpPrimalColumnSteepest` &rhs)  
*Copy constructor.*
- `ClpPrimalColumnSteepest` & `operator=` (const `ClpPrimalColumnSteepest` &rhs)  
*Assignment operator.*
- virtual `~ClpPrimalColumnSteepest` ()  
*Destructor.*
- virtual `ClpPrimalColumnPivot` \* `clone` (bool copyData=true) const  
*Clone.*

## Private functions to deal with devex

- bool `reference` (int i) const  
*reference would be faster using ClpSimplex's status\_, but I prefer to keep modularity.*
- void `setReference` (int i, bool trueFalse)
- void `setPersistence` (`Persistence` life)  
*Set/ get persistence.*
- `Persistence` `persistence` () const

## 3.50.1 Detailed Description

Primal Column Pivot Steepest Edge Algorithm Class.

See Forrest-Goldfarb paper for algorithm

Definition at line 23 of file `ClpPrimalColumnSteepest.hpp`.

## 3.50.2 Constructor &amp; Destructor Documentation

3.50.2.1 `ClpPrimalColumnSteepest::ClpPrimalColumnSteepest ( int mode = 3 )`

Default Constructor 0 is exact devex, 1 full steepest, 2 is partial exact devex 3 switches between 0 and 2 depending on factorization 4 starts as partial dantzig/devex but then may switch between 0 and 2.

By partial exact devex is meant that the weights are updated as normal but only part of the nonbasic variables are scanned. This can be faster on very easy problems.

## 3.50.3 Member Function Documentation

3.50.3.1 `virtual int ClpPrimalColumnSteepest::pivotColumn ( CoinIndexedVector * updates,  
CoinIndexedVector * spareRow1, CoinIndexedVector * spareRow2, CoinIndexedVector  
* spareColumn1, CoinIndexedVector * spareColumn2 ) [virtual]`

Returns pivot column, -1 if none.

The Packed CoinIndexedVector updates has cost updates - for normal LP that is just +-weight where a feasibility changed. It also has reduced cost from last iteration in pivot row Parts of operation split out into separate functions for profiling and speed

Implements [ClpPrimalColumnPivot](#).

3.50.3.2 `virtual int ClpPrimalColumnSteepest::numberSprintColumns ( int & numberIterations )  
const [virtual]`

Returns number of extra columns for sprint algorithm - 0 means off.

Also number of iterations before recompute

Reimplemented from [ClpPrimalColumnPivot](#).

The documentation for this class was generated from the following file:


- `ClpPrimalColumnSteepest.hpp`

## 3.51 ClpPrimalQuadraticDantzig Class Reference


Primal Column Pivot Dantzig Algorithm Class.

```
#include <ClpPrimalQuadraticDantzig.hpp>
```

Inheritance diagram for ClpPrimalQuadraticDantzig:



Collaboration diagram for ClpPrimalQuadraticDantzig:



## Public Member Functions

## Algorithmic methods

- virtual int [pivotColumn](#) (CoinIndexedVector \*updates, CoinIndexedVector \*spareRow1, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Returns pivot column, -1 if none.*
- virtual void [saveWeights](#) (ClpSimplex \*model, int mode)  
*Just sets model.*

## Constructors and destructors

- `ClpPrimalQuadraticDantzig ()`  
*Default Constructor.*

- [ClpPrimalQuadraticDantzig](#) (const [ClpPrimalQuadraticDantzig](#) &)  
*Copy constructor.*
- [ClpPrimalQuadraticDantzig](#) (ClpSimplexPrimalQuadratic \*model, ClpQuadraticInfo \*info)  
*Constructor from model.*
- [ClpPrimalQuadraticDantzig](#) & operator= (const [ClpPrimalQuadraticDantzig](#) &rhs)  
*Assignment operator.*
- virtual ~[ClpPrimalQuadraticDantzig](#) ()  
*Destructor.*
- virtual [ClpPrimalColumnPivot](#) \* clone (bool copyData=true) const  
*Clone.*

### 3.51.1 Detailed Description

Primal Column Pivot Dantzig Algorithm Class.

This is simplest choice - choose largest infeasibility

Definition at line 20 of file ClpPrimalQuadraticDantzig.hpp.

### 3.51.2 Member Function Documentation

3.51.2.1 virtual int ClpPrimalQuadraticDantzig::pivotColumn ( CoinIndexedVector \* updates, CoinIndexedVector \* spareRow1, CoinIndexedVector \* spareRow2, CoinIndexedVector \* spareColumn1, CoinIndexedVector \* spareColumn2 ) [virtual]

Returns pivot column, -1 if none.

Lumbers over all columns - slow updateArray has cost updates (also use pivotRow\_ from last iteration) Can just do full price if you really want to be slow

Implements [ClpPrimalColumnPivot](#).

The documentation for this class was generated from the following file:


- ClpPrimalQuadraticDantzig.hpp

## 3.52 ClpQuadraticObjective Class Reference


Quadratic Objective Class.

```
#include <ClpQuadraticObjective.hpp>
```

Inheritance diagram for ClpQuadraticObjective:



Collaboration diagram for ClpQuadraticObjective:



### Public Member Functions

#### Stuff

- virtual double \* [gradient](#) (const [ClpSimplex](#) \*model, const double \*solution, double &offset, bool refresh, int includeLinear=2)  
*Returns gradient.*
- virtual double [reducedGradient](#) ([ClpSimplex](#) \*model, double \*region, bool useFeasibleCosts)  
*Resize objective.*
- virtual double [stepLength](#) ([ClpSimplex](#) \*model, const double \*solution, const double \*change, double maximumTheta, double &currentObj, double &predictedObj, double &thetaObj)

*Returns step length which gives minimum of objective for solution + theta \* change vector up to maximum theta.*

- virtual double [objectiveValue](#) (const [ClpSimplex](#) \*model, const double \*solution) const

*Return objective value (without any [ClpModel](#) offset) (model may be NULL)*

- virtual void [resize](#) (int newNumberColumns)

*Resize objective.*

- virtual void [deleteSome](#) (int numberToDelete, const int \*which)

*Delete columns in objective.*

- virtual void [reallyScale](#) (const double \*columnScale)

*Scale objective.*

- virtual int [markNonlinear](#) (char \*which)

*Given a zeroed array sets nonlinear columns to 1.*

#### Constructors and destructors

- [ClpQuadraticObjective](#) ()

*Default Constructor.*

- [ClpQuadraticObjective](#) (const double \*linearObjective, int numberColumns, const CoinBigIndex \*start, const int \*column, const double \*element, int numberExtendedColumns\_ = -1)

*Constructor from objective.*

- [ClpQuadraticObjective](#) (const [ClpQuadraticObjective](#) &rhs, int type=0)

*Copy constructor .*

- [ClpQuadraticObjective](#) (const [ClpQuadraticObjective](#) &rhs, int numberColumns, const int \*whichColumns)

*Subset constructor.*

- [ClpQuadraticObjective](#) & [operator=](#) (const [ClpQuadraticObjective](#) &rhs)

*Assignment operator.*

- virtual [~ClpQuadraticObjective](#) ()

*Destructor.*

- virtual [ClpObjective](#) \* [clone](#) () const

*Clone.*

- virtual [ClpObjective](#) \* [subsetClone](#) (int numberColumns, const int \*whichColumns) const

*Subset clone.*

- void [loadQuadraticObjective](#) (const int numberColumns, const CoinBigIndex \*start, const int \*column, const double \*element, int numberExtendedColumns=-1)

*Load up quadratic objective.*

- void [loadQuadraticObjective](#) (const CoinPackedMatrix &matrix)

- void [deleteQuadraticObjective](#) ()

*Get rid of quadratic objective.*

#### Gets and sets

- CoinPackedMatrix \* [quadraticObjective](#) () const

*Quadratic objective.*

- double \* [linearObjective](#) () const

*Linear objective.*

- int [numberExtendedColumns](#) () const  
*Length of linear objective which could be bigger.*
- int [numberColumns](#) () const  
*Number of columns in quadratic objective.*
- bool [fullMatrix](#) () const  
*If a full or half matrix.*

### 3.52.1 Detailed Description

Quadratic Objective Class.

Definition at line 18 of file ClpQuadraticObjective.hpp.

### 3.52.2 Constructor & Destructor Documentation

**3.52.2.1** `ClpQuadraticObjective::ClpQuadraticObjective ( const ClpQuadraticObjective & rhs, int type = 0 )`

Copy constructor .

If type is -1 then make sure half symmetric, if +1 then make sure full

**3.52.2.2** `ClpQuadraticObjective::ClpQuadraticObjective ( const ClpQuadraticObjective & rhs, int numberColumns, const int * whichColumns )`

Subset constructor.

Duplicates are allowed and order is as given.

### 3.52.3 Member Function Documentation

**3.52.3.1** `virtual double* ClpQuadraticObjective::gradient ( const ClpSimplex * model, const double * solution, double & offset, bool refresh, int includeLinear = 2 )`  
[virtual]

Returns gradient.

If Quadratic then solution may be NULL, also returns an offset (to be added to current one) If refresh is false then uses last solution Uses model for scaling includeLinear 0 - no, 1 as is, 2 as feasible

Implements [ClpObjective](#).

**3.52.3.2** `virtual double ClpQuadraticObjective::reducedGradient ( ClpSimplex * model, double * region, bool useFeasibleCosts )` [virtual]

Resize objective.

Returns reduced gradient.Returns an offset (to be added to current one).

Implements [ClpObjective](#).

3.52.3.3 `virtual double ClpQuadraticObjective::stepLength ( ClpSimplex * model, const double * solution, const double * change, double maximumTheta, double & currentObj, double & predictedObj, double & thetaObj ) [virtual]`

Returns step length which gives minimum of objective for solution + theta \* change vector up to maximum theta.

arrays are numberColumns+numberRows Also sets current objective, predicted and at maximumTheta

Implements [ClpObjective](#).

3.52.3.4 `virtual int ClpQuadraticObjective::markNonlinear ( char * which ) [virtual]`

Given a zeroed array sets nonlinear columns to 1.

Returns number of nonlinear columns

Reimplemented from [ClpObjective](#).

3.52.3.5 `virtual ClpObjective* ClpQuadraticObjective::subsetClone ( int numberColumns, const int * whichColumns ) const [virtual]`

Subset clone.

Duplicates are allowed and order is as given.

Reimplemented from [ClpObjective](#).

3.52.3.6 `void ClpQuadraticObjective::loadQuadraticObjective ( const int numberColumns, const CoinBigIndex * start, const int * column, const double * element, int numberExtendedColumns = -1 )`

Load up quadratic objective.

This is stored as a CoinPackedMatrix

The documentation for this class was generated from the following file:


- `ClpQuadraticObjective.hpp`

### 3.53 ClpSimplex Class Reference


This solves LPs using the simplex method.

```
#include <ClpSimplex.hpp>
```

Inheritance diagram for ClpSimplex:



Collaboration diagram for ClpSimplex:



## Public Types

- enum **Status**  
*enums for status of various sorts.*

## Public Member Functions

## Constructors and destructor and copy

- **ClpSimplex** (bool emptyMessages=false)

*Default constructor.*

- [ClpSimplex](#) (const [ClpSimplex](#) &rhs, int scalingMode=-1)

*Copy constructor.*

- [ClpSimplex](#) (const [ClpModel](#) &rhs, int scalingMode=-1)

*Copy constructor from model.*

- [ClpSimplex](#) (const [ClpModel](#) \*wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns, bool dropNames=true, bool dropIntegers=true, bool fixOthers=false)

*Subproblem constructor.*

- [ClpSimplex](#) (const [ClpSimplex](#) \*wholeModel, int numberOfRows, const int \*whichRows, int numberColumns, const int \*whichColumns, bool dropNames=true, bool dropIntegers=true, bool fixOthers=false)

*Subproblem constructor.*

- [ClpSimplex](#) ([ClpSimplex](#) \*wholeModel, int numberColumns, const int \*whichColumns)

*This constructor modifies original [ClpSimplex](#) and stores original stuff in created [ClpSimplex](#).*

- void [originalModel](#) ([ClpSimplex](#) \*miniModel)

*This copies back stuff from miniModel and then deletes miniModel.*

- void [setPersistenceFlag](#) (int value)

*Array persistence flag If 0 then as now (delete/new) 1 then only do arrays if bigger needed 2 as 1 but give a bit extra if bigger needed.*

- void [makeBaseModel](#) ()

*Save a copy of model with certain state - normally without cuts.*

- void [deleteBaseModel](#) ()

*Switch off base model.*

- [ClpSimplex](#) \* [baseModel](#) () const

*See if we have base model.*

- void [setToBaseModel](#) ([ClpSimplex](#) \*model=NULL)

*Reset to base model (just size and arrays needed) If model NULL use internal copy.*

- [ClpSimplex](#) & [operator=](#) (const [ClpSimplex](#) &rhs)

*Assignment operator. This copies the data.*

- [~ClpSimplex](#) ()

*Destructor.*

- void [loadProblem](#) (const [ClpMatrixBase](#) &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)

*Loads a problem (the constraints on the rows are given by lower and upper bounds).*

- void [loadProblem](#) (const [CoinPackedMatrix](#) &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)

- void [loadProblem](#) (const int numcols, const int numRows, const [CoinBigIndex](#) \*start, const int \*index, const double \*value, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)

*Just like the other [loadProblem\(\)](#) method except that the matrix is given in a standard column major ordered format (without gaps).*

- void [loadProblem](#) (const int numcols, const int numRows, const [CoinBigIndex](#) \*start, const int \*index, const double \*value, const int \*length, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub, const double \*rowObjective=NULL)

*This one is for after presolve to save memory.*

- int [loadProblem](#) (CoinModel &modelObject, bool keepSolution=false)

*This loads a model from a coinModel object - returns number of errors.*

- int [readMps](#) (const char \*filename, bool keepNames=false, bool ignoreErrors=false)

*Read an mps file from the given filename.*

- int [readGMPL](#) (const char \*filename, const char \*dataName, bool keepNames=false)

*Read GMPL files from the given filenames.*

- int [readLp](#) (const char \*filename, const double epsilon=1e-5)

*Read file in LP format from file with name filename.*

- void [borrowModel](#) (ClpModel &otherModel)

*Borrow model.*

- void [borrowModel](#) (ClpSimplex &otherModel)
- void [passInEventHandler](#) (const ClpEventHandler \*eventHandler)

*Pass in Event handler (cloned and deleted at end)*

- void [getbackSolution](#) (const ClpSimplex &smallModel, const int \*whichRow, const int \*whichColumn)

*Puts solution back into small model.*

- int [loadNonLinear](#) (void \*info, int &numberConstraints, ClpConstraint \*\*&constraints)

*Load nonlinear part of problem from AMPL info Returns 0 if linear 1 if quadratic objective 2 if quadratic constraints 3 if nonlinear objective 4 if nonlinear constraints.*

#### Functions most useful to user

- int [initialSolve](#) (ClpSolve &options)

*General solve algorithm which can do presolve.*

- int [initialSolve](#) ()

*Default initial solve.*

- int [initialDualSolve](#) ()

*Dual initial solve.*

- int [initialPrimalSolve](#) ()

*Primal initial solve.*

- int [initialBarrierSolve](#) ()

*Barrier initial solve.*

- int [initialBarrierNoCrossSolve](#) ()

*Barrier initial solve, not to be followed by crossover.*

- int [dual](#) (int ifValuesPass=0, int startFinishOptions=0)

*Dual algorithm - see [ClpSimplexDual.hpp](#) for method.*

- int [dualDebug](#) (int ifValuesPass=0, int startFinishOptions=0)

- int [primal](#) (int ifValuesPass=0, int startFinishOptions=0)

*Primal algorithm - see [ClpSimplexPrimal.hpp](#) for method.*

- int [nonlinearSLP](#) (int numberPasses, double deltaTolerance)

*Solves nonlinear problem using SLP - may be used as crash for other algorithms when number of iterations small.*

- int [nonlinearSLP](#) (int numberConstraints, ClpConstraint \*\*constraints, int numberPasses, double deltaTolerance)

*Solves problem with nonlinear constraints using SLP - may be used as crash for other algorithms when number of iterations small.*

- int [barrier](#) (bool crossover=true)  
*Solves using barrier (assumes you have good cholesky factor code).*
- int [reducedGradient](#) (int phase=0)  
*Solves non-linear using reduced gradient.*
- int [solve](#) (CoinStructuredModel \*model)  
*Solve using structure of model and maybe in parallel.*
- int [loadProblem](#) (CoinStructuredModel &modelObject, bool originalOrder=true, bool keepSolution=false)  
*This loads a model from a CoinStructuredModel object - returns number of errors.*
- int [cleanup](#) (int cleanupScaling)  
*When scaling is on it is possible that the scaled problem is feasible but the unscaled is not.*
- int [dualRanging](#) (int numberCheck, const int \*which, double \*costIncrease, int \*sequenceIncrease, double \*costDecrease, int \*sequenceDecrease, double \*valueIncrease=NULL, double \*valueDecrease=NULL)  
*Dual ranging.*
- int [primalRanging](#) (int numberCheck, const int \*which, double \*valueIncrease, int \*sequenceIncrease, double \*valueDecrease, int \*sequenceDecrease)  
*Primal ranging.*
- int [writeBasis](#) (const char \*filename, bool writeValues=false, int formatType=0) const  
*Write the basis in MPS format to the specified file.*
- int [readBasis](#) (const char \*filename)  
*Read a basis from the given filename, returns -1 on file error, 0 if no values, 1 if values.*
- CoinWarmStartBasis \* [getBasis](#) () const  
*Returns a basis (to be deleted by user)*
- void [setFactorization](#) (ClpFactorization &factorization)  
*Passes in factorization.*
- ClpFactorization \* [swapFactorization](#) (ClpFactorization \*factorization)
- void [copyFactorization](#) (ClpFactorization &factorization)  
*Copies in factorization to existing one.*
- int [tightenPrimalBounds](#) (double factor=0.0, int doTight=0, bool tightIntegers=false)  
*Tightens primal bounds to make dual faster.*
- int [crash](#) (double gap, int pivot)  
*Crash - at present just aimed at dual, returns.*
- void [setDualRowPivotAlgorithm](#) (ClpDualRowPivot &choice)  
*Sets row pivot choice algorithm in dual.*
- void [setPrimalColumnPivotAlgorithm](#) (ClpPrimalColumnPivot &choice)  
*Sets column pivot choice algorithm in primal.*
- int [strongBranching](#) (int numberVariables, const int \*variables, double \*newLower, double \*newUpper, double \*\*outputSolution, int \*outputStatus, int \*outputIterations, bool stopOnFirstInfeasible=true, bool alwaysFinish=false, int startFinishOptions=0)  
*For strong branching.*
- int [fathom](#) (void \*stuff)  
*Fathom - 1 if solution.*
- int [fathomMany](#) (void \*stuff)

- *Do up to N deep - returns.*
- double `doubleCheck` ()
- *Double checks OK.*
- int `startFastDual2` (ClpNodeStuff \*stuff)
- *Starts Fast dual2.*
- int `fastDual2` (ClpNodeStuff \*stuff)
- *Like Fast dual.*
- void `stopFastDual2` (ClpNodeStuff \*stuff)
- *Stops Fast dual2.*
- ClpSimplex \* `fastCrunch` (ClpNodeStuff \*stuff, int mode)
- *Deals with crunch aspects mode 0 - in 1 - out with solution 2 - out without solution returns small model or NULL.*

#### Needed for functionality of OsiSimplexInterface

- int `pivot` ()
- *Pivot in a variable and out a variable.*
- int `primalPivotResult` ()
- *Pivot in a variable and choose an outgoing one.*
- int `dualPivotResult` ()
- *Pivot out a variable and choose an incoing one.*
- int `startup` (int ifValuesPass, int startFinishOptions=0)
- *Common bits of coding for dual and primal.*
- void `finish` (int startFinishOptions=0)
- bool `statusOfProblem` (bool initial=false)
- *Factorizes and returns true if optimal.*
- void `defaultFactorizationFrequency` ()
- *If user left factorization frequency then compute.*

#### most useful gets and sets

- bool `primalFeasible` () const
- *If problem is primal feasible.*
- bool `dualFeasible` () const
- *If problem is dual feasible.*
- ClpFactorization \* `factorization` () const
- *factorization*
- bool `sparseFactorization` () const
- *Sparsity on or off.*
- void `setSparseFactorization` (bool value)
- int `factorizationFrequency` () const
- *Factorization frequency.*
- void `setFactorizationFrequency` (int value)
- double `dualBound` () const
- *Dual bound.*
- void `setDualBound` (double value)
- double `infeasibilityCost` () const
- *Infeasibility cost.*
- void `setInfeasibilityCost` (double value)

- int [perturbation](#) () const  
*Amount of print out: 0 - none 1 - just final 2 - just factorizations 3 - as 2 plus a bit more 4 - verbose above that 8,16,32 etc just for selective debug.*
- void **setPerturbation** (int value)
- int [algorithm](#) () const  
*Current (or last) algorithm.*
- void **setAlgorithm** (int value)  
*Set algorithm.*
- bool **isObjectiveLimitTestValid** () const  
*Return true if the objective limit test can be relied upon.*
- double [sumDualInfeasibilities](#) () const  
*Sum of dual infeasibilities.*
- void **setSumDualInfeasibilities** (double value)
- double [sumOfRelaxedDualInfeasibilities](#) () const  
*Sum of relaxed dual infeasibilities.*
- void **setSumOfRelaxedDualInfeasibilities** (double value)
- int [numberDualInfeasibilities](#) () const  
*Number of dual infeasibilities.*
- void **setNumberDualInfeasibilities** (int value)
- int [numberDualInfeasibilitiesWithoutFree](#) () const  
*Number of dual infeasibilities (without free)*
- double [sumPrimalInfeasibilities](#) () const  
*Sum of primal infeasibilities.*
- void **setSumPrimalInfeasibilities** (double value)
- double [sumOfRelaxedPrimalInfeasibilities](#) () const  
*Sum of relaxed primal infeasibilities.*
- void **setSumOfRelaxedPrimalInfeasibilities** (double value)
- int [numberPrimalInfeasibilities](#) () const  
*Number of primal infeasibilities.*
- void **setNumberPrimalInfeasibilities** (int value)
- int [saveModel](#) (const char \*fileName)  
*Save model to file, returns 0 if success.*
- int [restoreModel](#) (const char \*fileName)  
*Restore model from file, returns 0 if success, deletes current model.*
- void [checkSolution](#) (int setToBounds=0)  
*Just check solution (for external use) - sets sum of infeasibilities etc.*
- void [checkSolutionInternal](#) ()  
*Just check solution (for internal use) - sets sum of infeasibilities etc.*
- void [checkUnscaledSolution](#) ()  
*Check unscaled primal solution but allow for rounding error.*
- CoinIndexedVector \* [rowArray](#) (int index) const  
*Useful row length arrays (0,1,2,3,4,5)*
- CoinIndexedVector \* [columnArray](#) (int index) const  
*Useful column length arrays (0,1,2,3,4,5)*
- double [alphaAccuracy](#) () const  
*Initial value for alpha accuracy calculation (-1.0 off)*
- void **setAlphaAccuracy** (double value)
- void **setDisasterHandler** ([ClpDisasterHandler](#) \*handler)  
*Objective value.*

- `ClpDisasterHandler * disasterHandler () const`  
*Get disaster handler.*
- `double largeValue () const`  
*Large bound value (for complementarity etc)*
- `void setLargeValue (double value)`
- `double largestPrimalError () const`  
*Largest error on Ax-b.*
- `double largestDualError () const`  
*Largest error on basic duals.*
- `void setLargestPrimalError (double value)`  
*Largest error on Ax-b.*
- `void setLargestDualError (double value)`  
*Largest error on basic duals.*
- `double zeroTolerance () const`  
*Get zero tolerance.*
- `void setZeroTolerance (double value)`  
*Set zero tolerance.*
- `int * pivotVariable () const`  
*Basic variables pivoting on which rows.*
- `bool automaticScaling () const`  
*If automatic scaling on.*
- `void setAutomaticScaling (bool onOff)`
- `double currentDualTolerance () const`  
*Current dual tolerance.*
- `void setCurrentDualTolerance (double value)`
- `double currentPrimalTolerance () const`  
*Current primal tolerance.*
- `void setCurrentPrimalTolerance (double value)`
- `int numberRefinements () const`  
*How many iterative refinements to do.*
- `void setNumberRefinements (int value)`
- `double alpha () const`  
*Alpha (pivot element) for use by classes e.g. steepestedge.*
- `void setAlpha (double value)`
- `double dualln () const`  
*Reduced cost of last incoming for use by classes e.g. steepestedge.*
- `int pivotRow () const`  
*Pivot Row for use by classes e.g. steepestedge.*
- `void setPivotRow (int value)`
- `double valueIncomingDual () const`  
*value of incoming variable (in Dual)*

#### public methods

- `double * solutionRegion (int section) const`  
*Return row or column sections - not as much needed as it once was.*
- `double * djRegion (int section) const`
- `double * lowerRegion (int section) const`
- `double * upperRegion (int section) const`

- double \* **costRegion** (int section) const
- double \* **solutionRegion** () const
  - Return region as single array.*
- double \* **djRegion** () const
- double \* **lowerRegion** () const
- double \* **upperRegion** () const
- double \* **costRegion** () const
- **Status** **getStatus** (int sequence) const
- void **setStatus** (int sequence, **Status** newstatus)
- bool **startPermanentArrays** ()
  - Start or reset using maximumRows\_ and Columns\_ - true if change.*
- void **setInitialDenseFactorization** (bool onOff)
  - Normally the first factorization does sparse coding because the factorization could be singular.*
- bool **initialDenseFactorization** () const
- int **sequenceIn** () const
  - Return sequence In or Out.*
- int **sequenceOut** () const
- void **setSequenceIn** (int sequence)
  - Set sequenceIn or Out.*
- void **setSequenceOut** (int sequence)
- int **directionIn** () const
  - Return direction In or Out.*
- int **directionOut** () const
- void **setDirectionIn** (int direction)
  - Set directionIn or Out.*
- void **setDirectionOut** (int direction)
- double **valueOut** () const
  - Value of Out variable.*
- void **setValueOut** (double value)
  - Set value of out variable.*
- void **setLowerOut** (double value)
  - Set lower of out variable.*
- void **setUpperOut** (double value)
  - Set upper of out variable.*
- void **setTheta** (double value)
  - Set theta of out variable.*
- int **isColumn** (int sequence) const
  - Returns 1 if sequence indicates column.*
- int **sequenceWithin** (int sequence) const
  - Returns sequence number within section.*
- double **solution** (int sequence)
  - Return row or column values.*
- double & **solutionAddress** (int sequence)
  - Return address of row or column values.*
- double **reducedCost** (int sequence)
- double & **reducedCostAddress** (int sequence)
- double **lower** (int sequence)
- double & **lowerAddress** (int sequence)

*Return address of row or column lower bound.*

- double **upper** (int sequence)
- double & **upperAddress** (int sequence)

*Return address of row or column upper bound.*

- double **cost** (int sequence)
- double & **costAddress** (int sequence)

*Return address of row or column cost.*

- double **originalLower** (int iSequence) const

*Return original lower bound.*

- double **originalUpper** (int iSequence) const

*Return original lower bound.*

- double **theta** () const

*Theta (pivot change)*

- double **bestPossibleImprovement** () const

*Best possible improvement using djs (primal) or obj change by flipping bounds to make dual feasible (dual)*

- **ClpNonLinearCost** \* **nonLinearCost** () const

*Return pointer to details of costs.*

- int **moreSpecialOptions** () const

*Return more special options 1 bit - if presolve says infeasible in **ClpSolve** return 2 bit - if presolved problem infeasible return 4 bit - keep arrays like upper\_ around 8 bit - if factorization kept can still declare optimal at once 16 bit - if checking replaceColumn accuracy before updating 32 bit - say optimal if primal feasible! 64 bit - give up easily in dual (and say infeasible) 128 bit - no objective, 0-1 and in B&B 256 bit - in primal from dual or vice versa 512 bit - alternative use of solveType\_ 1024 bit - don't do row copy of factorization 2048 bit - perturb in complete fathoming 4096 bit - try more for complete fathoming.*

- void **setMoreSpecialOptions** (int value)

*Set more special options 1 bit - if presolve says infeasible in **ClpSolve** return 2 bit - if presolved problem infeasible return 4 bit - keep arrays like upper\_ around 8 bit - no free or superBasic variables 16 bit - if checking replaceColumn accuracy before updating 32 bit - say optimal if primal feasible! 64 bit - give up easily in dual (and say infeasible) 128 bit - no objective, 0-1 and in B&B 256 bit - in primal from dual or vice versa 512 bit - alternative use of solveType\_ 1024 bit - don't do row copy of factorization 2048 bit - perturb in complete fathoming 4096 bit - try more for complete fathoming.*

#### status methods

- void **setFakeBound** (int sequence, FakeBound fakeBound)
- FakeBound **getFakeBound** (int sequence) const
- void **setRowStatus** (int sequence, **Status** newstatus)
- **Status** **getRowStatus** (int sequence) const
- void **setColumnStatus** (int sequence, **Status** newstatus)
- **Status** **getColumnStatus** (int sequence) const
- void **setPivoted** (int sequence)
- void **clearPivoted** (int sequence)
- bool **pivoted** (int sequence) const
- void **setFlagged** (int sequence)

*To flag a variable (not inline to allow for column generation)*

- void **clearFlagged** (int sequence)

- bool **flagged** (int sequence) const
- void **setActive** (int iRow)  
*To say row active in primal pivot row choice.*
- void **clearActive** (int iRow)
- bool **active** (int iRow) const
- void **createStatus** ()  
*Set up status array (can be used by OsiClp).*
- void **allSlackBasis** (bool resetSolution=false)  
*Sets up all slack basis and resets solution to as it was after initial load or readMps.*
- int **lastBadIteration** () const  
*So we know when to be cautious.*
- int **progressFlag** () const  
*Progress flag - at present 0 bit says artificials out.*
- void **forceFactorization** (int value)  
*Force re-factorization early.*
- double **rawObjectiveValue** () const  
*Raw objective value (so always minimize in primal)*
- void **computeObjectiveValue** (bool useWorkingSolution=false)  
*Compute objective value from solution and put in objectiveValue\_.*
- double **computeInternalObjectiveValue** ()  
*Compute minimization objective value from internal solution without perturbation.*
- int **numberExtraRows** () const  
*Number of extra rows.*
- int **maximumBasic** () const  
*Maximum number of basic variables - can be more than number of rows if GUB.*
- int **baseliteration** () const  
*Iteration when we entered dual or primal.*
- void **generateCpp** (FILE \*fp, bool defaultFactor=false)  
*Create C++ lines to get to current state.*
- **ClpFactorization** \* **getEmptyFactorization** ()  
*Gets clean and emptyish factorization.*
- void **setEmptyFactorization** ()  
*May delete or may make clean and emptyish factorization.*
- void **moveInfo** (const **ClpSimplex** &rhs, bool justStatus=false)  
*Move status and solution across.*

#### Basis handling

- void **getBlvARow** (int row, double \*z, double \*slack=NULL)  
*Get a row of the tableau (slack part in slack if not NULL)*
- void **getBlvRow** (int row, double \*z)  
*Get a row of the basis inverse.*
- void **getBlvACol** (int col, double \*vec)  
*Get a column of the tableau.*
- void **getBlvCol** (int col, double \*vec)  
*Get a column of the basis inverse.*
- void **getBasics** (int \*index)  
*Get basic indices (order of indices corresponds to the order of elements in a vector returned by **getBlvACol()** and **getBlvCol()**).*

## Changing bounds on variables and constraints

- void [setObjectiveCoefficient](#) (int elementIndex, double elementValue)  
*Set an objective function coefficient.*
- void [setObjCoeff](#) (int elementIndex, double elementValue)  
*Set an objective function coefficient.*
- void [setColumnLower](#) (int elementIndex, double elementValue)  
*Set a single column lower bound*  
*Use -DBL\_MAX for -infinity.*
- void [setColumnUpper](#) (int elementIndex, double elementValue)  
*Set a single column upper bound*  
*Use DBL\_MAX for infinity.*
- void [setColumnBounds](#) (int elementIndex, double lower, double upper)  
*Set a single column lower and upper bound.*
- void [setColumnSetBounds](#) (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of columns simultaneously*  
*The default implementation just invokes [setColLower\(\)](#) and [setColUpper\(\)](#) over and over again.*
- void [setColLower](#) (int elementIndex, double elementValue)  
*Set a single column lower bound*  
*Use -DBL\_MAX for -infinity.*
- void [setColUpper](#) (int elementIndex, double elementValue)  
*Set a single column upper bound*  
*Use DBL\_MAX for infinity.*
- void [setColBounds](#) (int elementIndex, double newlower, double newupper)  
*Set a single column lower and upper bound.*
- void [setColSetBounds](#) (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of columns simultaneously*
- void [setRowLower](#) (int elementIndex, double elementValue)  
*Set a single row lower bound*  
*Use -DBL\_MAX for -infinity.*
- void [setRowUpper](#) (int elementIndex, double elementValue)  
*Set a single row upper bound*  
*Use DBL\_MAX for infinity.*
- void [setRowBounds](#) (int elementIndex, double lower, double upper)  
*Set a single row lower and upper bound.*
- void [setRowSetBounds](#) (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of rows simultaneously*
- void [resize](#) (int newNumberRows, int newNumberColumns)  
*Resizes rim part of model.*

## Protected Member Functions

## protected methods

- int [gutsOfSolution](#) (double \*givenDuals, const double \*givenPrimals, bool valuesPass=false)

- May change basis and then returns number changed.*

  - void [gutsOfDelete](#) (int type)
 

*Does most of deletion (0 = all, 1 = most, 2 most + factorization)*
  - void [gutsOfCopy](#) (const [ClpSimplex](#) &rhs)
 

*Does most of copying.*
  - bool [createRim](#) (int what, bool makeRowCopy=false, int startFinishOptions=0)
 

*puts in format I like (rowLower,rowUpper) also see StandardMatrix 1 bit does rows (now and columns), (2 bit does column bounds), 4 bit does objective(s).*
  - void [createRim1](#) (bool initial)
 

*Does rows and columns.*
  - void [createRim4](#) (bool initial)
 

*Does objective.*
  - void [createRim5](#) (bool initial)
 

*Does rows and columns and objective.*
  - void [deleteRim](#) (int getRidOfFactorizationData=2)
 

*releases above arrays and does solution scaling out.*
  - bool [sanityCheck](#) ()
 

*Sanity check on input rim data (after scaling) - returns true if okay.*

#### Friends

- void [ClpSimplexUnitTest](#) (const std::string &mpsDir)
 

*A function that tests the methods in the [ClpSimplex](#) class.*

#### Functions less likely to be useful to casual user

- int [getSolution](#) (const double \*rowActivities, const double \*columnActivities)
 

*Given an existing factorization computes and checks primal and dual solutions.*
- int [getSolution](#) ()
 

*Given an existing factorization computes and checks primal and dual solutions.*
- int [createPiecewiseLinearCosts](#) (const int \*starts, const double \*lower, const double \*gradient)
 

*Constructs a non linear cost from list of non-linearities (columns only) First lower of each column is taken as real lower Last lower is taken as real upper and cost ignored.*
- [ClpDualRowPivot](#) \* [dualRowPivot](#) () const
 

*dual row pivot choice*
- [ClpPrimalColumnPivot](#) \* [primalColumnPivot](#) () const
 

*primal column pivot choice*
- bool [goodAccuracy](#) () const
 

*Returns true if model looks OK.*
- void [returnModel](#) ([ClpSimplex](#) &otherModel)
 

*Return model - updates any scalars.*
- int [internalFactorize](#) (int solveType)
 

*Factorizes using current basis.*

- [ClpDataSave saveData](#) ()  
*Save data.*
- void [restoreData](#) ([ClpDataSave](#) saved)  
*Restore data.*
- void [cleanStatus](#) ()  
*Clean up status.*
- int [factorize](#) ()  
*Factorizes using current basis. For external use.*
- void [computeDuals](#) (double \*givenDjs)  
*Computes duals from scratch.*
- void [computePrimals](#) (const double \*rowActivities, const double \*columnActivities)  
  
*Computes primals from scratch.*
- void [add](#) (double \*array, int column, double multiplier) const  
*Adds multiple of a column into an array.*
- void [unpack](#) (CoinIndexedVector \*rowArray) const  
*Unpacks one column of the matrix into indexed array Uses sequenceIn\_ Also applies scaling if needed.*
- void [unpack](#) (CoinIndexedVector \*rowArray, int sequence) const  
*Unpacks one column of the matrix into indexed array Slack if sequence >= numberColumns Also applies scaling if needed.*
- void [unpackPacked](#) (CoinIndexedVector \*rowArray)  
*Unpacks one column of the matrix into indexed array as packed vector Uses sequenceIn\_ - Also applies scaling if needed.*
- void [unpackPacked](#) (CoinIndexedVector \*rowArray, int sequence)  
*Unpacks one column of the matrix into indexed array as packed vector Slack if sequence >= numberColumns Also applies scaling if needed.*
- void [setValuesPassAction](#) (double incomingInfeasibility, double allowedInfeasibility)  
  
*For advanced use.*
- int [housekeeping](#) (double objectiveChange)  
*This does basis housekeeping and does values for in/out variables.*
- void [checkPrimalSolution](#) (const double \*rowActivities=NULL, const double \*columnActivities=NULL)  
  
*This sets largest infeasibility and most infeasible and sum and number of infeasibilities (Primal)*
- void [checkDualSolution](#) ()  
*This sets largest infeasibility and most infeasible and sum and number of infeasibilities (Dual)*
- void [checkBothSolutions](#) ()  
*This sets sum and number of infeasibilities (Dual and Primal)*
- double [scaleObjective](#) (double value)  
*If input negative scales objective so maximum <= -value and returns scale factor used.*
- int [solveDW](#) (CoinStructuredModel \*model)  
*Solve using Dantzig-Wolfe decomposition and maybe in parallel.*
- int [solveBenders](#) (CoinStructuredModel \*model)  
*Solve using Benders decomposition and maybe in parallel.*

data. Many arrays have a row part and a column part.

There is a single array with both - columns then rows and then normally two arrays pointing to rows and columns.

The single array is the owner of memory

- double [bestPossibleImprovement\\_](#)  
*Best possible improvement using djs (primal) or obj change by flipping bounds to make dual feasible (dual)*
- double [zeroTolerance\\_](#)  
*Zero tolerance.*
- int [columnPrimalSequence\\_](#)  
*Sequence of worst (-1 if feasible)*
- int [rowPrimalSequence\\_](#)  
*Sequence of worst (-1 if feasible)*
- double [bestObjectiveValue\\_](#)  
*"Best" objective value*
- int [moreSpecialOptions\\_](#)  
*More special options - see set for details.*
- int [baseIteration\\_](#)  
*Iteration when we entered dual or primal.*
- double [primalToleranceToGetOptimal\\_](#)  
*Primal tolerance needed to make dual feasible (< largeTolerance)*
- double [largeValue\\_](#)  
*Large bound value (for complementarity etc)*
- double [largestPrimalError\\_](#)  
*Largest error on Ax=b.*
- double [largestDualError\\_](#)  
*Largest error on basic duals.*
- double [alphaAccuracy\\_](#)  
*For computing whether to re-factorize.*
- double [dualBound\\_](#)  
*Dual bound.*
- double [alpha\\_](#)  
*Alpha (pivot element)*
- double [theta\\_](#)  
*Theta (pivot change)*
- double [lowerIn\\_](#)  
*Lower Bound on In variable.*
- double [valueIn\\_](#)  
*Value of In variable.*
- double [upperIn\\_](#)  
*Upper Bound on In variable.*

- double [dualIn\\_](#)  
*Reduced cost of In variable.*
- double [lowerOut\\_](#)  
*Lower Bound on Out variable.*
- double [valueOut\\_](#)  
*Value of Out variable.*
- double [upperOut\\_](#)  
*Upper Bound on Out variable.*
- double [dualOut\\_](#)  
*Infeasibility (dual) or ? (primal) of Out variable.*
- double [dualTolerance\\_](#)  
*Current dual tolerance for algorithm.*
- double [primalTolerance\\_](#)  
*Current primal tolerance for algorithm.*
- double [sumDualInfeasibilities\\_](#)  
*Sum of dual infeasibilities.*
- double [sumPrimalInfeasibilities\\_](#)  
*Sum of primal infeasibilities.*
- double [infeasibilityCost\\_](#)  
*Weight assigned to being infeasible in primal.*
- double [sumOfRelaxedDualInfeasibilities\\_](#)  
*Sum of Dual infeasibilities using tolerance based on error in duals.*
- double [sumOfRelaxedPrimalInfeasibilities\\_](#)  
*Sum of Primal infeasibilities using tolerance based on error in primals.*
- double [acceptablePivot\\_](#)  
*Acceptable pivot value just after factorization.*
- double \* [lower\\_](#)  
*Working copy of lower bounds (Owner of arrays below)*
- double \* [rowLowerWork\\_](#)  
*Row lower bounds - working copy.*
- double \* [columnLowerWork\\_](#)  
*Column lower bounds - working copy.*
- double \* [upper\\_](#)  
*Working copy of upper bounds (Owner of arrays below)*
- double \* [rowUpperWork\\_](#)  
*Row upper bounds - working copy.*
- double \* [columnUpperWork\\_](#)  
*Column upper bounds - working copy.*
- double \* [cost\\_](#)  
*Working copy of objective (Owner of arrays below)*
- double \* [rowObjectiveWork\\_](#)  
*Row objective - working copy.*
- double \* [objectiveWork\\_](#)

*Column objective - working copy.*

- CoinIndexedVector \* [rowArray\\_](#) [6]

*Useful row length arrays.*

- CoinIndexedVector \* [columnArray\\_](#) [6]

*Useful column length arrays.*

- int [sequenceIn\\_](#)

*Sequence of In variable.*

- int [directionIn\\_](#)

*Direction of In, 1 going up, -1 going down, 0 not a clude.*

- int [sequenceOut\\_](#)

*Sequence of Out variable.*

- int [directionOut\\_](#)

*Direction of Out, 1 to upper bound, -1 to lower bound, 0 - superbasic.*

- int [pivotRow\\_](#)

*Pivot Row.*

- int [lastGoodIteration\\_](#)

*Last good iteration (immediately after a re-factorization)*

- double \* [dj\\_](#)

*Working copy of reduced costs (Owner of arrays below)*

- double \* [rowReducedCost\\_](#)

*Reduced costs of slacks not same as duals (or - duals)*

- double \* [reducedCostWork\\_](#)

*Possible scaled reduced costs.*

- double \* [solution\\_](#)

*Working copy of primal solution (Owner of arrays below)*

- double \* [rowActivityWork\\_](#)

*Row activities - working copy.*

- double \* [columnActivityWork\\_](#)

*Column activities - working copy.*

- int [numberDualInfeasibilities\\_](#)

*Number of dual infeasibilities.*

- int [numberDualInfeasibilitiesWithoutFree\\_](#)

*Number of dual infeasibilities (without free)*

- int [numberPrimalInfeasibilities\\_](#)

*Number of primal infeasibilities.*

- int [numberRefinements\\_](#)

*How many iterative refinements to do.*

- ClpDualRowPivot \* [dualRowPivot\\_](#)

*dual row pivot choice*

- ClpPrimalColumnPivot \* [primalColumnPivot\\_](#)

*primal column pivot choice*

- int \* [pivotVariable\\_](#)

*Basic variables pivoting on which rows.*

- [ClpFactorization](#) \* [factorization\\_](#)  
*factorization*
- double \* [savedSolution\\_](#)  
*Saved version of solution.*
- int [numberTimesOptimal\\_](#)  
*Number of times code has tentatively thought optimal.*
- [ClpDisasterHandler](#) \* [disasterArea\\_](#)  
*Disaster handler.*
- int [changeMade\\_](#)  
*If change has been made (first attempt at stopping looping)*
- int [algorithm\\_](#)  
*Algorithm  $>0$  == Primal,  $<0$  == Dual.*
- int [forceFactorization\\_](#)  
*Now for some reliability aids This forces re-factorization early.*
- int [perturbation\\_](#)  
*Perturbation:*
- unsigned char \* [saveStatus\\_](#)  
*Saved status regions.*
- [ClpNonLinearCost](#) \* [nonLinearCost\\_](#)  
*Very wasteful way of dealing with infeasibilities in primal.*
- int [lastBadIteration\\_](#)  
*So we know when to be cautious.*
- int [lastFlaggedIteration\\_](#)  
*So we know when to open up again.*
- int [numberFake\\_](#)  
*Can be used for count of fake bounds (dual) or fake costs (primal)*
- int [numberChanged\\_](#)  
*Can be used for count of changed costs (dual) or changed bounds (primal)*
- int [progressFlag\\_](#)  
*Progress flag - at present 0 bit says artificials out, 1 free in.*
- int [firstFree\\_](#)  
*First free/super-basic variable (-1 if none)*
- int [numberExtraRows\\_](#)  
*Number of extra rows.*
- int [maximumBasic\\_](#)  
*Maximum number of basic variables - can be more than number of rows if GUB.*
- int [dontFactorizePivots\\_](#)  
*If may skip final factorize then allow up to this pivots (default 20)*
- double [incomingInfeasibility\\_](#)  
*For advanced use.*
- double [allowedInfeasibility\\_](#)
- int [automaticScale\\_](#)  
*Automatic scaling of objective and rhs and bounds.*

- int [maximumPerturbationSize\\_](#)  
*Maximum perturbation array size (take out when code rewritten)*
- double \* [perturbationArray\\_](#)  
*Perturbation array (maximumPerturbationSize\_)*
- [ClpSimplex](#) \* [baseModel\\_](#)  
*A copy of model with certain state - normally without cuts.*
- [ClpSimplexProgress](#) [progress\\_](#)  
*For dealing with all issues of cycling etc.*
- int [spareIntArray\\_](#) [4]  
*Spare int array for passing information [0]!=0 switches on.*
- double [spareDoubleArray\\_](#) [4]  
*Spare double array for passing information [0]!=0 switches on.*
- class [OsiClpSolverInterface](#)  
*Allow OsiClp certain perks.*

### 3.53.1 Detailed Description

This solves LPs using the simplex method.

It inherits from [ClpModel](#) and all its arrays are created at algorithm time. Originally I tried to work with model arrays but for simplicity of coding I changed to single arrays with structural variables then row variables. Some coding is still based on old style and needs cleaning up.

For a description of algorithms:

for dual see [ClpSimplexDual.hpp](#) and at top of [ClpSimplexDual.cpp](#) for primal see [ClpSimplexPrimal.hpp](#) and at top of [ClpSimplexPrimal.cpp](#)

There is an algorithm data member. + for primal variations and - for dual variations

Definition at line 49 of file [ClpSimplex.hpp](#).

### 3.53.2 Member Enumeration Documentation

#### 3.53.2.1 enum [ClpSimplex::Status](#)

enums for status of various sorts.

First 4 match CoinWarmStartBasis, isFixed means fixed at lower bound and out of basis

Definition at line 57 of file [ClpSimplex.hpp](#).

### 3.53.3 Constructor & Destructor Documentation

#### 3.53.3.1 [ClpSimplex::ClpSimplex](#) ( const [ClpSimplex](#) & *rhs*, int *scalingMode* = -1 )

Copy constructor.

May scale depending on mode -1 leave mode as is 0 -off, 1 equilibrium, 2 geometric, 3, auto, 4 dynamic(later)

### 3.53.3.2 ClpSimplex::ClpSimplex ( const ClpModel & rhs, int scalingMode = -1 )

Copy constructor from model.

May scale depending on mode -1 leave mode as is 0 -off, 1 equilibrium, 2 geometric, 3, auto, 4 dynamic(later)

### 3.53.3.3 ClpSimplex::ClpSimplex ( const ClpModel \* wholeModel, int numberOfRows, const int \* whichRows, int numberOfColumns, const int \* whichColumns, bool dropNames = true, bool dropIntegers = true, bool fixOthers = false )

Subproblem constructor.

A subset of whole model is created from the row and column lists given. The new order is given by list order and duplicates are allowed. Name and integer information can be dropped Can optionally modify rhs to take into account variables NOT in list in this case duplicates are not allowed (also see getbackSolution)

### 3.53.3.4 ClpSimplex::ClpSimplex ( const ClpSimplex \* wholeModel, int numberOfRows, const int \* whichRows, int numberOfColumns, const int \* whichColumns, bool dropNames = true, bool dropIntegers = true, bool fixOthers = false )

Subproblem constructor.

A subset of whole model is created from the row and column lists given. The new order is given by list order and duplicates are allowed. Name and integer information can be dropped Can optionally modify rhs to take into account variables NOT in list in this case duplicates are not allowed (also see getbackSolution)

### 3.53.3.5 ClpSimplex::ClpSimplex ( ClpSimplex \* wholeModel, int numberOfColumns, const int \* whichColumns )

This constructor modifies original [ClpSimplex](#) and stores original stuff in created [ClpSimplex](#).

It is only to be used in conjunction with originalModel

## 3.53.4 Member Function Documentation

### 3.53.4.1 void ClpSimplex::originalModel ( ClpSimplex \* miniModel )

This copies back stuff from miniModel and then deletes miniModel.

Only to be used with mini constructor

### 3.53.4.2 void ClpSimplex::loadProblem ( const ClpMatrixBase & matrix, const double \* collb, const double \* colub, const double \* obj, const double \* rowlb, const double \* rowub, const double \* rowObjective = NULL )

Loads a problem (the constraints on the rows are given by lower and upper bounds).

If a pointer is 0 then the following values are the default:

- `colub`: all columns have upper bound infinity
- `collb`: all columns have lower bound 0
- `rowub`: all rows have upper bound infinity
- `rowlb`: all rows have lower bound -infinity
- `obj`: all variables have 0 objective coefficient

Reimplemented from [ClpModel](#).

```
3.53.4.3 void ClpSimplex::loadProblem ( const int numcols, const int numrows, const
CoinBigIndex * start, const int * index, const double * value, const double * collb,
const double * colub, const double * obj, const double * rowlb, const double *
rowub, const double * rowObjective = NULL )
```

Just like the other [loadProblem\(\)](#) method except that the matrix is given in a standard column major ordered format (without gaps).

Reimplemented from [ClpModel](#).

```
3.53.4.4 int ClpSimplex::loadProblem ( CoinModel & modelObject, bool keepSolution = false
)
```

This loads a model from a coinModel object - returns number of errors.

If keepSolution true and size is same as current then keeps current status and solution

Reimplemented from [ClpModel](#).

```
3.53.4.5 int ClpSimplex::readLp ( const char * filename, const double epsilon = 1e-5 )
```

Read file in LP format from file with name filename.

See class CoinLpIO for description of this format.

```
3.53.4.6 void ClpSimplex::borrowModel ( ClpModel & otherModel )
```

Borrow model.

This is so we dont have to copy large amounts of data around. It assumes a derived class wants to overwrite an empty model with a real one - while it does an algorithm. This is same as [ClpModel](#) one, but sets scaling on etc.

Reimplemented from [ClpModel](#).

```
3.53.4.7 int ClpSimplex::loadNonLinear ( void * info, int & numberConstraints,
ClpConstraint **& constraints )
```

Load nonlinear part of problem from AMPL info Returns 0 if linear 1 if quadratic objective 2 if quadratic constraints 3 if nonlinear objective 4 if nonlinear constraints.

-1 on failure

**3.53.4.8** `int ClpSimplex::initialSolve ( ClpSolve & options )`

General solve algorithm which can do presolve.

See [ClpSolve.hpp](#) for options

**3.53.4.9** `int ClpSimplex::dual ( int ifValuesPass = 0, int startFinishOptions = 0 )`

Dual algorithm - see [ClpSimplexDual.hpp](#) for method.

ifValuesPass==2 just does values pass and then stops.

startFinishOptions - bits 1 - do not delete work areas and factorization at end 2 - use old factorization if same number of rows 4 - skip as much initialization of work areas as possible (based on whatsChanged in clpmodel.hpp) \*\* work in progress maybe other bits later

Reimplemented in [ClpSimplexDual](#).

**3.53.4.10** `int ClpSimplex::primal ( int ifValuesPass = 0, int startFinishOptions = 0 )`

Primal algorithm - see [ClpSimplexPrimal.hpp](#) for method.

ifValuesPass==2 just does values pass and then stops.

startFinishOptions - bits 1 - do not delete work areas and factorization at end 2 - use old factorization if same number of rows 4 - skip as much initialization of work areas as possible (based on whatsChanged in clpmodel.hpp) \*\* work in progress maybe other bits later

Reimplemented in [ClpSimplexPrimal](#).

**3.53.4.11** `int ClpSimplex::nonlinearSLP ( int numberPasses, double deltaTolerance )`

Solves nonlinear problem using SLP - may be used as crash for other algorithms when number of iterations small.

Also exits if all problematical variables are changing less than deltaTolerance

**3.53.4.12** `int ClpSimplex::nonlinearSLP ( int numberConstraints, ClpConstraint ** constraints, int numberPasses, double deltaTolerance )`

Solves problem with nonlinear constraints using SLP - may be used as crash for other algorithms when number of iterations small.

Also exits if all problematical variables are changing less than deltaTolerance

**3.53.4.13** `int ClpSimplex::barrier ( bool crossover = true )`

Solves using barrier (assumes you have good cholesky factor code).

Does crossover to simplex if asked

**3.53.4.14** `int ClpSimplex::reducedGradient ( int phase = 0 )`

Solves non-linear using reduced gradient.

Phase = 0 get feasible, =1 use solution

**3.53.4.15** `int ClpSimplex::loadProblem ( CoinStructuredModel & modelObject, bool  
originalOrder = true, bool keepSolution = false )`

This loads a model from a CoinStructuredModel object - returns number of errors.

If originalOrder then keep to order stored in blocks, otherwise first column/rows correspond to first block - etc. If keepSolution true and size is same as current then keeps current status and solution

**3.53.4.16** `int ClpSimplex::cleanup ( int cleanupScaling )`

When scaling is on it is possible that the scaled problem is feasible but the unscaled is not.

Clp returns a secondary status code to that effect. This option allows for a cleanup. If you use it I would suggest 1. This only affects actions when scaled optimal 0 - no action 1 - clean up using dual if primal infeasibility 2 - clean up using dual if dual infeasibility 3 - clean up using dual if primal or dual infeasibility 11,12,13 - as 1,2,3 but use primal

return code as dual/primal

**3.53.4.17** `int ClpSimplex::dualRanging ( int numberCheck, const int * which, double  
* costIncrease, int * sequenceIncrease, double * costDecrease, int *  
sequenceDecrease, double * valueIncrease = NULL, double * valueDecrease =  
NULL )`

Dual ranging.

This computes increase/decrease in cost for each given variable and corresponding sequence numbers which would change basis. Sequence numbers are 0..numberColumns and numberColumns.. for artificials/slacks. For non-basic variables the information is trivial to compute and the change in cost is just minus the reduced cost and the sequence number will be that of the non-basic variables. For basic variables a ratio test is between the reduced costs for non-basic variables and the row of the tableau corresponding to the basic variable. The increase/decrease value is always  $\geq 0.0$

Up to user to provide correct length arrays where each array is of length numberCheck. which contains list of variables for which information is desired. All other arrays will be filled in by function. If fifth entry in which is variable 7 then fifth entry in output arrays will be information for variable 7.

If valueIncrease/Decrease not NULL (both must be NULL or both non NULL) then these are filled with the value of variable if such a change in cost were made (the existing bounds are ignored)

Returns non-zero if infeasible unbounded etc

Reimplemented in [ClpSimplexOther](#).

3.53.4.18 `int ClpSimplex::primalRanging ( int numberCheck, const int * which, double * valueIncrease, int * sequenceIncrease, double * valueDecrease, int * sequenceDecrease )`

Primal ranging.

This computes increase/decrease in value for each given variable and corresponding sequence numbers which would change basis. Sequence numbers are 0..`numberColumns` and `numberColumns`.. for artificials/slacks. This should only be used for non-basic variables as otherwise information is pretty useless. For basic variables the sequence number will be that of the basic variables.

Up to user to provide correct length arrays where each array is of length `numberCheck`. `which` contains list of variables for which information is desired. All other arrays will be filled in by function. If fifth entry in `which` is variable 7 then fifth entry in output arrays will be information for variable 7.

Returns non-zero if infeasible unbounded etc

Reimplemented in [ClpSimplexOther](#).

3.53.4.19 `int ClpSimplex::writeBasis ( const char * filename, bool writeValues = false, int formatType = 0 ) const`

Write the basis in MPS format to the specified file.

If `writeValues` true writes values of structurals (and adds VALUES to end of NAME card)

Row and column names may be null. `formatType` is

- 0 - normal
- 1 - extra accuracy
- 2 - IEEE hex (later)

Returns non-zero on I/O error

Reimplemented in [ClpSimplexOther](#).

3.53.4.20 `int ClpSimplex::tightenPrimalBounds ( double factor = 0.0, int doTight = 0, bool tightIntegers = false )`

Tightens primal bounds to make dual faster.

Unless fixed or `doTight`>10, bounds are slightly looser than they could be. This is to make dual go faster and is probably not needed with a presolve. Returns non-zero if problem infeasible.

Fudge for branch and bound - put bounds on columns of `factor` \* largest value (at continuous) - should improve stability in branch and bound on infeasible branches (0.0 is off)

3.53.4.21 `int ClpSimplex::crash ( double gap, int pivot )`

Crash - at present just aimed at dual, returns.

-2 if dual preferred and crash basis created -1 if dual preferred and all slack basis preferred 0 if basis going in was not all slack 1 if primal preferred and all slack basis preferred 2 if primal preferred and crash basis created.

if gap between bounds  $\leq$  "gap" variables can be flipped ( If pivot -1 then can be made super basic!)

If "pivot" is -1 No pivoting - always primal 0 No pivoting (so will just be choice of algorithm) 1 Simple pivoting e.g. gub 2 Mini iterations

**3.53.4.22** `int ClpSimplex::strongBranching ( int numberVariables, const int * variables, double * newLower, double * newUpper, double ** outputSolution, int * outputStatus, int * outputIterations, bool stopOnFirstInfeasible = true, bool alwaysFinish = false, int startFinishOptions = 0 )`

For strong branching.

On input lower and upper are new bounds while on output they are change in objective function values ( $> 1.0e50$  infeasible). Return code is 0 if nothing interesting, -1 if infeasible both ways and +1 if infeasible one way (check values to see which one(s)) Solutions are filled in as well - even down, odd up - also status and number of iterations

Reimplemented in [ClpSimplexDual](#).

**3.53.4.23** `int ClpSimplex::fathomMany ( void * stuff )`

Do up to N deep - returns.

-1 - no solution nNodes\_ valid nodes  $\geq$  if solution and that node gives solution [ClpNode](#) array is  $2*N$  long. Values for N and array are in stuff (nNodes\_ also in stuff)

**3.53.4.24** `int ClpSimplex::pivot ( )`

Pivot in a variable and out a variable.

Returns 0 if okay, 1 if inaccuracy forced re-factorization, -1 if would be singular. Also updates primal/dual infeasibilities. Assumes sequenceIn\_ and pivotRow\_ set and also directionIn and Out.

**3.53.4.25** `int ClpSimplex::primalPivotResult ( )`

Pivot in a variable and choose an outgoing one.

Assumes primal feasible - will not go through a bound. Returns step length in theta Returns ray in ray\_ (or NULL if no pivot) Return codes as before but -1 means no acceptable pivot

**3.53.4.26** `int ClpSimplex::dualPivotResult ( )`

Pivot out a variable and choose an incoming one.

Assumes dual feasible - will not go through a reduced cost. Returns step length in theta Returns ray in ray\_ (or NULL if no pivot) Return codes as before but -1 means no acceptable pivot

**3.53.4.27** `int ClpSimplex::startup ( int ifValuesPass, int startFinishOptions = 0 )`

Common bits of coding for dual and primal.

Return 0 if okay, 1 if bad matrix, 2 if very bad factorization

startFinishOptions - bits 1 - do not delete work areas and factorization at end 2 - use old factorization if same number of rows 4 - skip as much initialization of work areas as possible (based on whatsChanged in clpmodel.hpp) \*\* work in progress maybe other bits later

**3.53.4.28** `bool ClpSimplex::statusOfProblem ( bool initial = false )`

Factorizes and returns true if optimal.

Used by user

**3.53.4.29** `int ClpSimplex::perturbation ( ) const [inline]`

Amount of print out: 0 - none 1 - just final 2 - just factorizations 3 - as 2 plus a bit more 4 - verbose above that 8,16,32 etc just for selective debug.

Perturbation: 50 - switch on perturbation 100 - auto perturb if takes too long (1.0e-6 largest nonzero) 101 - we are perturbed 102 - don't try perturbing again default is 100 others are for playing

Definition at line 531 of file ClpSimplex.hpp.

**3.53.4.30** `int ClpSimplex::saveModel ( const char * fileName )`

Save model to file, returns 0 if success.

This is designed for use outside algorithms so does not save iterating arrays etc. It does not save any messaging information. Does not save scaling values. It does not know about all types of virtual functions.

**3.53.4.31** `void ClpSimplex::checkSolution ( int setToBounds = 0 )`

Just check solution (for external use) - sets sum of infeasibilities etc.

If setToBounds 0 then primal column values not changed and used to compute primal row activity values. If 1 or 2 then status used - so all nonbasic variables set to indicated bound and if any values changed (or ==2) basic values re-computed.

**3.53.4.32** `void ClpSimplex::checkSolutionInternal ( )`

Just check solution (for internal use) - sets sum of infeasibilities etc.

**3.53.4.33** `int ClpSimplex::getSolution ( const double * rowActivities, const double * columnActivities )`

Given an existing factorization computes and checks primal and dual solutions.

Uses input arrays for variables at bounds. Returns feasibility states

3.53.4.34 `int ClpSimplex::getSolution ( )`

Given an existing factorization computes and checks primal and dual solutions.

Uses current problem arrays for bounds. Returns feasibility states

3.53.4.35 `int ClpSimplex::createPiecewiseLinearCosts ( const int * starts, const double * lower, const double * gradient )`

Constructs a non linear cost from list of non-linearities (columns only) First lower of each column is taken as real lower Last lower is taken as real upper and cost ignored.

Returns nonzero if bad data e.g. lowers not monotonic

3.53.4.36 `int ClpSimplex::internalFactorize ( int solveType )`

Factorizes using current basis.

*solveType* - 1 iterating, 0 initial, -1 external If 10 added then in primal values pass Return codes are as from [ClpFactorization](#) unless initial factorization when total number of singularities is returned. Special case is `numberRows_+1` -> all slack basis.

3.53.4.37 `void ClpSimplex::computeDuals ( double * givenDjs )`

Computes duals from scratch.

If *givenDjs* then allows for nonzero basic djs

3.53.4.38 `int ClpSimplex::housekeeping ( double objectiveChange )` [protected]

This does basis housekeeping and does values for in/out variables.

Can also decide to re-factorize

3.53.4.39 `double ClpSimplex::scaleObjective ( double value )` [protected]

If input negative scales objective so maximum  $\leq$  -value and returns scale factor used.

If positive unscales and also redoes dual stuff

3.53.4.40 `void ClpSimplex::setValuesPassAction ( double incomingInfeasibility, double allowedInfeasibility )`

For advanced use.

When doing iterative solves things can get nasty so on values pass if incoming solution has largest infeasibility  $<$  *incomingInfeasibility* throw out variables from basis until largest infeasibility  $<$  *allowedInfeasibility* or incoming largest infeasibility. If *allowedInfeasibility*  $\geq$  *incomingInfeasibility* this is always possible although you may end up with an all slack basis.

Defaults are 1.0,10.0

3.53.4.41 `void ClpSimplex::setDisasterHandler ( ClpDisasterHandler * handler )`  
`[inline]`

Objective value.

Set disaster handler

Definition at line 764 of file ClpSimplex.hpp.

3.53.4.42 `int ClpSimplex::gutsOfSolution ( double * givenDuals, const double * givenPrimals,`  
`bool valuesPass = false ) [protected]`

May change basis and then returns number changed.

Computation of solutions may be overridden by given pi and solution

3.53.4.43 `bool ClpSimplex::createRim ( int what, bool makeRowCopy = false, int`  
`startFinishOptions = 0 ) [protected]`

puts in format I like (rowLower,rowUpper) also see StandardMatrix 1 bit does rows (now and columns), (2 bit does column bounds), 4 bit does objective(s).

8 bit does solution scaling in 16 bit does rowArray and columnArray indexed vectors and makes row copy if wanted, also sets columnStart\_ etc Also creates scaling arrays if needed. It does scaling if needed. 16 also moves solutions etc in to work arrays On 16 returns false if problem "bad" i.e. matrix or bounds bad If startFinishOptions is -1 then called by user in getSolution so do arrays but keep pivotVariable\_

3.53.4.44 `void ClpSimplex::deleteRim ( int getRidOfFactorizationData = 2 ) [protected]`

releases above arrays and does solution scaling out.

May also get rid of factorization data - 0 get rid of nothing, 1 get rid of arrays, 2 also factorization

3.53.4.45 `double* ClpSimplex::solutionRegion ( int section ) const [inline]`

Return row or column sections - not as much needed as it once was.

These just map into single arrays

Definition at line 896 of file ClpSimplex.hpp.

3.53.4.46 `void ClpSimplex::setInitialDenseFactorization ( bool onOff )`

Normally the first factorization does sparse coding because the factorization could be singular.

This allows initial dense factorization when it is known to be safe

3.53.4.47 `void ClpSimplex::createStatus ( )`

Set up status array (can be used by OsiClp).

Also can be used to set up all slack basis

3.53.4.48 `int ClpSimplex::numberExtraRows ( ) const [inline]`

Number of extra rows.

These are ones which will be dynamically created each iteration. This is for GUB but may have other uses.

Definition at line 1184 of file `ClpSimplex.hpp`.

3.53.4.49 `void ClpSimplex::setColumnLower ( int elementIndex, double elementValue )`

Set a single column lower bound

Use `-DBL_MAX` for -infinity.

Reimplemented from [ClpModel](#).

3.53.4.50 `void ClpSimplex::setColumnUpper ( int elementIndex, double elementValue )`

Set a single column upper bound

Use `DBL_MAX` for infinity.

Reimplemented from [ClpModel](#).

3.53.4.51 `void ClpSimplex::setColumnSetBounds ( const int * indexFirst, const int * indexLast, const double * boundList )`

Set the bounds on a number of columns simultaneously

The default implementation just invokes [setColLower\(\)](#) and [setColUpper\(\)](#) over and over again.

#### Parameters

|                  |   |
|------------------|---|
| <i>index-</i>    | pointers to the beginning and after the end of the array of the indices of the <i>First, indexLas</i> variables whose <i>either</i> bound changes |
| <i>boundList</i> | the new lower/upper bound pairs for the variables   |

Reimplemented from [ClpModel](#).

3.53.4.52 `void ClpSimplex::setColLower ( int elementIndex, double elementValue ) [inline]`

Set a single column lower bound

Use `-DBL_MAX` for -infinity.

Reimplemented from [ClpModel](#).

Definition at line 1265 of file `ClpSimplex.hpp`.

3.53.4.53 `void ClpSimplex::setColUpper ( int elementIndex, double elementValue ) [inline]`

Set a single column upper bound

Use DBL\_MAX for infinity.

Reimplemented from [ClpModel](#).

Definition at line 1270 of file ClpSimplex.hpp.

**3.53.4.54** void ClpSimplex::setColSetBounds ( const int \* *indexFirst*, const int \* *indexLast*,  
const double \* *boundList* ) [inline]

Set the bounds on a number of columns simultaneously

#### Parameters

|                              |  |
|------------------------------|--|
| <i>indexFirst, indexLast</i> | pointers to the beginning and after the end of the array of the indices of the variables whose <i>either</i> bound changes |
| <i>boundList</i>             | the new lower/upper bound pairs for the variables  |

Reimplemented from [ClpModel](#).

Definition at line 1286 of file ClpSimplex.hpp.

**3.53.4.55** void ClpSimplex::setRowLower ( int *elementIndex*, double *elementValue* )

Set a single row lower bound

Use -DBL\_MAX for -infinity.

Reimplemented from [ClpModel](#).

**3.53.4.56** void ClpSimplex::setRowUpper ( int *elementIndex*, double *elementValue* )

Set a single row upper bound

Use DBL\_MAX for infinity.

Reimplemented from [ClpModel](#).

**3.53.4.57** void ClpSimplex::setRowSetBounds ( const int \* *indexFirst*, const int \* *indexLast*,  
const double \* *boundList* )

Set the bounds on a number of rows simultaneously

#### Parameters

|                              |  |
|------------------------------|--|
| <i>indexFirst, indexLast</i> | pointers to the beginning and after the end of the array of the indices of the constraints whose <i>either</i> bound changes |
| <i>boundList</i>             | the new lower/upper bound pairs for the constraints  |

Reimplemented from [ClpModel](#).

### 3.53.5 Friends And Related Function Documentation

**3.53.5.1 void ClpSimplexUnitTest ( const std::string & mpsDir ) [friend]**

A function that tests the methods in the [ClpSimplex](#) class.

The only reason for it not to be a member method is that this way it doesn't have to be compiled into the library. And that's a gain, because the library should be compiled with optimization on, but this method should be compiled with debugging.

It also does some testing of [ClpFactorization](#) class

**3.53.6 Member Data Documentation****3.53.6.1 int ClpSimplex::perturbation\_ [protected]**

Perturbation:

-50 to +50 - perturb by this power of ten (-6 sounds good) 100 - auto perturb if takes too long (1.0e-6 largest nonzero) 101 - we are perturbed 102 - don't try perturbing again default is 100

Definition at line 1472 of file ClpSimplex.hpp.

**3.53.6.2 ClpNonLinearCost\* ClpSimplex::nonLinearCost\_ [protected]**

Very wasteful way of dealing with infeasibilities in primal.

However it will allow non-linearities and use of dual analysis. If it doesn't work it can easily be replaced.

Definition at line 1479 of file ClpSimplex.hpp.

**3.53.6.3 int ClpSimplex::numberExtraRows\_ [protected]**

Number of extra rows.

These are ones which will be dynamically created each iteration. This is for GUB but may have other uses.

Definition at line 1495 of file ClpSimplex.hpp.

**3.53.6.4 double ClpSimplex::incomingInfeasibility\_ [protected]**

For advanced use.

When doing iterative solves things can get nasty so on values pass if incoming solution has largest infeasibility < incomingInfeasibility throw out variables from basis until largest infeasibility < allowedInfeasibility. if allowedInfeasibility >= incomingInfeasibility this is always possible although you may end up with an all slack basis.

Defaults are 1.0,10.0

Definition at line 1510 of file ClpSimplex.hpp.

The documentation for this class was generated from the following file:


- ClpSimplex.hpp

### 3.54 ClpSimplexDual Class Reference


This solves LPs using the dual simplex method.

```
#include <ClpSimplexDual.hpp>
```

Inheritance diagram for ClpSimplexDual:



Collaboration diagram for ClpSimplexDual:



## Public Member Functions

### Description of algorithm

- int **dual** (int ifValuesPass, int startFinishOptions=0)  
*Dual algorithm.*
- int **strongBranching** (int numberVariables, const int \*variables, double \*newLower, double \*newUpper, double \*\*outputSolution, int \*outputStatus, int \*outputIterations,

bool stopOnFirstInfeasible=true, bool alwaysFinish=false, int startFinishOptions=0)

*For strong branching.*

- [ClpFactorization](#) \* [setUpForStrongBranching](#) (char \*arrays, int numberOfRows, int numberOfColumns, bool solveLp=false)

*This does first part of StrongBranching.*

- void [cleanupAfterStrongBranching](#) ([ClpFactorization](#) \*factorization)

*This cleans up after strong branching.*

#### Functions used in dual

- int [whileIterating](#) (double \*&givenPi, int ifValuesPass)  
*This has the flow between re-factorizations Broken out for clarity and will be used by strong branching.*
- int [updateDualsInDual](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray, CoinIndexedVector \*outputArray, double theta, double &objectiveChange, bool fullRecompute)

*The duals are updated by the given arrays.*

- void [updateDualsInValuesPass](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray, double theta)

*The duals are updated by the given arrays.*

- void [flipBounds](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray)

*While updateDualsInDual sees what effect is of flip this does actual flipping.*

- double [dualColumn](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray, CoinIndexedVector \*spareArray, CoinIndexedVector \*spareArray2, double acceptablePivot, CoinBigIndex \*dubiousWeights)

*Row array has row part of pivot row Column array has column part.*

- int [dualColumn0](#) (const CoinIndexedVector \*rowArray, const CoinIndexedVector \*columnArray, CoinIndexedVector \*spareArray, double acceptablePivot, double &upperReturn, double &bestReturn, double &badFree)

*Does first bit of dualColumn.*

- void [checkPossibleValuesMove](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray, double acceptablePivot)

*Row array has row part of pivot row Column array has column part.*

- void [checkPossibleCleanup](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray, double acceptablePivot)

*Row array has row part of pivot row Column array has column part.*

- void [doEasyOnesInValuesPass](#) (double \*givenReducedCosts)

*This sees if we can move duals in dual values pass.*

- void [dualRow](#) (int alreadyChosen)

*Chooses dual pivot row Would be faster with separate region to scan and will have this (with square of infeasibility) when steepest For easy problems we can just choose one of the first rows we look at.*

- int [changeBounds](#) (int initialize, CoinIndexedVector \*outputArray, double &changeCost)

*Checks if any fake bounds active - if so returns number and modifies updatedDualBound\_ and everything.*

- bool [changeBound](#) (int iSequence)

*As changeBounds but just changes new bounds for a single variable.*

- void **originalBound** (int iSequence)  
*Restores bound to original bound.*
- int **checkUnbounded** (CoinIndexedVector \*ray, CoinIndexedVector \*spare, double changeCost)  
*Checks if tentative optimal actually means unbounded in dual Returns -3 if not, 2 if is unbounded.*
- void **statusOfProblemInDual** (int &lastCleaned, int type, double \*givenDjs, **Clp-DataSave** &saveData, int ifValuesPass)  
*Refactorizes if necessary Checks if finished.*
- int **perturb** ()  
*Perturbs problem (method depends on **perturbation()**) returns nonzero if should go to dual.*
- int **fastDual** (bool alwaysFinish=false)  
*Fast iterations.*
- int **numberAtFakeBound** ()  
*Checks number of variables at fake bounds.*
- int **pivotResult** ()  
*Pivot in a variable and choose an outgoing one.*
- int **nextSuperBasic** ()  
*Get next free , -1 if none.*
- int **startupSolve** (int ifValuesPass, double \*saveDuals, int startFinishOptions)  
*Startup part of dual (may be extended to other algorithms) returns 0 if good, 1 if bad.*
- void **finishSolve** (int startFinishOptions)
- void **gutsOfDual** (int ifValuesPass, double \*saveDuals, int initialStatus, **Clp-DataSave** &saveData)
- void **resetFakeBounds** (int type)

### 3.54.1 Detailed Description

This solves LPs using the dual simplex method.

It inherits from **ClpSimplex**. It has no data of its own and is never created - only cast from a **ClpSimplex** object at algorithm time.

Definition at line 23 of file ClpSimplexDual.hpp.

### 3.54.2 Member Function Documentation

#### 3.54.2.1 int ClpSimplexDual::dual ( int ifValuesPass, int startFinishOptions = 0 )

Dual algorithm.

Method

It tries to be a single phase approach with a weight of 1.0 being given to getting optimal and a weight of updatedDualBound\_ being given to getting dual feasible. In this version I have used the idea that this weight can be thought of as a fake bound. If the distance between the lower and upper bounds on a variable is less than the feasibility weight then we are always better off flipping to other bound to make dual feasible. If the distance

is greater then we make up a fake bound `updatedDualBound_` away from one bound. If we end up optimal or primal infeasible, we check to see if bounds okay. If so we have finished, if not we increase `updatedDualBound_` and continue (after checking if unbounded). I am undecided about free variables - there is coding but I am not sure about it. At present I put them in basis anyway.

The code is designed to take advantage of sparsity so arrays are seldom zeroed out from scratch or gone over in their entirety. The only exception is a full scan to find outgoing variable for Dantzig row choice. For steepest edge we keep an updated list of infeasibilities (actually squares). On easy problems we don't need full scan - just pick first reasonable.

One problem is how to tackle degeneracy and accuracy. At present I am using the modification of costs which I put in OSL and some of what I think is the dual analog of Gill et al. I am still not sure of the exact details.

The flow of dual is three while loops as follows:

```
while (not finished) {
  while (not clean solution) {
```

Factorize and/or clean up solution by flipping variables so dual feasible. If looks finished check fake dual bounds. Repeat until status is iterating (-1) or finished (0,1,2)

```
}
while (status===-1) {
```

Iterate until no pivot in or out or time to re-factorize.

Flow is:

choose pivot row (outgoing variable). if none then we are primal feasible so looks as if done but we need to break and check bounds etc.

Get pivot row in tableau

Choose incoming column. If we don't find one then we look primal infeasible so break and check bounds etc. (Also the pivot tolerance is larger after any iterations so that may be reason)

If we do find incoming column, we may have to adjust costs to keep going forwards (anti-degeneracy). Check pivot will be stable and if unstable throw away iteration and break to re-factorize. If minor error re-factorize after iteration.

Update everything (this may involve flipping variables to stay dual feasible.

```
}
}
```

TODO's (or maybe not)

At present we never check we are going forwards. I overdid that in OSL so will try and make a last resort.

Needs partial scan pivot out option.

May need other anti-degeneracy measures, especially if we try and use loose tolerances as a way to solve in fewer iterations.

I like idea of dynamic scaling. This gives opportunity to decouple different implications of scaling for accuracy, iteration count and feasibility tolerance.

for use of exotic parameter startFinishoptions see Clpsimplex.hpp

Reimplemented from [ClpSimplex](#).

```
3.54.2.2 int ClpSimplexDual::strongBranching ( int numberVariables, const int * variables,
double * newLower, double * newUpper, double ** outputSolution, int *
outputStatus, int * outputIterations, bool stopOnFirstInfeasible = true, bool
alwaysFinish = false, int startFinishOptions = 0 )
```

For strong branching.

On input lower and upper are new bounds while on output they are change in objective function values ( $> 1.0e50$  infeasible). Return code is 0 if nothing interesting, -1 if infeasible both ways and +1 if infeasible one way (check values to see which one(s)) Solutions are filled in as well - even down, odd up - also status and number of iterations

Reimplemented from [ClpSimplex](#).

```
3.54.2.3 int ClpSimplexDual::whileIterating ( double *& givenPi, int ifValuesPass )
```

This has the flow between re-factorizations Broken out for clarity and will be used by strong branching.

Reasons to come out: -1 iterations etc -2 inaccuracy -3 slight inaccuracy (and done iterations) +0 looks optimal (might be unbounded - but we will investigate) +1 looks infeasible +3 max iterations

If givenPi not NULL then in values pass

```
3.54.2.4 int ClpSimplexDual::updateDualsInDual ( CoinIndexedVector * rowArray,
CoinIndexedVector * columnArray, CoinIndexedVector * outputArray, double theta,
double & objectiveChange, bool fullRecompute )
```

The duals are updated by the given arrays.

Returns number of infeasibilities. After rowArray and columnArray will just have those which have been flipped. Variables may be flipped between bounds to stay dual feasible. The output vector has movement of primal solution (row length array)

```
3.54.2.5 void ClpSimplexDual::updateDualsInValuesPass ( CoinIndexedVector * rowArray,
CoinIndexedVector * columnArray, double theta )
```

The duals are updated by the given arrays.

This is in values pass - so no changes to primal is made

```
3.54.2.6 double ClpSimplexDual::dualColumn ( CoinIndexedVector * rowArray,
CoinIndexedVector * columnArray, CoinIndexedVector * sparseArray,
CoinIndexedVector * sparseArray2, double acceptablePivot, CoinBigIndex *
dubiousWeights )
```

Row array has row part of pivot row Column array has column part.

This chooses pivot column. Spare arrays are used to save pivots which will go infeasible. We will check for basic so spare array will never overflow. If necessary will modify costs. For speed, we may need to go to a bucket approach when many variables are being flipped. Returns best possible pivot value.

**3.54.2.7** void ClpSimplexDual::checkPossibleValuesMove ( CoinIndexedVector \* *rowArray*,  
CoinIndexedVector \* *columnArray*, double *acceptablePivot* )

Row array has row part of pivot row. Column array has column part.

This sees what is best thing to do in dual values pass. If `sequenceIn==sequenceOut` can change dual on chosen row and leave variable in basis.

**3.54.2.8** void ClpSimplexDual::checkPossibleCleanup ( CoinIndexedVector \* *rowArray*,  
CoinIndexedVector \* *columnArray*, double *acceptablePivot* )

Row array has row part of pivot row. Column array has column part.

This sees what is best thing to do in branch and bound cleanup. If `sequenceIn_ < 0` then can't do anything.

**3.54.2.9** void ClpSimplexDual::doEasyOnesInValuesPass ( double \* *givenReducedCosts* )

This sees if we can move duals in dual values pass.

This is done before any pivoting.

**3.54.2.10** void ClpSimplexDual::dualRow ( int *alreadyChosen* )

Chooses dual pivot row. Would be faster with separate region to scan and will have this (with square of infeasibility) when steepest. For easy problems we can just choose one of the first rows we look at.

If `alreadyChosen >= 0` then in values pass and that row has been selected.

**3.54.2.11** int ClpSimplexDual::changeBounds ( int *initialize*, CoinIndexedVector \* *outputArray*,  
double & *changeCost* )

Checks if any fake bounds active - if so returns number and modifies `updatedDualBound_` - and everything.

Free variables will be left as free. Returns number of bounds changed if `>= 0`. Returns -1 if not initialize and no effect. Fills in `changeVector` which can be used to see if unbounded and cost of change vector. If 2 sets to original (just changed).

**3.54.2.12** bool ClpSimplexDual::changeBound ( int *iSequence* )

As `changeBounds` but just changes new bounds for a single variable.

Returns true if change.

**3.54.2.13** void ClpSimplexDual::statusOfProblemInDual ( int & *lastCleaned*, int *type*, double \*  
*givenDjs*, ClpDataSave & *saveData*, int *ifValuesPass* )

Refactorizes if necessary. Checks if finished.

Updates status. lastCleaned refers to iteration at which some objective/feasibility cleaning took place.

type - 0 initial so set up save arrays etc

- 1 normal -if good update save

2 restoring from saved

**3.54.2.14** `int ClpSimplexDual::fastDual ( bool alwaysFinish = false )`

Fast iterations.

Misses out a lot of initialization. Normally stops on maximum iterations, first re-factorization or tentative optimum. If looks interesting then continues as normal. Returns 0 if finished properly, 1 otherwise.

**3.54.2.15** `int ClpSimplexDual::numberAtFakeBound ( )`

Checks number of variables at fake bounds.

This is used by fastDual so can exit gracefully before end

**3.54.2.16** `int ClpSimplexDual::pivotResult ( )`

Pivot in a variable and choose an outgoing one.

Assumes dual feasible - will not go through a reduced cost. Returns step length in theta Returns ray in ray\_ (or NULL if no pivot) Return codes as before but -1 means no acceptable pivot

The documentation for this class was generated from the following file:


- ClpSimplexDual.hpp

### 3.55 ClpSimplexNonlinear Class Reference


This solves non-linear LPs using the primal simplex method.

```
#include <ClpSimplexNonlinear.hpp>
```

Inheritance diagram for ClpSimplexNonlinear:



Collaboration diagram for ClpSimplexNonlinear:



## Public Member Functions

### Description of algorithm

- int [primal](#) ()  
*Primal algorithms for reduced gradient At present we have two algorithms:*
- int [primalSLP](#) (int numberPasses, double deltaTolerance)  
*Primal algorithm for quadratic Using a semi-trust region approach as for pooling problem This is in because I have it lying around.*
- int [primalSLP](#) (int numberConstraints, [ClpConstraint](#) \*\*constraints, int numberPasses, double deltaTolerance)

*Primal algorithm for nonlinear constraints Using a semi-trust region approach as for pooling problem This is in because I have it lying around.*

- void [directionVector](#) (CoinIndexedVector \*longArray, CoinIndexedVector \*spare1, CoinIndexedVector \*spare2, int mode, double &normFlagged, double &normUnflagged, int &numberNonBasic)

*Creates direction vector.*

- int [whileIterating](#) (int &pivotMode)

*Main part.*

- int [pivotColumn](#) (CoinIndexedVector \*longArray, CoinIndexedVector \*rowArray, CoinIndexedVector \*columnArray, CoinIndexedVector \*spare, int &pivotMode, double &solutionError, double \*array1)

*longArray has direction pivotMode - 0 - use all dual infeasible variables 1 - largest dj while  $\geq 10$  trying startup phase Returns 0 - can do normal iteration (basis change) 1 - no basis change 2 - if wants singleton 3 - if time to re-factorize If sequenceIn\_  $\geq 0$  then that will be incoming variable*

- void [statusOfProblemInPrimal](#) (int &lastCleaned, int type, [ClpSimplexProgress](#) \*progress, bool doFactorization, double &bestObjectiveWhenFlagged)

*Refactorizes if necessary Checks if finished.*

- int [pivotNonlinearResult](#) ()

*Do last half of an iteration.*

### 3.55.1 Detailed Description

This solves non-linear LPs using the primal simplex method.

It inherits from [ClpSimplexPrimal](#). It has no data of its own and is never created - only cast from a [ClpSimplexPrimal](#) object at algorithm time. If needed create new class and pass around

Definition at line 28 of file ClpSimplexNonlinear.hpp.

### 3.55.2 Member Function Documentation

#### 3.55.2.1 int ClpSimplexNonlinear::primal ( )

Primal algorithms for reduced gradient At present we have two algorithms:

A reduced gradient method.

#### 3.55.2.2 int ClpSimplexNonlinear::primalSLP ( int *numberPasses*, double *deltaTolerance* )

Primal algorithm for quadratic Using a semi-trust region approach as for pooling problem This is in because I have it lying around.

#### 3.55.2.3 int ClpSimplexNonlinear::primalSLP ( int *numberConstraints*, [ClpConstraint](#) \*\* *constraints*, int *numberPasses*, double *deltaTolerance* )

Primal algorithm for nonlinear constraints Using a semi-trust region approach as for pooling problem This is in because I have it lying around.

3.55.2.4 void ClpSimplexNonlinear::directionVector ( CoinIndexedVector \* *longArray*,  
CoinIndexedVector \* *spare1*, CoinIndexedVector \* *spare2*, int *mode*, double &  
*normFlagged*, double & *normUnflagged*, int & *numberNonBasic* )

Creates direction vector.

note longArray is long enough for rows and columns. If numberNonBasic 0 then is updated otherwise mode is ignored and those are used. Norms are only for those > 1.0e3\*dualTolerance If mode is nonzero then just largest dj

3.55.2.5 void ClpSimplexNonlinear::statusOfProblemInPrimal ( int & *lastCleaned*, int  
*type*, ClpSimplexProgress \* *progress*, bool *doFactorization*, double &  
*bestObjectiveWhenFlagged* )

Refactorizes if necessary Checks if finished.

Updates status. lastCleaned refers to iteration at which some objective/feasibility cleaning took place.

type - 0 initial so set up save arrays etc

- 1 normal -if good update save

2 restoring from saved

3.55.2.6 int ClpSimplexNonlinear::pivotNonlinearResult ( )

Do last half of an iteration.

Return codes Reasons to come out normal mode -1 normal -2 factorize now - good iteration -3 slight inaccuracy - refactorize - iteration done -4 inaccuracy - refactorize - no iteration -5 something flagged - go round again +2 looks unbounded +3 max iterations (iteration done)

The documentation for this class was generated from the following file:


- ClpSimplexNonlinear.hpp

## 3.56 ClpSimplexOther Class Reference


This is for Simplex stuff which is neither dual nor primal.

```
#include <ClpSimplexOther.hpp>
```

Inheritance diagram for ClpSimplexOther:



Collaboration diagram for ClpSimplexOther:



## Methods

- void **dualRanging** (int numberCheck, const int \*which, double \*costIncrease, int \*sequenceIncrease, double \*costDecrease, int \*sequenceDecrease, double \*valueIncrease=NULL, double \*valueDecrease=NULL)  
*Dual ranging.*
- void **primalRanging** (int numberCheck, const int \*which, double \*valueIncrease, int \*sequenceIncrease, double \*valueDecrease, int \*sequenceDecrease)

*Primal ranging.*

- int [parametrics](#) (double startingTheta, double &endingTheta, double reportIncrement, const double \*changeLowerBound, const double \*changeUpperBound, const double \*changeLowerRhs, const double \*changeUpperRhs, const double \*changeObjective)

*Parametrics This is an initial slow version.*

- int [parametrics](#) (const char \*dataFile)

*Version of parametrics which reads from file See CbcClpParam.cpp for details of format Returns -2 if unable to open file.*

- int [writeBasis](#) (const char \*filename, bool writeValues=false, int formatType=0) const

*Write the basis in MPS format to the specified file.*

- int [readBasis](#) (const char \*filename)

*Read a basis from the given filename.*

- [ClpSimplex](#) \* [dualOfModel](#) (double fractionRowRanges=1.0, double fractionColumnRanges=1.0) const

*Creates dual of a problem if looks plausible (defaults will always create model) fractionRowRanges is fraction of rows allowed to have ranges fractionColumnRanges is fraction of columns allowed to have ranges.*

- int [restoreFromDual](#) (const [ClpSimplex](#) \*dualProblem)

*Restores solution from dualized problem non-zero return code indicates minor problems.*

- [ClpSimplex](#) \* [crunch](#) (double \*rhs, int \*whichRows, int \*whichColumns, int &nBound, bool moreBounds=false, bool tightenBounds=false)

*Does very cursory presolve.*

- void [afterCrunch](#) (const [ClpSimplex](#) &small, const int \*whichRows, const int \*whichColumns, int nBound)

*After very cursory presolve.*

- [ClpSimplex](#) \* [gubVersion](#) (int \*whichRows, int \*whichColumns, int neededGub, int factorizationFrequency=50)

*Returns gub version of model or NULL whichRows has to be numberOfRows whichColumns has to be numberOfRows+numberColumns.*

- void [setGubBasis](#) ([ClpSimplex](#) &original, const int \*whichRows, const int \*whichColumns)

*Sets basis from original.*

- void [getGubBasis](#) ([ClpSimplex](#) &original, const int \*whichRows, const int \*whichColumns) const

*Restores basis to original.*

- void [cleanupAfterPostsolve](#) ()

*Quick try at cleaning up duals if postsolve gets wrong.*

- int [tightenIntegerBounds](#) (double \*rhsSpace)

*Tightens integer bounds - returns number tightened or -1 if infeasible.*

- int [expandKnapsack](#) (int knapsackRow, int &numberOutput, double \*buildObj, CoinBigIndex \*buildStart, int \*buildRow, double \*buildElement, int reConstruct=-1) const

*Expands out all possible combinations for a knapsack If buildObj NULL then just computes space needed - returns number elements On entry numberOutput is maximum allowed, on exit it is number needed or.*

## 3.56.1 Detailed Description

This is for Simplex stuff which is neither dual nor primal.

It inherits from [ClpSimplex](#). It has no data of its own and is never created - only cast from a [ClpSimplex](#) object at algorithm time.

Definition at line 23 of file ClpSimplexOther.hpp.

## 3.56.2 Member Function Documentation

**3.56.2.1** void ClpSimplexOther::dualRanging ( int *numberCheck*, const int \* *which*, double \* *costIncrease*, int \* *sequenceIncrease*, double \* *costDecrease*, int \* *sequenceDecrease*, double \* *valueIncrease* = NULL, double \* *valueDecrease* = NULL )

Dual ranging.

This computes increase/decrease in cost for each given variable and corresponding sequence numbers which would change basis. Sequence numbers are 0..numberColumns and numberColumns.. for artificials/slacks. For non-basic variables the information is trivial to compute and the change in cost is just minus the reduced cost and the sequence number will be that of the non-basic variables. For basic variables a ratio test is between the reduced costs for non-basic variables and the row of the tableau corresponding to the basic variable. The increase/decrease value is always  $\geq 0.0$

Up to user to provide correct length arrays where each array is of length numberCheck. which contains list of variables for which information is desired. All other arrays will be filled in by function. If fifth entry in which is variable 7 then fifth entry in output arrays will be information for variable 7.

If valueIncrease/Decrease not NULL (both must be NULL or both non NULL) then these are filled with the value of variable if such a change in cost were made (the existing bounds are ignored)

When here - guaranteed optimal

Reimplemented from [ClpSimplex](#).

**3.56.2.2** void ClpSimplexOther::primalRanging ( int *numberCheck*, const int \* *which*, double \* *valueIncrease*, int \* *sequenceIncrease*, double \* *valueDecrease*, int \* *sequenceDecrease* )

Primal ranging.

This computes increase/decrease in value for each given variable and corresponding sequence numbers which would change basis. Sequence numbers are 0..numberColumns and numberColumns.. for artificials/slacks. This should only be used for non-basic variables as otherwise information is pretty useless For basic variables the sequence number will be that of the basic variables.

Up to user to provide correct length arrays where each array is of length numberCheck. which contains list of variables for which information is desired. All other arrays will be filled in by function. If fifth entry in which is variable 7 then fifth entry in output arrays will

be information for variable 7.

When here - guaranteed optimal

Reimplemented from [ClpSimplex](#).

**3.56.2.3** `int ClpSimplexOther::parametrics ( double startingTheta, double & endingTheta,  
double reportIncrement, const double * changeLowerBound, const double  
* changeUpperBound, const double * changeLowerRhs, const double *  
changeUpperRhs, const double * changeObjective )`

Parametrics This is an initial slow version.

The code uses current bounds + theta \* change (if change array not NULL) and similarly for objective. It starts at startingTheta and returns ending theta in endingTheta. If reportIncrement 0.0 it will report on any movement If reportIncrement >0.0 it will report at startingTheta+k\*reportIncrement. If it can not reach input endingTheta return code will be 1 for infeasible, 2 for unbounded, if error on ranges -1, otherwise 0. Normal report is just theta and objective but if event handler exists it may do more On exit endingTheta is maximum reached (can be used for next startingTheta)

**3.56.2.4** `int ClpSimplexOther::writeBasis ( const char * filename, bool writeValues = false,  
int formatType = 0 ) const`

Write the basis in MPS format to the specified file.

If writeValues true writes values of structurals (and adds VALUES to end of NAME card)

Row and column names may be null. formatType is

- 0 - normal
- 1 - extra accuracy
- 2 - IEEE hex (later)

Returns non-zero on I/O error

Reimplemented from [ClpSimplex](#).

**3.56.2.5** `ClpSimplex* ClpSimplexOther::crunch ( double * rhs, int * whichRows, int *  
whichColumns, int & nBound, bool moreBounds = false, bool tightenBounds =  
false )`

Does very cursory presolve.

rhs is numberRows, whichRows is 3\*numberRows and whichColumns is 2\*numberColumns.

**3.56.2.6** `void ClpSimplexOther::afterCrunch ( const ClpSimplex & small, const int *  
whichRows, const int * whichColumns, int nBound )`

After very cursory presolve.

rhs is numberRows, whichRows is 3\*numberRows and whichColumns is 2\*numberColumns.

3.56.2.7 `int ClpSimplexOther::expandKnapsack ( int knapsackRow, int & numberOutput, double * buildObj, CoinBigIndex * buildStart, int * buildRow, double * buildElement, int reConstruct = -1 ) const`

Expands out all possible combinations for a knapsack. If *buildObj* NULL then just computes space needed - returns number elements. On entry *numberOutput* is maximum allowed, on exit it is number needed or.

-1 (as will be number elements) if maximum exceeded. *numberOutput* will have at least space to return values which reconstruct input. Rows returned will be original rows but no entries will be returned for any rows all of whose entries are in knapsack. So up to user to allow for this. If *reConstruct*  $\geq 0$  then returns number of entries which make up item "*reConstruct*" in expanded knapsack. Values in *buildRow* and *buildElement*;

The documentation for this class was generated from the following file:


- ClpSimplexOther.hpp

### 3.57 ClpSimplexPrimal Class Reference


This solves LPs using the primal simplex method.

```
#include <ClpSimplexPrimal.hpp>
```

Inheritance diagram for ClpSimplexPrimal:



Collaboration diagram for ClpSimplexPrimal:



## Public Member Functions

### Description of algorithm

- int **primal** (int ifValuesPass=0, int startFinishOptions=0)  
*Primal algorithm.*

## For advanced users

- void [alwaysOptimal](#) (bool onOff)  
*Do not change infeasibility cost and always say optimal.*
- bool **alwaysOptimal** () const
- void [exactOutgoing](#) (bool onOff)  
*Normally outgoing variables can go out to slightly negative values (but within tolerance) - this is to help stability and degeneracy.*
- bool **exactOutgoing** () const

## Functions used in primal

- int [whileIterating](#) (int valuesOption)  
*This has the flow between re-factorizations.*
- int [pivotResult](#) (int ifValuesPass=0)  
*Do last half of an iteration.*
- int [updatePrimalsInPrimal](#) (CoinIndexedVector \*rowArray, double theta, double &objectiveChange, int valuesPass)  
*The primals are updated by the given array.*
- void [primalRow](#) (CoinIndexedVector \*rowArray, CoinIndexedVector \*rhsArray, CoinIndexedVector \*spareArray, int valuesPass)  
*Row array has pivot column This chooses pivot row.*
- void [primalColumn](#) (CoinIndexedVector \*updateArray, CoinIndexedVector \*spareRow1, CoinIndexedVector \*spareRow2, CoinIndexedVector \*spareColumn1, CoinIndexedVector \*spareColumn2)  
*Chooses primal pivot column updateArray has cost updates (also use pivotRow\_ from last iteration) Would be faster with separate region to scan and will have this (with square of infeasibility) when steepest For easy problems we can just choose one of the first columns we look at.*
- int [checkUnbounded](#) (CoinIndexedVector \*ray, CoinIndexedVector \*spare, double changeCost)  
*Checks if tentative optimal actually means unbounded in primal Returns -3 if not, 2 if is unbounded.*
- void [statusOfProblemInPrimal](#) (int &lastCleaned, int type, [ClpSimplexProgress](#) \*progress, bool doFactorization, int ifValuesPass, [ClpSimplex](#) \*saveModel=NULL)  
*Refactorizes if necessary Checks if finished.*
- void [perturb](#) (int type)  
*Perturbs problem (method depends on [perturbation\(\)](#))*
- bool [unPerturb](#) ()  
*Take off effect of perturbation and say whether to try dual.*
- int [unflag](#) ()  
*Unflag all variables and return number unflagged.*
- int [nextSuperBasic](#) (int superBasicType, CoinIndexedVector \*columnArray)  
*Get next superbasic -1 if none, Normal type is 1 If type is 3 then initializes sorted list if 2 uses list.*
- void [primalRay](#) (CoinIndexedVector \*rowArray)  
*Create primal ray.*
- void [clearAll](#) ()  
*Clears all bits and clears rowArray[1] etc.*
- int [lexSolve](#) ()  
*Sort of lexicographic resolve.*

## 3.57.1 Detailed Description

This solves LPs using the primal simplex method.

It inherits from [ClpSimplex](#). It has no data of its own and is never created - only cast from a [ClpSimplex](#) object at algorithm time.

Definition at line 23 of file ClpSimplexPrimal.hpp.

## 3.57.2 Member Function Documentation

3.57.2.1 `int ClpSimplexPrimal::primal ( int ifValuesPass = 0, int startFinishOptions = 0 )`

Primal algorithm.

Method

It tries to be a single phase approach with a weight of 1.0 being given to getting optimal and a weight of `infeasibilityCost_` being given to getting primal feasible. In this version I have tried to be clever in a stupid way. The idea of fake bounds in dual seems to work so the primal analogue would be that of getting bounds on reduced costs (by a presolve approach) and using these for being above or below feasible region. I decided to waste memory and keep these explicitly. This allows for non-linear costs! I have not tested non-linear costs but will be glad to do something if a reasonable example is provided.

The code is designed to take advantage of sparsity so arrays are seldom zeroed out from scratch or gone over in their entirety. The only exception is a full scan to find incoming variable for Dantzig row choice. For steepest edge we keep an updated list of dual infeasibilities (actually squares). On easy problems we don't need full scan - just pick first reasonable. This method has not been coded.

One problem is how to tackle degeneracy and accuracy. At present I am using the modification of costs which I put in OSL and which was extended by Gill et al. I am still not sure whether we will also need explicit perturbation.

The flow of primal is three while loops as follows:

```
while (not finished) {
```

```
while (not clean solution) {
```

```
Factorize and/or clean up solution by changing bounds so primal feasible. If looks finished check fake primal bounds. Repeat until status is iterating (-1) or finished (0,1,2)
```

```
}
```

```
while (status== -1) {
```

```
Iterate until no pivot in or out or time to re-factorize.
```

```
Flow is:
```

```
choose pivot column (incoming variable). if none then we are primal feasible so looks as if done but we need to break and check bounds etc.
```

```
Get pivot column in tableau
```

```
Choose outgoing row. If we don't find one then we look primal unbounded so break and
```

check bounds etc. (Also the pivot tolerance is larger after any iterations so that may be reason)

If we do find outgoing row, we may have to adjust costs to keep going forwards (anti-degeneracy). Check pivot will be stable and if unstable throw away iteration and break to re-factorize. If minor error re-factorize after iteration.

Update everything (this may involve changing bounds on variables to stay primal feasible).

}

}

TODO's (or maybe not)

At present we never check we are going forwards. I overdid that in OSL so will try and make a last resort.

Needs partial scan pivot in option.

May need other anti-degeneracy measures, especially if we try and use loose tolerances as a way to solve in fewer iterations.

I like idea of dynamic scaling. This gives opportunity to decouple different implications of scaling for accuracy, iteration count and feasibility tolerance.

for use of exotic parameter startFinishoptions see Clpsimplex.hpp

Reimplemented from [ClpSimplex](#).

#### 3.57.2.2 void ClpSimplexPrimal::exactOutgoing ( bool *onOff* )

Normally outgoing variables can go out to slightly negative values (but within tolerance) - this is to help stability and and degeneracy.

This can be switched off

#### 3.57.2.3 int ClpSimplexPrimal::whileIterating ( int *valuesOption* )

This has the flow between re-factorizations.

Returns a code to say where decision to exit was made Problem status set to:

-2 re-factorize -4 Looks optimal/infeasible -5 Looks unbounded +3 max iterations

valuesOption has original value of valuesPass

#### 3.57.2.4 int ClpSimplexPrimal::pivotResult ( int *ifValuesPass* = 0 )

Do last half of an iteration.

This is split out so people can force incoming variable. If solveType\_ is 2 then this may re-factorize while normally it would exit to re-factorize. Return codes Reasons to come out (normal mode/user mode): -1 normal -2 factorize now - good iteration/ NA -3 slight inaccuracy - refactorize - iteration done/ same but factor done -4 inaccuracy - refactorize - no iteration/ NA -5 something flagged - go round again/ pivot not possible +2 looks unbounded +3 max iterations (iteration done)

With solveType\_ ==2 this should Pivot in a variable and choose an outgoing one. Assumes primal feasible - will not go through a bound. Returns step length in theta Returns ray in ray\_

**3.57.2.5** `int ClpSimplexPrimal::updatePrimalsInPrimal ( CoinIndexedVector * rowArray, double theta, double & objectiveChange, int valuesPass )`

The primals are updated by the given array.

Returns number of infeasibilities. After rowArray will have cost changes for use next iteration

**3.57.2.6** `void ClpSimplexPrimal::primalRow ( CoinIndexedVector * rowArray, CoinIndexedVector * rhsArray, CoinIndexedVector * spareArray, int valuesPass )`

Row array has pivot column This chooses pivot row.

Rhs array is used for distance to next bound (for speed) For speed, we may need to go to a bucket approach when many variables go through bounds If valuesPass non-zero then compute dj for direction

**3.57.2.7** `void ClpSimplexPrimal::statusOfProblemInPrimal ( int & lastCleaned, int type, ClpSimplexProgress * progress, bool doFactorization, int ifValuesPass, ClpSimplex * saveModel = NULL )`

Refactorizes if necessary Checks if finished.

Updates status. lastCleaned refers to iteration at which some objective/feasibility cleaning took place.

type - 0 initial so set up save arrays etc

- 1 normal -if good update save

2 restoring from saved saveModel is normally NULL but may not be if doing Sprint

The documentation for this class was generated from the following file:


- ClpSimplexPrimal.hpp

### 3.58 ClpSimplexProgress Class Reference

For saving extra information to see if looping.

```
#include <ClpSolve.hpp>
```

Collaboration diagram for ClpSimplexProgress:



## Public Member Functions

## Constructors and destructor and copy

- `ClpSimplexProgress ()`  
*Default constructor.*
- `ClpSimplexProgress (ClpSimplex *model)`  
*Constructor from model.*
- `ClpSimplexProgress (const ClpSimplexProgress &)`  
*Copy constructor.*
- `ClpSimplexProgress & operator= (const ClpSimplexProgress &rhs)`  
*Assignment operator. This copies the data.*

- [~ClpSimplexProgress](#) ()  
*Destructor.*
- void [reset](#) ()  
*Resets as much as possible.*
- void [fillFromModel](#) ([ClpSimplex](#) \*model)  
*Fill from model.*

#### Check progress

- int [looping](#) ()  
*Returns -1 if okay, -n+1 (n number of times bad) if bad but action taken, >=0 if give up and use as problem status.*
- void [startCheck](#) ()  
*Start check at beginning of whileiterating.*
- int [cycle](#) (int in, int out, int wayIn, int wayOut)  
*Returns cycle length in whileiterating.*
- double [lastObjective](#) (int back=1) const  
*Returns previous objective (if -1) - current if (0)*
- void [setInfeasibility](#) (double value)  
*Set real primal infeasibility and move back.*
- double [lastInfeasibility](#) (int back=1) const  
*Returns real primal infeasibility (if -1) - current if (0)*
- void [modifyObjective](#) (double value)  
*Modify objective e.g. if dual infeasible in dual.*
- int [lastIterationNumber](#) (int back=1) const  
*Returns previous iteration number (if -1) - current if (0)*
- void [clearIterationNumbers](#) ()  
*clears all iteration numbers (to switch off panic)*
- void [newOddState](#) ()  
*Odd state.*
- void [endOddState](#) ()
- void [clearOddState](#) ()
- int [oddState](#) () const
- int [badTimes](#) () const  
*number of bad times*
- void [clearBadTimes](#) ()
- int [reallyBadTimes](#) () const  
*number of really bad times*
- void [incrementReallyBadTimes](#) ()
- int [timesFlagged](#) () const  
*number of times flagged*
- void [clearTimesFlagged](#) ()
- void [incrementTimesFlagged](#) ()

#### Public Attributes

##### Data

- double [objective\\_](#) [CLP\_PROGRESS]

- Objective values.
- double [infeasibility\\_](#) [CLP\_PROGRESS]  
*Sum of infeasibilities for algorithm.*
- double [realInfeasibility\\_](#) [CLP\_PROGRESS]  
*Sum of real primal infeasibilities for primal.*
- double [initialWeight\\_](#)  
*Initial weight for weights.*
- int [in\\_](#) [CLP\_CYCLE]  
*For cycle checking.*
- int [out\\_](#) [CLP\_CYCLE]
- char [way\\_](#) [CLP\_CYCLE]
- [ClpSimplex](#) \* [model\\_](#)  
*Pointer back to model so we can get information.*
- int [numberInfeasibilities\\_](#) [CLP\_PROGRESS]  
*Number of infeasibilities.*
- int [iterationNumber\\_](#) [CLP\_PROGRESS]  
*Iteration number at which occurred.*
- int [numberTimes\\_](#)  
*Number of times checked (so won't stop too early)*
- int [numberBadTimes\\_](#)  
*Number of times it looked like loop.*
- int [numberReallyBadTimes\\_](#)  
*Number really bad times.*
- int [numberTimesFlagged\\_](#)  
*Number of times no iterations as flagged.*
- int [oddState\\_](#)  
*If things are in an odd state.*

### 3.58.1 Detailed Description

For saving extra information to see if looping.

Definition at line 244 of file ClpSolve.hpp.

The documentation for this class was generated from the following file:

- ClpSolve.hpp

## 3.59 ClpSolve Class Reference

This is a very simple class to guide algorithms.

```
#include <ClpSolve.hpp>
```

### Public Types

- enum [SolveType](#)  
*enums for solve function*

## Public Member Functions

## Constructors and destructor and copy

- [ClpSolve](#) ()  
*Default constructor.*
- [ClpSolve](#) ([SolveType](#) method, [PresolveType](#) presolveType, int numberPasses, int options[6], int extraInfo[6], int independentOptions[3])  
*Constructor when you really know what you are doing.*
- void [generateCpp](#) (FILE \*fp)  
*Generates code for above constructor.*
- [ClpSolve](#) (const [ClpSolve](#) &)  
*Copy constructor.*
- [ClpSolve](#) & [operator=](#) (const [ClpSolve](#) &rhs)  
*Assignment operator. This copies the data.*
- [~ClpSolve](#) ()  
*Destructor.*

## Functions most useful to user

- void [setSpecialOption](#) (int which, int value, int extraInfo=-1)  
*Special options - bits 0 4 - use crash (default allslack in dual, idiot in primal) 8 - all slack basis in primal 2 16 - switch off interrupt handling 3 32 - do not try and make plus minus one matrix 64 - do not use sprint even if problem looks good.*
- int [getSpecialOption](#) (int which) const
- void [setSolveType](#) ([SolveType](#) method, int extraInfo=-1)  
*Solve types.*
- [SolveType](#) [getSolveType](#) ()
- void [setPresolveType](#) ([PresolveType](#) amount, int extraInfo=-1)
- [PresolveType](#) [getPresolveType](#) ()
- int [getPresolvePasses](#) () const
- int [getExtraInfo](#) (int which) const  
*Extra info for idiot (or sprint)*
- void [setInfeasibleReturn](#) (bool trueFalse)  
*Say to return at once if infeasible, default is to solve.*
- bool [infeasibleReturn](#) () const
- bool [doDual](#) () const  
*Whether we want to do dual part of presolve.*
- void [setDoDual](#) (bool doDual\_)
- bool [doSingleton](#) () const  
*Whether we want to do singleton part of presolve.*
- void [setDoSingleton](#) (bool doSingleton\_)
- bool [doDoubleton](#) () const  
*Whether we want to do doubleton part of presolve.*
- void [setDoDoubleton](#) (bool doDoubleton\_)
- bool [doTripletion](#) () const  
*Whether we want to do tripletion part of presolve.*
- void [setDoTripletion](#) (bool doTripletion\_)
- bool [doTighten](#) () const  
*Whether we want to do tighten part of presolve.*

- void **setDoTighten** (bool doTighten\_)
- bool **doForcing** () const  
*Whether we want to do forcing part of presolve.*
- void **setDoForcing** (bool doForcing\_)
- bool **doImpliedFree** () const  
*Whether we want to do impliedfree part of presolve.*
- void **setDoImpliedFree** (bool doImpliedfree)
- bool **doDupcol** () const  
*Whether we want to do dupcol part of presolve.*
- void **setDoDupcol** (bool doDupcol\_)
- bool **doDuprow** () const  
*Whether we want to do duprow part of presolve.*
- void **setDoDuprow** (bool doDuprow\_)
- bool **doSingletonColumn** () const  
*Whether we want to do singleton column part of presolve.*
- void **setDoSingletonColumn** (bool doSingleton\_)
- int **presolveActions** () const  
*Set whole group.*
- void **setPresolveActions** (int action)
- int **substitution** () const  
*Largest column for substitution (normally 3)*
- void **setSubstitution** (int value)

### 3.59.1 Detailed Description

This is a very simple class to guide algorithms.

It is used to tidy up passing parameters to initialSolve and maybe for output from that Definition at line 20 of file ClpSolve.hpp.

### 3.59.2 Member Function Documentation

#### 3.59.2.1 void ClpSolve::setSpecialOption ( int which, int value, int extraInfo = -1 )

Special options - bits 0 4 - use crash (default allslack in dual, idiot in primal) 8 - all slack basis in primal 2 16 - switch off interrupt handling 3 32 - do not try and make plus minus one matrix 64 - do not use sprint even if problem looks good.

which translation is: which: 0 - startup in Dual (nothing if basis exists): 0 - no basis 1 - crash 2 - use initiative about idiot! but no crash 1 - startup in Primal (nothing if basis exists): 0 - use initiative 1 - use crash 2 - use idiot and look at further info 3 - use sprint and look at further info 4 - use all slack 5 - use initiative but no idiot 6 - use initiative but no sprint 7 - use initiative but no crash 8 - do allslack or idiot 9 - do allslack or sprint 10 - slp before 11 - no nothing and primal(0) 2 - interrupt handling - 0 yes, 1 no (for threadsafe) 3 - whether to make +- 1matrix - 0 yes, 1 no 4 - for barrier 0 - dense cholesky 1 - Wssmp allowing some long columns 2 - Wssmp not allowing long columns 3 - Wssmp using KKT 4 - Using Florida ordering 8 - bit set to do scaling 16 - set to be aggressive with gamma/delta? 32 - Use KKT 5 - for presolve 1 - switch off dual stuff 6 - for detailed printout (initially just presolve) 1 - presolve statistics

The documentation for this class was generated from the following file:

- ClpSolve.hpp

### 3.60 ClpTrustedData Struct Reference

For a structure to be used by trusted code.

```
#include <ClpParameters.hpp>
```

#### 3.60.1 Detailed Description

For a structure to be used by trusted code.

Definition at line 119 of file ClpParameters.hpp.

The documentation for this struct was generated from the following file:

- ClpParameters.hpp

### 3.61 ClpHashValue::CoinHashLink Struct Reference

Data.

```
#include <ClpNode.hpp>
```

#### 3.61.1 Detailed Description

Data.

Definition at line 335 of file ClpNode.hpp.

The documentation for this struct was generated from the following file:

- ClpNode.hpp

### 3.62 Idiot Class Reference

This class implements a very silly algorithm.

```
#include <Idiot.hpp>
```

#### Public Member Functions

- void [solve2](#)(CoinMessageHandler \*handler, const CoinMessages \*messages)  
*Stuff for internal use.*

## Constructors and destructor

*Just a pointer to model is kept*

- `Idiot ()`  
*Default constructor.*
- `Idiot (OsiSolverInterface &model)`  
*Constructor with model.*
- `Idiot (const Idiot &)`  
*Copy constructor.*
- `Idiot & operator= (const Idiot &rhs)`  
*Assignment operator. This copies the data.*
- `~Idiot ()`  
*Destructor.*

## Algorithmic calls

- `void solve ()`  
*Get an approximate solution with the idiot code.*
- `void crash (int numberPass, CoinMessageHandler *handler, const CoinMessages *messages, bool doCrossover=true)`  
*Lightweight "crash".*
- `void crossOver (int mode)`  
*Use simplex to get an optimal solution mode is how many steps the simplex crossover should take to arrive to an extreme point: 0 - chosen, all ever used, all 1 - chosen, all 2 - all 3 - do not do anything - maybe basis + 16 do presolves.*

## Gets and sets of most useful data

- `double getStartingWeight () const`  
*Starting weight - small emphasizes feasibility, default 1.0e-4.*
- `void setStartingWeight (double value)`
- `double getWeightFactor () const`  
*Weight factor - weight multiplied by this when changes, default 0.333.*
- `void setWeightFactor (double value)`
- `double getFeasibilityTolerance () const`  
*Feasibility tolerance - problem essentially feasible if individual infeasibilities less than this.*
- `void setFeasibilityTolerance (double value)`
- `double getReasonablyFeasible () const`  
*Reasonably feasible.*
- `void setReasonablyFeasible (double value)`
- `double getExitInfeasibility () const`  
*Exit infeasibility - exit if sum of infeasibilities less than this.*
- `void setExitInfeasibility (double value)`
- `int getMajorIterations () const`  
*Major iterations.*
- `void setMajorIterations (int value)`
- `int getMinorIterations () const`  
*Minor iterations.*
- `void setMinorIterations (int value)`

- int **getMinorIterations0** () const
- void **setMinorIterations0** (int value)
- int **getReduceliterations** () const  
*Reduce weight after this many major iterations.*
- void **setReduceliterations** (int value)
- int **getLogLevel** () const  
*Amount of information - default of 1 should be okay.*
- void **setLogLevel** (int value)
- int **getLightweight** () const  
*How lightweight - 0 not, 1 yes, 2 very lightweight.*
- void **setLightweight** (int value)
- int **getStrategy** () const  
*strategy*
- void **setStrategy** (int value)
- double **getDropEnoughFeasibility** () const  
*Fine tuning - okay if feasibility drop this factor.*
- void **setDropEnoughFeasibility** (double value)
- double **getDropEnoughWeighted** () const  
*Fine tuning - okay if weighted obj drop this factor.*
- void **setDropEnoughWeighted** (double value)

### 3.62.1 Detailed Description

This class implements a very silly algorithm.

It has no merit apart from the fact that it gets an approximate solution to some classes of problems. Better if vaguely homogeneous. It works on problems where volume algorithm works and often gets a better primal solution but it has no dual solution.

It can also be used as a "crash" to get a problem started. This is probably its most useful function.

It is based on the idea that algorithms with terrible convergence properties may be okay at first. Throw in some random dubious tricks and the resulting code may be worth keeping as long as you don't look at it.

Definition at line 48 of file Idiot.hpp.

### 3.62.2 Member Function Documentation

#### 3.62.2.1 double Idiot::getFeasibilityTolerance ( ) const [inline]

Feasibility tolerance - problem essentially feasible if individual infeasibilities less than this.

default 0.1

Definition at line 113 of file Idiot.hpp.

**3.62.2.2** `double Idiot::getReasonablyFeasible ( ) const [inline]`

Reasonably feasible.

Dubious method concentrates more on objective when sum of infeasibilities less than this. Very dubious default value of (Number of rows)/20

Definition at line 122 of file Idiot.hpp.

**3.62.2.3** `double Idiot::getExitInfeasibility ( ) const [inline]`

Exit infeasibility - exit if sum of infeasibilities less than this.

Default -1.0 (i.e. switched off)

Definition at line 130 of file Idiot.hpp.

**3.62.2.4** `int Idiot::getMajorIterations ( ) const [inline]`

Major iterations.

stop after this number. Default 30. Use 2-5 for "crash" 50-100 for serious crunching

Definition at line 138 of file Idiot.hpp.

**3.62.2.5** `int Idiot::getMinorIterations ( ) const [inline]`

Minor iterations.

Do this number of tiny steps before deciding whether to change weights etc. Default - dubious sqrt(Number of Rows). Good numbers 105 to 405 say (5 is dubious method of making sure idiot is not trying to be clever which it may do every 10 minor iterations)

Definition at line 150 of file Idiot.hpp.

**3.62.2.6** `int Idiot::getReduceIterations ( ) const [inline]`

Reduce weight after this many major iterations.

It may get reduced before this but this is a maximum. Default 3. 3-10 plausible.

Definition at line 166 of file Idiot.hpp.

**3.62.2.7** `void Idiot::solve2 ( CoinMessageHandler * handler, const CoinMessages * messages )`

Stuff for internal use.

Does actual work

The documentation for this class was generated from the following file:

- Idiot.hpp

### 3.63 IdiotResult Struct Reference

for use internally

```
#include <Idiot.hpp>
```

#### 3.63.1 Detailed Description

for use internally

Definition at line 22 of file Idiot.hpp.

The documentation for this struct was generated from the following file:

- Idiot.hpp

### 3.64 Info Struct Reference

\*\*\*\*\* DATA to be moved into protected section of [ClpInterior](#)

```
#include <ClpInterior.hpp>
```

#### 3.64.1 Detailed Description

\*\*\*\*\* DATA to be moved into protected section of [ClpInterior](#)

Definition at line 27 of file ClpInterior.hpp.

The documentation for this struct was generated from the following file:


- ClpInterior.hpp

### 3.65 MyEventHandler Class Reference


This is so user can trap events and do useful stuff.

```
#include <MyEventHandler.hpp>
```

Inheritance diagram for MyEventHandler:



Collaboration diagram for MyEventHandler:



## Public Member Functions

### Overrides

- virtual int **event** (**Event** whichEvent)  
*This can do whatever it likes.*

### Constructors, destructor etc

- **MyEventHandler** ()  
*Default constructor.*
- **MyEventHandler** (**ClpSimplex** \*model)  
*Constructor with pointer to model (redundant as setEventHandler does)*
- virtual **~MyEventHandler** ()  
*Destructor.*
- **MyEventHandler** (const **MyEventHandler** &rhs)  
*The copy constructor.*
- **MyEventHandler** & **operator=** (const **MyEventHandler** &rhs)  
*Assignment.*
- virtual **ClpEventHandler** \* **clone** () const  
*Clone.*

### 3.65.1 Detailed Description

This is so user can trap events and do useful stuff.

This is used in Clp/Test/unitTest.cpp

**ClpSimplex** model\_ is available as well as anything else you care to pass in

Definition at line 18 of file MyEventHandler.hpp.

### 3.65.2.1 MyEventHandler::MyEventHandler ( )

### 3.65.2.2 MyEventHandler::MyEventHandler ( const MyEventHandler & rhs )


### 3.65.3 Member Function Documentation

This can do whatever it likes.

Reimplemented from [ClpEventHandler](#).

- MyEventHandler.hpp

Collaboration diagram for MyMessageHandler:



Generated on Wed Nov 9 2011 10:10:29 for Clp by Doxygen

## Overrides

- virtual int **print** ()

## set and get

- const [ClpSimplex](#) \* **model** () const  
*Model.*
- void **setModel** ([ClpSimplex](#) \*model)
- const std::deque< StdVectorDouble > & **getFeasibleExtremePoints** () const  
*Get queue of feasible extreme points.*
- void **clearFeasibleExtremePoints** ()  
*Empty queue of feasible extreme points.*

## Constructors, destructor

- [MyMessageHandler](#) ()  
*Default constructor.*
- [MyMessageHandler](#) ([ClpSimplex](#) \*model, FILE \*userPointer=NULL)  
*Constructor with pointer to model.*
- virtual [~MyMessageHandler](#) ()  
*Destructor.*

## Copy method

- [MyMessageHandler](#) (const [MyMessageHandler](#) &)  
*The copy constructor.*
- [MyMessageHandler](#) (const [CoinMessageHandler](#) &)  
*The copy constructor from an [CoinSimplexMessageHandler](#).*
- [MyMessageHandler](#) & **operator=** (const [MyMessageHandler](#) &)
- virtual [CoinMessageHandler](#) \* **clone** () const  
*Clone.*

## Protected Attributes

## Data members

*The data members are protected to allow access for derived classes.*

- [ClpSimplex](#) \* **model\_**  
*Pointer back to model.*
- std::deque< StdVectorDouble > **feasibleExtremePoints\_**  
*Saved extreme points.*
- int **iterationNumber\_**  
*Iteration number so won't do same one twice.*

## 3.66.1 Detailed Description

Definition at line 28 of file [MyMessageHandler.hpp](#).

### 3.66.2 Constructor & Destructor Documentation

#### 3.66.2.1 MyMessageHandler::MyMessageHandler ( )

Default constructor.

#### 3.66.2.2 MyMessageHandler::MyMessageHandler ( const MyMessageHandler & )

The copy constructor.

#### 3.66.2.3 MyMessageHandler::MyMessageHandler ( const CoinMessageHandler & )

The copy constructor from an CoinSimplexMessageHandler.

The documentation for this class was generated from the following file:


- MyMessageHandler.hpp

## 3.67 myPdco Class Reference


This implements a simple network matrix as derived from [ClpMatrixBase](#).

```
#include <myPdco.hpp>
```

Inheritance diagram for myPdco:



Collaboration diagram for myPdco:



#### Public Member Functions

##### Useful methods

- virtual void **matVecMult** ([ClpInterior](#) \*model, int mode, double \*x, double \*y) const
- virtual void **getGrad** ([ClpInterior](#) \*model, CoinDenseVector< double > &grad) const
- virtual void **getHessian** ([ClpInterior](#) \*model, CoinDenseVector< double > &x, CoinDenseVector< double > &H) const
- virtual double **getObj** ([ClpInterior](#) \*model, CoinDenseVector< double > &x) const
- virtual void **matPrecon** ([ClpInterior](#) \*model, double delta, double \*x, double \*y) const

##### Constructors, destructor

- [myPdco](#) ()  
*Default constructor.*
- [myPdco](#) (double d1, double d2, int numnodes, int numlinks)  
*Constructor from Stuff.*
- [myPdco](#) ([ClpInterior](#) &model, FILE \*fpData, FILE \*fpParam)  
*Also reads a model.*
- virtual [~myPdco](#) ()  
*Destructor.*

##### Copy method

- [myPdco](#) (const [myPdco](#) &)  
*The copy constructor.*
- [myPdco](#) & **operator=** (const [myPdco](#) &)
- virtual [ClpPdcoBase](#) \* **clone** () const  
*Clone.*

### Protected Attributes

#### Data members

*The data members are protected to allow access for derived classes.*

- int \* **rowIndex\_**
- int **numlinks\_**
- int **numnodes\_**

#### 3.67.1 Detailed Description

This implements a simple network matrix as derived from [ClpMatrixBase](#).

If you want more sophisticated version then you could inherit from this. Also you might want to allow networks with gain

Definition at line 19 of file myPdco.hpp.

#### 3.67.2 Constructor & Destructor Documentation

##### 3.67.2.1 myPdco::myPdco ( )

Default constructor.

##### 3.67.2.2 myPdco::myPdco ( const myPdco & )

The copy constructor.

The documentation for this class was generated from the following file:

- myPdco.hpp

### 3.68 Options Struct Reference

\*\*\*\*\* DATA to be moved into protected section of [ClpInterior](#)

```
#include <ClpInterior.hpp>
```

#### 3.68.1 Detailed Description

\*\*\*\*\* DATA to be moved into protected section of [ClpInterior](#)


Definition at line 44 of file ClpInterior.hpp.

The documentation for this struct was generated from the following file:


- ClpInterior.hpp

## 3.69 OsiClpDisasterHandler Class Reference

Inheritance diagram for OsiClpDisasterHandler:



Collaboration diagram for OsiClpDisasterHandler:



## Public Member Functions

Virtual methods that the derived classe should provide.

- virtual void `intoSimplex` ()  
*Into simplex.*
- virtual bool `check` () const  
*Checks if disaster.*
- virtual void `saveInfo` ()  
*saves information for next attempt*
- virtual int `typeOfDisaster` ()  
*Type of disaster 0 can fix, 1 abort.*

Constructors, destructor

- `OsiClpDisasterHandler` (`OsiClpSolverInterface` \*model=NULL)  
*Default constructor.*
- virtual `~OsiClpDisasterHandler` ()  
*Destructor.*
- **`OsiClpDisasterHandler`** (const `OsiClpDisasterHandler` &)
- `OsiClpDisasterHandler` & **`operator=`** (const `OsiClpDisasterHandler` &)
- virtual `ClpDisasterHandler` \* `clone` () const  
*Clone.*

Sets/gets

- void `setOsiModel` (`OsiClpSolverInterface` \*model)  
*set model.*
- `OsiClpSolverInterface` \* `osiModel` () const  
*Get model.*
- void `setWhereFrom` (int value)  
*Set where from.*
- int `whereFrom` () const  
*Get where from.*
- void `setPhase` (int value)  
*Set phase.*
- int `phase` () const  
*Get phase.*
- bool `inTrouble` () const  
*are we in trouble*

Protected Attributes

Data members

*The data members are protected to allow access for derived classes.*

- `OsiClpSolverInterface` \* `osiModel_`  
*Pointer to model.*
- int `whereFrom_`

*Where from 0 dual (resolve) 1 crunch 2 primal (resolve) 4 dual (initialSolve) 6 primal (initialSolve)*

- int [phase\\_](#)  
*phase 0 initial 1 trying continuing with back in and maybe different perturb 2 trying continuing with back in and different scaling 3 trying dual from all slack 4 trying primal from previous stored basis*
- bool [inTrouble\\_](#)  
*Are we in trouble.*

### 3.69.1 Detailed Description

Definition at line 1394 of file OsiClpSolverInterface.hpp.

### 3.69.2 Constructor & Destructor Documentation

**3.69.2.1** OsiClpDisasterHandler::OsiClpDisasterHandler ( OsiClpSolverInterface \* *model* = NULL )

Default constructor.

### 3.69.3 Member Function Documentation

**3.69.3.1** void OsiClpDisasterHandler::setOsiModel ( OsiClpSolverInterface \* *model* )

set model.

The documentation for this class was generated from the following file:


- OsiClpSolverInterface.hpp

## 3.70 OsiClpSolverInterface Class Reference

Clp Solver Interface.

```
#include <OsiClpSolverInterface.hpp>
```

Collaboration diagram for OsiClpSolverInterface:



## Public Member Functions

- virtual void **setObjSense** (double s)  
*Set objective function sense (1 for min (default), -1 for max.)*
- virtual void **setColSolution** (const double \*colsol)  
*Set the primal solution column values.*
- virtual void **setRowPrice** (const double \*rowprice)  
*Set dual solution vector.*

## Solve methods

- virtual void **initialSolve** ()  
*Solve initial LP relaxation.*
- virtual void **resolve** ()  
*Resolve an LP relaxation after problem modification.*
- virtual void **resolveGub** (int needed)  
*Resolve an LP relaxation after problem modification (try GUB)*
- virtual void **branchAndBound** ()  
*Invoke solver's built-in enumeration algorithm.*
- void **crossover** (int options, int basis)  
*Solve when primal column and dual row solutions are near-optimal options - 0 no presolve (use primal and dual) 1 presolve (just use primal) 2 no presolve (just use primal) basis - 0 use all slack basis 1 try and put some in basis.*

## OsiSimplexInterface methods

Methods for the Osi Simplex API.

The current implementation should work for both minimisation and maximisation in mode 1 (tableau access). In mode 2 (single pivot), only minimisation is supported as of 100907.

- virtual int [canDoSimplexInterface](#) () const  
*Simplex API capability.*
- virtual void [enableFactorization](#) () const  
*Enables simplex mode 1 (tableau access)*
- virtual void [disableFactorization](#) () const  
*Undo any setting changes made by [enableFactorization](#).*
- virtual bool [basisIsAvailable](#) () const  
*Returns true if a basis is available AND problem is optimal.*
- virtual void [getBasisStatus](#) (int \*cstat, int \*rstat) const  
*The following two methods may be replaced by the methods of OsiSolverInterface using OsiWarmStartBasis if: 1.*
- virtual int [setBasisStatus](#) (const int \*cstat, const int \*rstat)  
*Set the status of structural/artificial variables and factorize, update solution etc.*
- virtual void [getReducedGradient](#) (double \*columnReducedCosts, double \*duals, const double \*c) const  
*Get the reduced gradient for the cost vector c.*
- virtual void [getBlvARow](#) (int row, double \*z, double \*slack=NULL) const  
*Get a row of the tableau (slack part in slack if not NULL)*
- virtual void [getBlvARow](#) (int row, CoinIndexedVector \*z, CoinIndexedVector \*slack=NULL, bool keepScaled=false) const  
*Get a row of the tableau (slack part in slack if not NULL) If keepScaled is true then scale factors not applied after so user has to use coding similar to what is in this method.*
- virtual void [getBlvRow](#) (int row, double \*z) const  
*Get a row of the basis inverse.*
- virtual void [getBlvACol](#) (int col, double \*vec) const  
*Get a column of the tableau.*
- virtual void [getBlvACol](#) (int col, CoinIndexedVector \*vec) const  
*Get a column of the tableau.*
- virtual void [getBlvACol](#) (CoinIndexedVector \*vec) const  
*Update (i.e.*
- virtual void [getBlvCol](#) (int col, double \*vec) const  
*Get a column of the basis inverse.*
- virtual void [getBasics](#) (int \*index) const  
*Get basic indices (order of indices corresponds to the order of elements in a vector returned by [getBlvACol\(\)](#) and [getBlvCol\(\)](#)).*
- virtual void [enableSimplexInterface](#) (bool doingPrimal)  
*Enables simplex mode 2 (individual pivot control)*
- virtual void [disableSimplexInterface](#) ()  
*Undo setting changes made by [enableSimplexInterface](#).*
- virtual int [pivot](#) (int colIn, int colOut, int outStatus)  
*Perform a pivot by substituting a colIn for colOut in the basis.*

- virtual int [primalPivotResult](#) (int colIn, int sign, int &colOut, int &outStatus, double &t, CoinPackedVector \*dx)  
*Obtain a result of the primal pivot Outputs: colOut -- leaving column, outStatus -- its status, t -- step size, and, if dx!=NULL, \*dx -- primal ray direction.*
- virtual int [dualPivotResult](#) (int &colIn, int &sign, int colOut, int outStatus, double &t, CoinPackedVector \*dx)  
*Obtain a result of the dual pivot (similar to the previous method) Differences: entering variable and a sign of its change are now the outputs, the leaving variable and its status -- the inputs If dx!=NULL, then \*dx contains dual ray Return code: same.*

#### Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the clp algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

- bool **setIntParam** (OsiIntParam key, int value)
- bool **setDbiParam** (OsiDbiParam key, double value)
- bool **setStrParam** (OsiStrParam key, const std::string &value)
- bool **getIntParam** (OsiIntParam key, int &value) const
- bool **getDbiParam** (OsiDbiParam key, double &value) const
- bool **getStrParam** (OsiStrParam key, std::string &value) const
- virtual bool **setHintParam** (OsiHintParam key, bool yesNo=true, OsiHintStrength strength=OsiHintTry, void \*otherInformation=NULL)

#### Methods returning info on how the solution process terminated

- virtual bool [isAbandoned](#) () const  
*Are there a numerical difficulties?*
- virtual bool [isProvenOptimal](#) () const  
*Is optimality proven?*
- virtual bool [isProvenPrimalInfeasible](#) () const  
*Is primal infeasibility proven?*
- virtual bool [isProvenDualInfeasible](#) () const  
*Is dual infeasibility proven?*
- virtual bool [isPrimalObjectiveLimitReached](#) () const  
*Is the given primal objective limit reached?*
- virtual bool [isDualObjectiveLimitReached](#) () const  
*Is the given dual objective limit reached?*
- virtual bool [isIterationLimitReached](#) () const  
*Iteration limit reached?*

## WarmStart related methods

- virtual CoinWarmStart \* [getEmptyWarmStart](#) () const  
*Get an empty warm start object.*
- virtual CoinWarmStart \* [getWarmStart](#) () const  
*Get warmstarting information.*
- CoinWarmStartBasis \* [getPointerToWarmStart](#) ()  
*Get warmstarting information.*
- const CoinWarmStartBasis \* [getConstPointerToWarmStart](#) () const  
*Get warmstarting information.*
- virtual bool [setWarmStart](#) (const CoinWarmStart \*warmstart)  
*Set warmstarting information.*
- virtual CoinWarmStart \* [getPointerToWarmStart](#) (bool &mustDelete)  
*Get warm start information.*

## Hotstart related methods (primarily used in strong branching).

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

**NOTE:** between hotstarted optimizations only bound changes are allowed.

- virtual void [markHotStart](#) ()  
*Create a hotstart point of the optimization process.*
- virtual void [solveFromHotStart](#) ()  
*Optimize starting from the hotstart.*
- virtual void [unmarkHotStart](#) ()  
*Delete the snapshot.*
- int [startFastDual](#) (int options)  
*Start faster dual - returns negative if problems 1 if infeasible, [Options](#) to pass to solver 1 - create external reduced costs for columns 2 - create external reduced costs for rows 4 - create external row activity (columns always done) Above only done if feasible When set resolve does less work.*
- void [stopFastDual](#) ()  
*Stop fast dual.*
- void [setStuff](#) (double tolerance, double increment)  
*Sets integer tolerance and increment.*

## Methods related to querying the input data

- virtual int [getNumCols](#) () const  
*Get number of columns.*
- virtual int [getNumRows](#) () const  
*Get number of rows.*
- virtual int [getNumElements](#) () const  
*Get number of nonzero elements.*
- virtual std::string [getRowName](#) (int rowIndex, unsigned maxlen=static\_cast<unsigned>(std::string::npos)) const  
*Return name of row if one exists or Rnnnnnnn maxlen is currently ignored and only there to match the signature from the base class!*

- virtual std::string [getColName](#) (int colIndex, unsigned maxLen=static\_cast< unsigned >(std::string::npos)) const  
*Return name of column if one exists or Cnnnnnnn maxLen is currently ignored and only there to match the signature from the base class!*
- virtual const double \* [getColLower](#) () const  
*Get pointer to array[getNumCols()] of column lower bounds.*
- virtual const double \* [getColUpper](#) () const  
*Get pointer to array[getNumCols()] of column upper bounds.*
- virtual const char \* [getRowSense](#) () const  
*Get pointer to array[getNumRows()] of row constraint senses.*
- virtual const double \* [getRightHandSide](#) () const  
*Get pointer to array[getNumRows()] of rows right-hand sides.*
- virtual const double \* [getRowRange](#) () const  
*Get pointer to array[getNumRows()] of row ranges.*
- virtual const double \* [getRowLower](#) () const  
*Get pointer to array[getNumRows()] of row lower bounds.*
- virtual const double \* [getRowUpper](#) () const  
*Get pointer to array[getNumRows()] of row upper bounds.*
- virtual const double \* [getObjCoefficients](#) () const  
*Get pointer to array[getNumCols()] of objective function coefficients.*
- virtual double [getObjSense](#) () const  
*Get objective function sense (1 for min (default), -1 for max)*
- virtual bool [isContinuous](#) (int colNumber) const  
*Return true if column is continuous.*
- virtual bool [isBinary](#) (int colIndex) const  
*Return true if variable is binary.*
- virtual bool [isInteger](#) (int colIndex) const  
*Return true if column is integer.*
- virtual bool [isIntegerNonBinary](#) (int colIndex) const  
*Return true if variable is general integer.*
- virtual bool [isFreeBinary](#) (int colIndex) const  
*Return true if variable is binary and not fixed at either bound.*
- virtual const char \* [getColType](#) (bool refresh=false) const  
*Return array of column length 0 - continuous 1 - binary (may get fixed later) 2 - general integer (may get fixed later)*
- bool [isOptionalInteger](#) (int colIndex) const  
*Return true if column is integer but does not have to be declared as such.*
- void [setOptionalInteger](#) (int index)  
*Set the index-th variable to be an optional integer variable.*
- virtual const CoinPackedMatrix \* [getMatrixByRow](#) () const  
*Get pointer to row-wise copy of matrix.*
- virtual const CoinPackedMatrix \* [getMatrixByCol](#) () const  
*Get pointer to column-wise copy of matrix.*
- virtual CoinPackedMatrix \* [getMutableMatrixByCol](#) () const  
*Get pointer to mutable column-wise copy of matrix.*
- virtual double [getInfinity](#) () const  
*Get solver's value for infinity.*

## Methods related to querying the solution

- virtual const double \* [getColSolution](#) () const  
*Get pointer to array[getNumCols()] of primal solution vector.*
- virtual const double \* [getRowPrice](#) () const  
*Get pointer to array[getNumRows()] of dual prices.*
- virtual const double \* [getReducedCost](#) () const  
*Get a pointer to array[getNumCols()] of reduced costs.*
- virtual const double \* [getRowActivity](#) () const  
*Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector).*
- virtual double [getObjValue](#) () const  
*Get objective function value.*
- virtual int [getIterationCount](#) () const  
*Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver).*
- virtual std::vector< double \* > [getDualRays](#) (int maxNumRays, bool fullRay=false) const  
*Get as many dual rays as the solver can provide.*
- virtual std::vector< double \* > [getPrimalRays](#) (int maxNumRays) const  
*Get as many primal rays as the solver can provide.*

## Changing bounds on variables and constraints

- virtual void [setObjCoeff](#) (int elementIndex, double elementValue)  
*Set an objective function coefficient.*
- virtual void [setColLower](#) (int elementIndex, double elementValue)  
*Set a single column lower bound  
Use -DBL\_MAX for -infinity.*
- virtual void [setColUpper](#) (int elementIndex, double elementValue)  
*Set a single column upper bound  
Use DBL\_MAX for infinity.*
- virtual void [setColBounds](#) (int elementIndex, double lower, double upper)  
*Set a single column lower and upper bound.*
- virtual void [setColSetBounds](#) (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of columns simultaneously  
The default implementation just invokes [setColLower\(\)](#) and [setColUpper\(\)](#) over and over again.*
- virtual void [setRowLower](#) (int elementIndex, double elementValue)  
*Set a single row lower bound  
Use -DBL\_MAX for -infinity.*
- virtual void [setRowUpper](#) (int elementIndex, double elementValue)  
*Set a single row upper bound  
Use DBL\_MAX for infinity.*
- virtual void [setRowBounds](#) (int elementIndex, double lower, double upper)  
*Set a single row lower and upper bound.*
- virtual void [setRowType](#) (int index, char sense, double rightHandSide, double range)  
*Set the type of a single row*

- virtual void [setRowSetBounds](#) (const int \*indexFirst, const int \*indexLast, const double \*boundList)  
*Set the bounds on a number of rows simultaneously*  
*The default implementation just invokes [setRowLower\(\)](#) and [setRowUpper\(\)](#) over and over again.*
- virtual void [setRowSetTypes](#) (const int \*indexFirst, const int \*indexLast, const char \*senseList, const double \*rhsList, const double \*rangeList)  
*Set the type of a number of rows simultaneously*  
*The default implementation just invokes [setRowType\(\)](#) over and over again.*
- virtual void [setObjective](#) (const double \*array)  
*Set the objective coefficients for all columns array [[getNumCols\(\)](#)] is an array of values for the objective.*
- virtual void [setColLower](#) (const double \*array)  
*Set the lower bounds for all columns array [[getNumCols\(\)](#)] is an array of values for the objective.*
- virtual void [setColUpper](#) (const double \*array)  
*Set the upper bounds for all columns array [[getNumCols\(\)](#)] is an array of values for the objective.*
- virtual void [setRowName](#) (int rowIndex, std::string name)  
*Set name of row.*
- virtual void [setColName](#) (int colIndex, std::string name)  
*Set name of column.*

#### Integrality related changing methods

- virtual void [setContinuous](#) (int index)  
*Set the index-th variable to be a continuous variable.*
- virtual void [setInteger](#) (int index)  
*Set the index-th variable to be an integer variable.*
- virtual void [setContinuous](#) (const int \*indices, int len)  
*Set the variables listed in indices (which is of length len) to be continuous variables.*
- virtual void [setInteger](#) (const int \*indices, int len)  
*Set the variables listed in indices (which is of length len) to be integer variables.*
- int [numberSOS](#) () const  
*Number of SOS sets.*
- const CoinSet \* [setInfo](#) () const  
*SOS set info.*
- virtual int [findIntegersAndSOS](#) (bool justCount)  
*Identify integer variables and SOS and create corresponding objects.*

#### Methods to expand a problem.<br>

*Note that if a column is added then by default it will correspond to a continuous variable.*

- virtual void [addCol](#) (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj)
- virtual void [addCol](#) (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj, std::string name)  
*Add a named column (primal variable) to the problem.*

- virtual void [addCol](#) (int numberElements, const int \*rows, const double \*elements, const double collb, const double colub, const double obj)  
*Add a column (primal variable) to the problem.*
- virtual void [addCol](#) (int numberElements, const int \*rows, const double \*elements, const double collb, const double colub, const double obj, std::string name)  
*Add a named column (primal variable) to the problem.*
- virtual void **addCols** (const int numcols, const CoinPackedVectorBase \*const \*cols, const double \*collb, const double \*colub, const double \*obj)
- virtual void **addCols** (const int numcols, const int \*columnStarts, const int \*rows, const double \*elements, const double \*collb, const double \*colub, const double \*obj)
- virtual void **deleteCols** (const int num, const int \*colIndices)
- virtual void **addRow** (const CoinPackedVectorBase &vec, const double rowlb, const double rowub)
- virtual void [addRow](#) (const CoinPackedVectorBase &vec, const double rowlb, const double rowub, std::string name)  
*Add a named row (constraint) to the problem.*
- virtual void **addRow** (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)
- virtual void [addRow](#) (int numberElements, const int \*columns, const double \*element, const double rowlb, const double rowub)  
*Add a row (constraint) to the problem.*
- virtual void [addRow](#) (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng, std::string name)  
*Add a named row (constraint) to the problem.*
- virtual void **addRows** (const int numRows, const CoinPackedVectorBase \*const \*rows, const double \*rowlb, const double \*rowub)
- virtual void **addRows** (const int numRows, const CoinPackedVectorBase \*const \*rows, const char \*rowsen, const double \*rowrhs, const double \*rowrng)
- virtual void **addRows** (const int numRows, const int \*rowStarts, const int \*columns, const double \*element, const double \*rowlb, const double \*rowub)
- void **modifyCoefficient** (int row, int column, double newElement, bool keepZero=false)
  
- virtual void **deleteRows** (const int num, const int \*rowIndices)
- virtual void [saveBaseModel](#) ()  
*If solver wants it can save a copy of "base" (continuous) model here.*
- virtual void [restoreBaseModel](#) (int numberRows)  
*Strip off rows to get to this number of rows.*
- virtual void [applyRowCuts](#) (int numberCuts, const OsiRowCut \*cuts)  
*Apply a collection of row cuts which are all effective.*
- virtual void [applyRowCuts](#) (int numberCuts, const OsiRowCut \*\*cuts)  
*Apply a collection of row cuts which are all effective.*
- virtual ApplyCutsReturnCode [applyCuts](#) (const OsiCuts &cs, double effectivenessLb=0.0)  
*Apply a collection of cuts.*

#### Methods to input a problem

- virtual void [loadProblem](#) (const CoinPackedMatrix &matrix, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub)

*Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).*

- virtual void [assignProblem](#) (CoinPackedMatrix \*&matrix, double \*&collb, double \*&colub, double \*&obj, double \*&rowlb, double \*&rowub)

*Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).*

- virtual void [loadProblem](#) (const CoinPackedMatrix &matrix, const double \*collb, const double \*colub, const double \*obj, const char \*rowsen, const double \*rowrhs, const double \*rowrng)

*Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).*

- virtual void [assignProblem](#) (CoinPackedMatrix \*&matrix, double \*&collb, double \*&colub, double \*&obj, char \*&rowsen, double \*&rowrhs, double \*&rowrng)

*Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).*

- virtual void [loadProblem](#) (const int numcols, const int numRows, const CoinBigIndex \*start, const int \*index, const double \*value, const double \*collb, const double \*colub, const double \*obj, const double \*rowlb, const double \*rowub)

*Just like the other [loadProblem\(\)](#) methods except that the matrix is given in a standard column major ordered format (without gaps).*

- virtual void [loadProblem](#) (const int numcols, const int numRows, const CoinBigIndex \*start, const int \*index, const double \*value, const double \*collb, const double \*colub, const double \*obj, const char \*rowsen, const double \*rowrhs, const double \*rowrng)

*Just like the other [loadProblem\(\)](#) methods except that the matrix is given in a standard column major ordered format (without gaps).*

- virtual int [loadFromCoinModel](#) (CoinModel &modelObject, bool keepSolution=false)

*This loads a model from a coinModel object - returns number of errors.*

- virtual int [readMps](#) (const char \*filename, const char \*extension="mps")

*Read an mps file from the given filename (defaults to Osi reader) - returns number of errors (see OsiMpsReader class)*

- int [readMps](#) (const char \*filename, bool keepNames, bool allowErrors)

*Read an mps file from the given filename returns number of errors (see OsiMpsReader class)*

- virtual int [readMps](#) (const char \*filename, const char \*extension, int &numberSets, CoinSet \*\*&sets)

*Read an mps file.*

- virtual void [writeMps](#) (const char \*filename, const char \*extension="mps", double objSense=0.0) const

*Write the problem into an mps file of the given filename.*

- virtual int [writeMpsNative](#) (const char \*filename, const char \*\*rowNames, const char \*\*columnNames, int formatType=0, int numberAcross=2, double objSense=0.0) const

*Write the problem into an mps file of the given filename, names may be null.*

- virtual int [readLp](#) (const char \*filename, const double epsilon=1e-5)

*Read file in LP format (with names)*

- virtual void [writeLp](#) (const char \*filename, const char \*extension="lp", double epsilon=1e-5, int numberAcross=10, int decimals=5, double objSense=0.0, bool useRowNames=true) const  
*Write the problem into an Lp file of the given filename.*
- virtual void [writeLp](#) (FILE \*fp, double epsilon=1e-5, int numberAcross=10, int decimals=5, double objSense=0.0, bool useRowNames=true) const  
*Write the problem into the file pointed to by the parameter fp.*
- virtual void [replaceMatrixOptional](#) (const CoinPackedMatrix &matrix)  
*I (JJF) am getting annoyed because I can't just replace a matrix.*
- virtual void [replaceMatrix](#) (const CoinPackedMatrix &matrix)  
*And if it does matter (not used at present)*

Message handling (extra for Clp messages).

Normally I presume you would want the same language.

If not then you could use underlying model pointer

- virtual void [passInMessageHandler](#) (CoinMessageHandler \*handler)  
*Pass in a message handler.*
- void [newLanguage](#) (CoinMessages::Language language)  
*Set language.*
- void [setLanguage](#) (CoinMessages::Language language)
- void [setLogLevel](#) (int value)  
*Set log level (will also set underlying solver's log level)*
- void [generateCpp](#) (FILE \*fp)  
*Create C++ lines to get to current state.*

#### Clp specific public interfaces

- [ClpSimplex](#) \* [getModelPtr](#) () const  
*Get pointer to Clp model.*
- [ClpSimplex](#) \* [swapModelPtr](#) ([ClpSimplex](#) \*newModel)  
*Set pointer to Clp model and return old.*
- unsigned int [specialOptions](#) () const  
*Get special options.*
- void [setSpecialOptions](#) (unsigned int value)
- int [lastAlgorithm](#) () const  
*Last algorithm used , 1 = primal, 2 = dual other unknown.*
- void [setLastAlgorithm](#) (int value)  
*Set last algorithm used , 1 = primal, 2 = dual other unknown.*
- int [cleanupScaling](#) () const  
*Get scaling action option.*
- void [setCleanupScaling](#) (int value)  
*Set Scaling option When scaling is on it is possible that the scaled problem is feasible but the unscaled is not.*
- double [smallestElementInCut](#) () const  
*Get smallest allowed element in cut.*
- void [setSmallestElementInCut](#) (double value)  
*Set smallest allowed element in cut.*

- double [smallestChangeInCut](#) () const  
*Get smallest change in cut.*
- void [setSmallestChangeInCut](#) (double value)  
*Set smallest change in cut.*
- void [setSolveOptions](#) (const [ClpSolve](#) &options)  
*Pass in initial solve options.*
- virtual int [tightenBounds](#) (int lightweight=0)  
*Tighten bounds - lightweight or very lightweight 0 - normal, 1 lightweight but just integers, 2 lightweight and all.*
- virtual CoinBigIndex [getSizeL](#) () const  
*Return number of entries in L part of current factorization.*
- virtual CoinBigIndex [getSizeU](#) () const  
*Return number of entries in U part of current factorization.*
- const [OsiClpDisasterHandler](#) \* [disasterHandler](#) () const  
*Get disaster handler.*
- void [passInDisasterHandler](#) ([OsiClpDisasterHandler](#) \*handler)  
*Pass in disaster handler.*
- [ClpLinearObjective](#) \* [fakeObjective](#) () const  
*Get fake objective.*
- void [setFakeObjective](#) ([ClpLinearObjective](#) \*fakeObjective)  
*Set fake objective (and take ownership)*
- void [setFakeObjective](#) (double \*fakeObjective)  
*Set fake objective.*
- void [setUpForRepeatedUse](#) (int senseOfAdventure=0, int printOut=0)  
*Set up solver for repeated use by Osi interface.*
- virtual void [synchronizeModel](#) ()  
*Synchronize model (really if no cuts in tree)*
- void [setSpecialOptionsMutable](#) (unsigned int value) const  
*Set special options in underlying clp solver.*

#### Constructors and destructors

- [OsiClpSolverInterface](#) ()  
*Default Constructor.*
- virtual [OsiSolverInterface](#) \* [clone](#) (bool copyData=true) const  
*Clone.*
- [OsiClpSolverInterface](#) (const [OsiClpSolverInterface](#) &)  
*Copy constructor.*
- [OsiClpSolverInterface](#) ([ClpSimplex](#) \*rhs, bool reallyOwn=false)  
*Borrow constructor - only delete one copy.*
- void [releaseClp](#) ()  
*Releases so won't error.*
- [OsiClpSolverInterface](#) & [operator=](#) (const [OsiClpSolverInterface](#) &rhs)  
*Assignment operator.*
- virtual [~OsiClpSolverInterface](#) ()  
*Destructor.*
- virtual void [reset](#) ()  
*Resets as if default constructor.*

## Protected Attributes

## Protected member data

- [ClpSimplex](#) \* [modelPtr\\_](#)  
*Clp model represented by this class instance.*

## Cached information derived from the OSL model

- char \* [rowsense\\_](#)  
*Pointer to dense vector of row sense indicators.*
- double \* [rhs\\_](#)  
*Pointer to dense vector of row right-hand side values.*
- double \* [rowrange\\_](#)  
*Pointer to dense vector of slack upper bounds for range constraints (undefined for non-range rows)*
- CoinWarmStartBasis \* [ws\\_](#)  
*A pointer to the warmstart information to be used in the hotstarts.*
- double \* [rowActivity\\_](#)  
*also save row and column information for hot starts only used in hotstarts so can be casual*
- double \* [columnActivity\\_](#)
- [ClpNodeStuff](#) [stuff\\_](#)  
*Stuff for fast dual.*
- int [numberSOS\\_](#)  
*Number of SOS sets.*
- CoinSet \* [setInfo\\_](#)  
*SOS set info.*
- [ClpSimplex](#) \* [smallModel\\_](#)  
*Alternate model (hot starts) - but also could be permanent and used for crunch.*
- [ClpFactorization](#) \* [factorization\\_](#)  
*factorization for hot starts*
- double [smallestElementInCut\\_](#)  
*Smallest allowed element in cut.*
- double [smallestChangeInCut\\_](#)  
*Smallest change in cut.*
- double [largestAway\\_](#)  
*Largest amount continuous away from bound.*
- char \* [spareArrays\\_](#)  
*Arrays for hot starts.*
- CoinWarmStartBasis [basis\\_](#)  
*Warmstart information to be used in resolves.*
- int [itlimOrig\\_](#)  
*The original iteration limit before hotstarts started.*
- int [lastAlgorithm\\_](#)  
*Last algorithm used.*
- bool [notOwned\\_](#)  
*To say if destructor should delete underlying model.*
- CoinPackedMatrix \* [matrixByRow\\_](#)

- Pointer to row-wise copy of problem matrix coefficients.*
- CoinPackedMatrix \* [matrixByRowAtContinuous\\_](#)
  - Pointer to row-wise copy of continuous problem matrix coefficients.*
- char \* [integerInformation\\_](#)
  - Pointer to integer information.*
- int \* [whichRange\\_](#)
  - Pointer to variables for which we want range information The number is in [0] memory is not owned by OsiClp.*
- bool [fakeMinInSimplex\\_](#)
  - Faking min to get proper dual solution signs in simplex API.*
- double \* [linearObjective\\_](#)
  - Linear objective.*
- [ClpDataSave](#) [saveData\\_](#)
  - To save data in OsiSimplex stuff.*
- [ClpSolve](#) [solveOptions\\_](#)
  - Options for initialSolve.*
- int [cleanupScaling\\_](#)
  - Scaling option When scaling is on it is possible that the scaled problem is feasible but the unscaled is not.*
- unsigned int [specialOptions\\_](#)
  - Special options 0x80000000 off 0 simple stuff for branch and bound 1 try and keep work regions as much as possible 2 do not use any perturbation 4 allow exit before re-factorization 8 try and re-use factorization if no cuts 16 use standard strong branching rather than clp's 32 Just go to first factorization in fast dual 64 try and tighten bounds in crunch 128 Model will only change in column bounds 256 Clean up model before hot start 512 Give user direct access to Clp regions in getBlncvARow etc (i.e., do not unscale, and do not return result in getBlncv parameters; you have to know where to look for the answer) 1024 Don't "borrow" model in initialSolve 2048 Don't crunch 4096 quick check for optimality Bits above 8192 give where called from in Cbc At present 0 is normal, 1 doing fast hotstarts, 2 is can do quick check 65536 Keep simple i.e.*
- [ClpSimplex](#) \* [baseModel\\_](#)
  - Copy of model when option 131072 set.*
- int [lastNumberRows\\_](#)
  - Number of rows when last "scaled".*
- [ClpSimplex](#) \* [continuousModel\\_](#)
  - Continuous model.*
- [OsiClpDisasterHandler](#) \* [disasterHandler\\_](#)
  - Possible disaster handler.*
- [ClpLinearObjective](#) \* [fakeObjective\\_](#)
  - Fake objective.*
- CoinDoubleArrayWithLength [rowScale\\_](#)
  - Row scale factors (has inverse at end)*
- CoinDoubleArrayWithLength [columnScale\\_](#)
  - Column scale factors (has inverse at end)*

#### Friends

- void [OsiClpSolverInterfaceUnitTest](#) (const std::string &mpsDir, const std::string &netlibDir)
  - A function that tests the methods in the [OsiClpSolverInterface](#) class.*

## Protected methods

- void [setBasis](#) (const CoinWarmStartBasis &basis)  
*Sets up working basis as a copy of input and puts in as basis.*
- void [setBasis](#) ()  
*Just puts current basis\_ into [ClpSimplex](#) model.*
- CoinWarmStartDiff \* [getBasisDiff](#) (const unsigned char \*statusArray) const  
*Warm start difference from basis\_ to statusArray.*
- CoinWarmStartBasis \* [getBasis](#) (const unsigned char \*statusArray) const  
*Warm start from statusArray.*
- void [deleteScaleFactors](#) ()  
*Delete all scale factor stuff and reset option.*
- const double \* [upRange](#) () const  
*If doing fast hot start then ranges are computed.*
- const double \* [downRange](#) () const
- void [passInRanges](#) (int \*array)  
*Pass in range array.*
- void [setSOSData](#) (int numberSOS, const char \*type, const int \*start, const int \*indices, const double \*weights=NULL)  
*Pass in sos stuff from AMPL.*
- void [computeLargestAway](#) ()  
*Compute largest amount any at continuous away from bound.*
- double [largestAway](#) () const  
*Get largest amount continuous away from bound.*
- void [setLargestAway](#) (double value)  
*Set largest amount continuous away from bound.*
- void [lexSolve](#) ()  
*Sort of lexicographic resolve.*
- virtual void [applyRowCut](#) (const OsiRowCut &rc)  
*Apply a row cut (append to constraint matrix).*
- virtual void [applyColCut](#) (const OsiColCut &cc)  
*Apply a column cut (adjust one or more bounds).*
- void [gutsOfDestructor](#) ()  
*The real work of a copy constructor (used by copy and assignment)*
- void [freeCachedResults](#) () const  
*Deletes all mutable stuff.*
- void [freeCachedResults0](#) () const  
*Deletes all mutable stuff for row ranges etc.*
- void [freeCachedResults1](#) () const  
*Deletes all mutable stuff for matrix etc.*
- void [extractSenseRhsRange](#) () const  
*A method that fills up the rowsense\_, rhs\_ and rowrange\_ arrays.*
- void [fillParamMaps](#) ()
- CoinWarmStartBasis [getBasis](#) ([ClpSimplex](#) \*model) const

*Warm start.*

- void [setBasis](#) (const CoinWarmStartBasis &basis, [ClpSimplex](#) \*model)

*Sets up working basis as a copy of input.*

- void [crunch](#) ()

*Crunch down problem a bit.*

- void [redoScaleFactors](#) (int numberOfRows, const CoinBigIndex \*starts, const int \*indices, const double \*elements)

*Extend scale factors.*

### 3.70.1 Detailed Description

Clp Solver Interface.

Instantiation of [OsiClpSolverInterface](#) for the Model Algorithm.

Definition at line 38 of file OsiClpSolverInterface.hpp.

### 3.70.2 Member Function Documentation

#### 3.70.2.1 virtual int OsiClpSolverInterface::canDoSimplexInterface ( ) const [virtual]

Simplex API capability.

Returns

- 0 if no simplex API
- 1 if can just do getBInv etc
- 2 if has all OsiSimplex methods

#### 3.70.2.2 virtual void OsiClpSolverInterface::enableFactorization ( ) const [virtual]

Enables simplex mode 1 (tableau access)

Tells solver that calls to getBInv etc are about to take place. Underlying code may need mutable as this may be called from CglCut::generateCuts which is const. If that is too horrific then each solver e.g. BCP or CBC will have to do something outside main loop.

#### 3.70.2.3 virtual bool OsiClpSolverInterface::basisIsAvailable ( ) const [virtual]

Returns true if a basis is available AND problem is optimal.

This should be used to see if the BInvARow type operations are possible and meaningful.

#### 3.70.2.4 virtual void OsiClpSolverInterface::getBasisStatus ( int \* cstat, int \* rstat ) const [virtual]

The following two methods may be replaced by the methods of OsiSolverInterface using OsiWarmStartBasis if: 1.

OsiWarmStartBasis resize operation is implemented more efficiently and 2. It is ensured that effects on the solver are the same

Returns a basis status of the structural/artificial variables At present as warm start i.e 0 free, 1 basic, 2 upper, 3 lower

NOTE artificials are treated as +1 elements so for  $\leq$  rhs artificial will be at lower bound if constraint is tight

This means that Clpsimplex flips artificials as it works in terms of row activities

**3.70.2.5** `virtual int OsiClpSolverInterface::setBasisStatus ( const int * cstat, const int * rstat )`  
[virtual]

Set the status of structural/artificial variables and factorize, update solution etc.

NOTE artificials are treated as +1 elements so for  $\leq$  rhs artificial will be at lower bound if constraint is tight

This means that Clpsimplex flips artificials as it works in terms of row activities Returns 0 if OK, 1 if problem is bad e.g. duplicate elements, too large ...

**3.70.2.6** `virtual void OsiClpSolverInterface::getBlvACol ( CoinIndexedVector * vec ) const`  
[virtual]

Update (i.e.

ffran) the vector passed in. Unscaling is applied after - can't be applied before

**3.70.2.7** `virtual void OsiClpSolverInterface::enableSimplexInterface ( bool doingPrimal )`  
[virtual]

Enables simplex mode 2 (individual pivot control)

This method is supposed to ensure that all typical things (like reduced costs, etc.) are updated when individual pivots are executed and can be queried by other methods.

**3.70.2.8** `virtual int OsiClpSolverInterface::pivot ( int colln, int colOut, int outStatus )`  
[virtual]

Perform a pivot by substituting a colln for colOut in the basis.

The status of the leaving variable is given in statOut. Where 1 is to upper bound, -1 to lower bound Return code is 0 for okay, 1 if inaccuracy forced re-factorization (should be okay) and -1 for singular factorization

**3.70.2.9** `virtual int OsiClpSolverInterface::primalPivotResult ( int colln, int sign, int & colOut, int & outStatus, double & t, CoinPackedVector * dx )` [virtual]

Obtain a result of the primal pivot Outputs: colOut -- leaving column, outStatus -- its status, t -- step size, and, if dx!=NULL, \*dx -- primal ray direction.

Inputs: colln -- entering column, sign -- direction of its change (+/-1). Both for colln and colOut, artificial variables are index by the negative of the row index minus 1. Return code (for now): 0 -- leaving variable found, -1 -- everything else? Clearly, more informative set of return values is required Primal and dual solutions are updated

**3.70.2.10** `virtual CoinWarmStart* OsiClpSolverInterface::getEmptyWarmStart ( ) const`  
`[virtual]`

Get an empty warm start object.

This routine returns an empty CoinWarmStartBasis object. Its purpose is to provide a way to give a client a warm start basis object of the appropriate type, which can be resized and modified as desired.

**3.70.2.11** `virtual bool OsiClpSolverInterface::setWarmStart ( const CoinWarmStart * warmstart`  
`) [virtual]`

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

**3.70.2.12** `virtual CoinWarmStart* OsiClpSolverInterface::getPointerToWarmStart ( bool &`  
`mustDelete ) [virtual]`

Get warm start information.

Return warm start information for the current state of the solver interface. If there is no valid warm start information, an empty warm start object will be returned. This does not necessarily create an object - may just point to one. mustDelete set true if user should delete returned object. OsiClp version always returns pointer and false.

**3.70.2.13** `virtual const char* OsiClpSolverInterface::getRowSense ( ) const` `[virtual]`

Get pointer to array[getNumRows()] of row constraint senses.

- 'L' <= constraint
- 'E' = constraint
- 'G' >= constraint
- 'R' ranged constraint
- 'N' free constraint

**3.70.2.14** `virtual const double* OsiClpSolverInterface::getRightHandSide ( ) const`  
`[virtual]`

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

**3.70.2.15** `virtual const double* OsiClpSolverInterface::getRowRange ( ) const`  
`[virtual]`

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] - rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is undefined

**3.70.2.16** `virtual bool OsiClpSolverInterface::isInteger ( int colIndex ) const` `[virtual]`

Return true if column is integer.

Note: This function returns true if the the column is binary or a general integer.

**3.70.2.17** `bool OsiClpSolverInterface::isOptionalInteger ( int colIndex ) const`

Return true if column is integer but does not have to be declared as such.

Note: This function returns true if the the column is binary or a general integer.

**3.70.2.18** `virtual int OsiClpSolverInterface::getIterationCount ( ) const` `[inline, virtual]`

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Definition at line 498 of file OsiClpSolverInterface.hpp.

**3.70.2.19** `virtual std::vector<double*> OsiClpSolverInterface::getDualRays ( int maxNumRays, bool fullRay = false ) const` `[virtual]`

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

**NOTE for implementers of solver interfaces:**

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

**NOTE for users of solver interfaces:**

It is the user's responsibility to free the double pointers in the vector using delete[].

**3.70.2.20** `virtual std::vector<double*> OsiClpSolverInterface::getPrimalRays ( int maxNumRays ) const` `[virtual]`

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

**NOTE for implementers of solver interfaces:**

The double pointers in the vector should point to arrays of length `getNumCols()` and they should be allocated via `new[]`.

**NOTE for users of solver interfaces:**

It is the user's responsibility to free the double pointers in the vector using `delete[]`.

**3.70.2.21** `virtual void OsiClpSolverInterface::setColLower ( int elementIndex, double elementValue ) [virtual]`

Set a single column lower bound

Use `-DBL_MAX` for -infinity.

**3.70.2.22** `virtual void OsiClpSolverInterface::setColUpper ( int elementIndex, double elementValue ) [virtual]`

Set a single column upper bound

Use `DBL_MAX` for infinity.

**3.70.2.23** `virtual void OsiClpSolverInterface::setColSetBounds ( const int * indexFirst, const int * indexLast, const double * boundList ) [virtual]`

Set the bounds on a number of columns simultaneously

The default implementation just invokes `setColLower()` and `setColUpper()` over and over again.

**Parameters**

|                   |  |
|-------------------|--|
| <i>indexFirst</i> | pointers to the beginning and after the end of the array of the indices of the variables whose <i>either</i> bound changes |
| <i>boundList</i>  | the new lower/upper bound pairs for the variables  |

**3.70.2.24** `virtual void OsiClpSolverInterface::setRowLower ( int elementIndex, double elementValue ) [virtual]`

Set a single row lower bound

Use `-DBL_MAX` for -infinity.

**3.70.2.25** `virtual void OsiClpSolverInterface::setRowUpper ( int elementIndex, double elementValue ) [virtual]`

Set a single row upper bound

Use `DBL_MAX` for infinity.

**3.70.2.26** `virtual void OsiClpSolverInterface::setRowSetBounds ( const int * indexFirst, const int * indexLast, const double * boundList ) [virtual]`

Set the bounds on a number of rows simultaneously

The default implementation just invokes [setRowLower\(\)](#) and [setRowUpper\(\)](#) over and over again.

#### Parameters

|                              |  |
|------------------------------|--|
| <i>indexFirst, indexLast</i> | pointers to the beginning and after the end of the array of the indices of the constraints whose <i>either</i> bound changes |
| <i>boundList</i>             | the new lower/upper bound pairs for the constraints  |

**3.70.2.27** `virtual void OsiClpSolverInterface::setRowSetTypes ( const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList )` [virtual]

Set the type of a number of rows simultaneously

The default implementation just invokes [setRowType\(\)](#) over and over again.

#### Parameters

|                              |   |
|------------------------------|---|
| <i>indexFirst, indexLast</i> | pointers to the beginning and after the end of the array of the indices of the constraints whose <i>any</i> characteristics changes |
| <i>senseList</i>             | the new senses  |
| <i>rhsList</i>               | the new right hand sides  |
| <i>rangeList</i>             | the new ranges  |

**3.70.2.28** `virtual void OsiClpSolverInterface::setObjective ( const double * array )` [virtual]

Set the objective coefficients for all columns array [\[getNumCols\(\)\]](#) is an array of values for the objective.

This defaults to a series of set operations and is here for speed.

**3.70.2.29** `virtual void OsiClpSolverInterface::setColLower ( const double * array )` [virtual]

Set the lower bounds for all columns array [\[getNumCols\(\)\]](#) is an array of values for the objective.

This defaults to a series of set operations and is here for speed.

**3.70.2.30** `virtual void OsiClpSolverInterface::setColUpper ( const double * array )` [virtual]

Set the upper bounds for all columns array [\[getNumCols\(\)\]](#) is an array of values for the objective.

This defaults to a series of set operations and is here for speed.

**3.70.2.31** `virtual int OsiClpSolverInterface::findIntegersAndSOS ( bool justCount )`  
`[virtual]`

Identify integer variables and SOS and create corresponding objects.

Record integer variables and create an OsiSimpleInteger object for each one. All existing OsiSimpleInteger objects will be destroyed. If the solver supports SOS then do the same for SOS. If justCount then no objects created and we just store numberIntegers\_. Returns number of SOS

**3.70.2.32** `virtual void OsiClpSolverInterface::setColSolution ( const double * colsol )`  
`[virtual]`

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

**3.70.2.33** `virtual void OsiClpSolverInterface::setRowPrice ( const double * rowprice )`  
`[virtual]`

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

**3.70.2.34** `virtual void OsiClpSolverInterface::addCol ( int numberElements, const int * rows,  
const double * elements, const double collb, const double colub, const double obj )`  
`[virtual]`

Add a column (primal variable) to the problem.

**3.70.2.35** `virtual void OsiClpSolverInterface::addRow ( const CoinPackedVectorBase & vec,  
const double rowlb, const double rowub, std::string name )` `[virtual]`

Add a named row (constraint) to the problem.

The default implementation adds the row, then changes the name. This can surely be made more efficient within an OsiXXX class.

**3.70.2.36** `virtual void OsiClpSolverInterface::addRow ( int numberElements, const int  
* columns, const double * element, const double rowlb, const double rowub )`  
`[virtual]`

Add a row (constraint) to the problem.

**3.70.2.37** `virtual void OsiClpSolverInterface::restoreBaseModel ( int numberOfRows )`  
`[virtual]`

Strip off rows to get to this number of rows.

If solver wants it can restore a copy of "base" (continuous) model here

**3.70.2.38** `virtual void OsiClpSolverInterface::applyRowCuts ( int numberOfCuts, const OsiRowCut  
 * cuts )` `[virtual]`

Apply a collection of row cuts which are all effective.

applyCuts seems to do one at a time which seems inefficient.

**3.70.2.39** `virtual void OsiClpSolverInterface::applyRowCuts ( int numberOfCuts, const OsiRowCut  
 ** cuts )` `[virtual]`

Apply a collection of row cuts which are all effective.

applyCuts seems to do one at a time which seems inefficient. This uses array of pointers

**3.70.2.40** `virtual ApplyCutsReturnCode OsiClpSolverInterface::applyCuts ( const OsiCuts & cs,  
 double effectivenessLb = 0.0 )` `[virtual]`

Apply a collection of cuts.

Only cuts which have an `effectiveness >= effectivenessLb` are applied.

- `ReturnCode.getNumineffective()` -- number of cuts which were not applied because they had an `effectiveness < effectivenessLb`
- `ReturnCode.getNuminconsistent()` -- number of invalid cuts
- `ReturnCode.getNuminconsistentWrtIntegerModel()` -- number of cuts that are invalid with respect to this integer model
- `ReturnCode.getNuminfeasible()` -- number of cuts that would make this integer model infeasible
- `ReturnCode.getNumApplied()` -- number of integer cuts which were applied to the integer model
- `cs.size() == getNumineffective() + getNuminconsistent() + getNuminconsistentWrtIntegerModel() + getNuminfeasible() + getNumApplied()`

**3.70.2.41** `virtual void OsiClpSolverInterface::loadProblem ( const CoinPackedMatrix & matrix,  
 const double * collb, const double * colub, const double * obj, const double *  
rowlb, const double * rowub )` `[virtual]`

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

If a pointer is NULL then the following values are the default:

- `colub`: all columns have upper bound infinity
- `collb`: all columns have lower bound 0
- `rowub`: all rows have upper bound infinity
- `rowlb`: all rows have lower bound -infinity
- `obj`: all variables have 0 objective coefficient

**3.70.2.42** `virtual void OsiClipSolverInterface::assignProblem ( CoinPackedMatrix * & matrix, double * & collb, double * & colub, double * & obj, double * & rowlb, double * & rowub ) [virtual]`

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

**WARNING:** The arguments passed to this method will be freed using the C++ `delete` and `delete[]` functions.

**3.70.2.43** `virtual void OsiClipSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * obj, const char * rowsen, const double * rowrhs, const double * rowrng ) [virtual]`

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

If a pointer is NULL then the following values are the default:

- `colub`: all columns have upper bound infinity
- `collb`: all columns have lower bound 0
- `obj`: all variables have 0 objective coefficient
- `rowsen`: all rows are  $\geq$
- `rowrhs`: all right hand sides are 0
- `rowrng`: 0 for the ranged rows

**3.70.2.44** `virtual void OsiClipSolverInterface::assignProblem ( CoinPackedMatrix * & matrix, double * & collb, double * & colub, double * & obj, char * & rowsen, double * & rowrhs, double * & rowrng ) [virtual]`

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

**WARNING:** The arguments passed to this method will be freed using the C++ `delete` and `delete[]` functions.

**3.70.2.45** `virtual void OsiClpSolverInterface::loadProblem ( const int numcols, const int numrows, const CoinBigIndex * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const double * rowlb, const double * rowub ) [virtual]`

Just like the other [loadProblem\(\)](#) methods except that the matrix is given in a standard column major ordered format (without gaps).

**3.70.2.46** `virtual void OsiClpSolverInterface::loadProblem ( const int numcols, const int numrows, const CoinBigIndex * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const char * rowSEN, const double * rowRHS, const double * rowRNG ) [virtual]`

Just like the other [loadProblem\(\)](#) methods except that the matrix is given in a standard column major ordered format (without gaps).

**3.70.2.47** `virtual void OsiClpSolverInterface::writeMps ( const char * filename, const char * extension = "mps", double objSense = 0.0 ) const [virtual]`

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

**3.70.2.48** `virtual int OsiClpSolverInterface::writeMpsNative ( const char * filename, const char ** rowNames, const char ** columnNames, int formatType = 0, int numberAcross = 2, double objSense = 0.0 ) const [virtual]`

Write the problem into an mps file of the given filename, names may be null.

formatType is 0 - normal 1 - extra accuracy 2 - IEEE hex (later)

Returns non-zero on I/O error

**3.70.2.49** `virtual void OsiClpSolverInterface::writeLp ( const char * filename, const char * extension = "lp", double epsilon = 1e-5, int numberAcross = 10, int decimals = 5, double objSense = 0.0, bool useRowNames = true ) const [virtual]`

Write the problem into an Lp file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants. This version calls writeLpNative with names

**3.70.2.50** `virtual void OsiClpSolverInterface::writeLp ( FILE * fp, double epsilon = 1e-5, int numberAcross = 10, int decimals = 5, double objSense = 0.0, bool useRowNames = true ) const [virtual]`

Write the problem into the file pointed to by the parameter fp.

Other parameters are similar to those of [writeLp\(\)](#) with first parameter filename.

**3.70.2.51** `virtual void OsiClpSolverInterface::replaceMatrixOptional ( const CoinPackedMatrix & matrix ) [virtual]`

I (JJF) am getting annoyed because I can't just replace a matrix.

The default behavior of this is do nothing so only use where that would not matter e.g. strengthening a matrix for MIP

**3.70.2.52** `virtual void OsiClpSolverInterface::passInMessageHandler ( CoinMessageHandler * handler ) [virtual]`

Pass in a message handler.

It is the client's responsibility to destroy a message handler installed by this routine; it will not be destroyed when the solver interface is destroyed.

**3.70.2.53** `void OsiClpSolverInterface::setCleanupScaling ( int value ) [inline]`

Set Scaling option When scaling is on it is possible that the scaled problem is feasible but the unscaled is not.

Clp returns a secondary status code to that effect. This option allows for a cleanup. If you use it I would suggest 1. This only affects actions when scaled optimal 0 - no action 1 - clean up using dual if primal infeasibility 2 - clean up using dual if dual infeasibility 3 - clean up using dual if primal or dual infeasibility 11,12,13 - as 1,2,3 but use primal

Definition at line 1035 of file OsiClpSolverInterface.hpp.

**3.70.2.54** `double OsiClpSolverInterface::smallestElementInCut ( ) const [inline]`

Get smallest allowed element in cut.

If smaller than this then ignored

Definition at line 1039 of file OsiClpSolverInterface.hpp.

**3.70.2.55** `void OsiClpSolverInterface::setSmallestElementInCut ( double value ) [inline]`

Set smallest allowed element in cut.

If smaller than this then ignored

Definition at line 1043 of file OsiClpSolverInterface.hpp.

**3.70.2.56** `double OsiClpSolverInterface::smallestChangeInCut ( ) const [inline]`

Get smallest change in cut.

If (upper-lower)\*element < this then element is taken out and cut relaxed. (upper-lower) is taken to be at least 1.0 and this is assumed >= smallestElementInCut\_

Definition at line 1051 of file OsiClpSolverInterface.hpp.

**3.70.2.57** `void OsiClpSolverInterface::setSmallestChangeInCut ( double value ) [inline]`

Set smallest change in cut.

If  $(\text{upper-lower}) * \text{element} < \text{this}$  then element is taken out and cut relaxed.  $(\text{upper-lower})$  is taken to be at least 1.0 and this is assumed  $\geq \text{smallestElementInCut\_}$

Definition at line 1059 of file OsiClpSolverInterface.hpp.

**3.70.2.58** `void OsiClpSolverInterface::setupForRepeatedUse ( int senseOfAdventure = 0, int printOut = 0 )`

Set up solver for repeated use by Osi interface.

The normal usage does things like keeping factorization around so can be used. Will also do things like keep scaling and row copy of matrix if matrix does not change.

*senseOfAdventure*:

- 0 - safe stuff as above
- 1 - will take more risks - if it does not work then bug which will be fixed
- 2 - don't bother doing most extreme termination checks e.g. don't bother re-factorizing if less than 20 iterations.
- 3 - Actually safer than 1 (mainly just keeps factorization)

*printOut*

- -1 always skip round common messages instead of doing some work
- 0 skip if normal defaults
- 1 leaves

**3.70.2.59** `void OsiClpSolverInterface::setSpecialOptionsMutable ( unsigned int value ) const`

Set special options in underlying clp solver.

Safe as const because [modelPtr\\_](#) is mutable.

**3.70.2.60** `virtual void OsiClpSolverInterface::applyRowCut ( const OsiRowCut & rc )`  
[protected, virtual]

Apply a row cut (append to constraint matrix).

**3.70.2.61** `virtual void OsiClpSolverInterface::applyColCut ( const OsiColCut & cc )`  
[protected, virtual]

Apply a column cut (adjust one or more bounds).

**3.70.2.62** `CoinWarmStartBasis OsiClpSolverInterface::getBasis ( ClpSimplex * model ) const`  
[protected]

Warm start.

NOTE artificials are treated as +1 elements so for  $\leq$  rhs artificial will be at lower bound if constraint is tight

This means that Clpsimplex flips artificials as it works in terms of row activities

**3.70.2.63** void OsiClpSolverInterface::setBasis ( const CoinWarmStartBasis & *basis*,  
ClpSimplex \* *model* ) [protected]

Sets up working basis as a copy of input.

NOTE artificials are treated as +1 elements so for  $\leq$  rhs artificial will be at lower bound if constraint is tight

This means that Clpsimplex flips artificials as it works in terms of row activities

### 3.70.3 Friends And Related Function Documentation

**3.70.3.1** void OsiClpSolverInterfaceUnitTest ( const std::string & *mpsDir*, const std::string & *netlibDir* ) [friend]

A function that tests the methods in the [OsiClpSolverInterface](#) class.

### 3.70.4 Member Data Documentation

**3.70.4.1** CoinWarmStartBasis\* OsiClpSolverInterface::ws\_ [mutable,  
protected]

A pointer to the warmstart information to be used in the hotstarts.

This is NOT efficient and more thought should be given to it...

Definition at line 1257 of file OsiClpSolverInterface.hpp.

**3.70.4.2** double OsiClpSolverInterface::smallestElementInCut\_ [protected]

Smallest allowed element in cut.

If smaller than this then ignored

Definition at line 1274 of file OsiClpSolverInterface.hpp.

**3.70.4.3** double OsiClpSolverInterface::smallestChangelnCut\_ [protected]

Smallest change in cut.

If (upper-lower)\*element  $<$  this then element is taken out and cut relaxed.

Definition at line 1278 of file OsiClpSolverInterface.hpp.

**3.70.4.4** CoinWarmStartBasis OsiClpSolverInterface::basis\_ [protected]

Warmstart information to be used in resolves.

Definition at line 1284 of file OsiClpSolverInterface.hpp.

**3.70.4.5** int OsiClpSolverInterface::itlimOrig\_ [protected]

The original iteration limit before hotstarts started.

Definition at line 1286 of file OsiClpSolverInterface.hpp.

**3.70.4.6** `int OsiClpSolverInterface::lastAlgorithm_` [mutable, protected]

Last algorithm used.

Coded as

- 0 invalid
- 1 primal
- 2 dual
- -911 disaster in the algorithm that was attempted
- 999 current solution no longer optimal due to change in problem or basis

Definition at line 1298 of file OsiClpSolverInterface.hpp.

**3.70.4.7** `double* OsiClpSolverInterface::linearObjective_` [mutable, protected]

Linear objective.

Normally a pointer to the linear coefficient array in the clp objective. An independent copy when [fakeMinInSimplex\\_](#) is true, because we need something permanent to point to when [getObjCoefficients](#) is called.

Definition at line 1330 of file OsiClpSolverInterface.hpp.

**3.70.4.8** `int OsiClpSolverInterface::cleanupScaling_` [protected]

Scaling option When scaling is on it is possible that the scaled problem is feasible but the unscaled is not.

Clp returns a secondary status code to that effect. This option allows for a cleanup. If you use it I would suggest 1. This only affects actions when scaled optimal 0 - no action 1 - clean up using dual if primal infeasibility 2 - clean up using dual if dual infeasibility 3 - clean up using dual if primal or dual infeasibility 11,12,13 - as 1,2,3 but use primal

Definition at line 1348 of file OsiClpSolverInterface.hpp.

**3.70.4.9** `unsigned int OsiClpSolverInterface::specialOptions_` [mutable, protected]

Special options 0x80000000 off 0 simple stuff for branch and bound 1 try and keep work regions as much as possible 2 do not use any perturbation 4 allow exit before re-factorization 8 try and re-use factorization if no cuts 16 use standard strong branching rather than clp's 32 Just go to first factorization in fast dual 64 try and tighten bounds in crunch 128 Model will only change in column bounds 256 Clean up model before hot start 512 Give user direct access to Clp regions in getBlvARow etc (i.e., do not unscale, and do not return result in getBlv parameters; you have to know where to look for the answer) 1024 Don't "borrow" model in initialSolve 2048 Don't crunch 4096 quick check for optimality Bits above 8192 give where called from in Cbc At present 0 is normal, 1 doing fast hotstarts, 2 is can do quick check 65536 Keep simple i.e.

no crunch etc 131072 Try and keep scaling factors around 262144 Don't try and tighten bounds (funny global cuts) 524288 Fake objective and 0-1 1048576 Don't recompute ray after crunch 2097152

Definition at line 1376 of file OsiClpSolverInterface.hpp.

The documentation for this class was generated from the following file:

- OsiClpSolverInterface.hpp

### 3.71 Outfo Struct Reference

\*\*\*\*\* DATA to be moved into protected section of [ClpInterior](#)

```
#include <ClpInterior.hpp>
```

#### 3.71.1 Detailed Description

\*\*\*\*\* DATA to be moved into protected section of [ClpInterior](#)

Definition at line 35 of file ClpInterior.hpp.

The documentation for this struct was generated from the following file:

- ClpInterior.hpp